Computer Systems 1 Lecture 10

Arrays

Dr. John T. O'Donnell School of Computing Science University of Glasgow

Copyright ©2019 John T. O'Donnell

Topics

- Address arithmetic
- 2 Arrays
 - Representation
 - Allocation
 - Indexed addressing
- Array traversal and for loops
- 4 Example program ArrayMax
- 6 Programming tips

Why [R0]?

- So far, we have always been writing [R0] after constants or names
 - ► lea R2,39[R0]
 - ▶ load R3,xyz[R0]
 - store R4,total[R0]
- Why?
- This is part of a general and powerful technique called address arithmetic

Address arithmetic

- Every piece of data in the computer (in registers, or memory) is a word
- A word can represent several different kinds of data
 - ► So far, we've just been using integers
 - ▶ Represented with two's complement: $-2^{15}, \ldots, -1, 0, 1, 2, \ldots, 2^{15} 1$
- Now, we'll start doing computations with addresses too
- Addresses are unsigned numbers: 0, 1, 2, ..., 65535

What can you do with address arithmetic?

- Powerful data structures
 - Today: Arrays
 - Pointers and records
 - ► Linked lists, queues, dequeues, stacks, trees, graphs, hash tables, ... Subject of *Algorithms and Data Structures*
- Powerful control structures
 - ► Input/Output
 - Procedures and functions
 - Recursion
 - Case dispatch
 - Coroutines, classes, methods

Data structures

- An ordinary variable holds one value (e.g. an integer)
- A data structure can hold many individual elements
- A data structure is a container
- The simplest data structure: array
- There are many more data structures!
- The key idea: we will do arithmetic on addresses

Arrays

• In mathematics, an array (vector) is a sequence of indexed values

$$X_0, X_1, \ldots, X_{n-1}$$

- x is the entire array
- \triangleright x_3 is one specific element of the array with index 3
- It's useful to refer to an arbitrary element by using an integer variable as index: x_i
- Arrays are ubiquitous: used in all kinds of applications
- In programming languages, we refer to x_i as x[i]

Representing an array

- An array is represented in a computer by placing the elements in consecutive memory locations
- The array x starts in memory at some location: here, it's 01a5
- The address of the array x is the address of its first element x[0]
- The elements follow in consecutive locations

```
value x[0] x[1] x[2] x[3] x[4] x[5] x[6] address ... 01a5 01a6 01a7 01a8 01a9 01aa 01ab ...
```

The address of x[i] is x+i

- 4 ロ ト 4 昼 ト 4 夏 ト 4 夏 ト 9 Q (C)

Allocating an array

- An array is in memory along with other data after the trap that terminates the program
- You can allocate the elements and give them initial value with data statements
- Use the name of the array as a label on the first element (the one with index 0)
- Don't put labels on the other elements

Example of array allocation

```
. . .
```

```
RO, RO, RO; terminate
      trap
; Variables and arrays
abc
      data
               25
                           some variable
n
      data
                6
                          ; size of array x
      data
               13
                          : x[0]
X
                          : x[1]
      data
              189
              870
                         : x[2]
      data
                          ; x[3]
      data
               42
                          ; x[4]
      data
                0
      data
             1749
                          ; x[5]
```

def data 0 ; some other variable

What about big arrays?

- In the programs we'll work with, the arrays will be small (a dozen elements or so)
- In real scientific computing, it's common to have large arrays with thousands — or even millions — of elements
- It would be horrible to have to write thousands of data statements!
- In large scale software, arrays are allocated dynamically with help from the operating system
 - ► The user program calculates how large an array it wants, and stores that in a variable (e.g. n = 40000)
 - It uses a trap to request (from the operating system) a block of memory big enough to hold the array
 - The operating system returns the address of this block to the user program
- We won't be doing this: we will just allocate small arrays using data statements

Computer Systems 1 Arrays Lecture 10 11 / 37

Accessing an element of an array

- Suppose we have array x with elements x[0], x[1], ..., x[n-1]
- Elements are stored in consecutive memory locations
- Use the label x to refer to the array; x is also the location of x[0]
- The address of x[i] is x+i
- To do any calculations on x[i], we must load it into a register, or store a new value into it
- But how?
- If you try load R4,x[R0] the effect will be R4 := x[0]
- We need a way to access x[i] where i is a variable

Computer Systems 1

Effective address

- An RX instruction specifies addresses in two parts, for example result[R0] or x[R4] or \$00a5[R2]
 - ► The displacement is a 16 bit constant (you can write the number, or use a name the assembler will put in the address for you)
 - ► The index register is written in brackets
- The machine adds the displacement to the value in the index register
 - this is called the effective address
- The instruction is performed using the effective address

Computer Systems 1

Using the effective address

The addressing mechanism is flexible!

- You can access an ordinary variable:

 load R2,sum[R0]
 R0 always contains 0, so the effective address is just the address of sum
- You can access an array element: if R8 contains an index i, then load R2,x[R8]
 will load x[i] into R2
- There's more: effective addresses are used to implement pointers, functions, procedures, methods, classes, instances, jump tables, case dispatch, coroutines, records, interrupt vectors, lists, heaps, trees, forests, graphs, hash tables, activation records, stacks, queues, dequeues, . . .

Computer Systems 1 Arrays Lecture 10 14 / 37

Addressing modes

- An addressing mode is a scheme for specifying the address of data
- Sigma16 has one addressing mode: displacement[index], e.g. x[R4]
- Many older computers provided many addressing modes: one for variables, another for arrays, yet another for linked lists, still another for stacks, and so on
- It's more efficient to provide just one or two flexible addressing modes, rather than a big collection of them

Computer Systems 1

Using effective address for an array

Suppose we want to execute x[i] := x[i] + 50

```
lea R1,50[R0] ; R1 := 50
load R5,i[R0] ; R5 := i
load R6,x[R5] ; R6 := x[i]
add R6,R6,R1 ; R6 := x[i] + 50
store R6,x[R5] ; x[i] := x[i] + 50
```

Array traversal

- A typical operation on an array is to traverse it
- That means to perform a calculation on each element

Here's a loop that doubles each element of x:

```
i := 0;
while i < n do
    { x[i] := x[i] * 2;
        i := i + 1;
}</pre>
```

For loops

- A for loop is designed specifically for array traversal
- It handles the loop index automatically
- It sets the index to each array element index and executes the body
- The intuition is "do the body for every element of the array"

```
for i := exp1 to exp2 do
    { statements }
```

Array traversal with while and for

Here is the program that doubles each element of x, written with both constructs

Translating the for loop to low level

High level for loop (with any number of statements in the body)

```
for i := exp1 to exp2 do
    { statement1;
     statement2;
}
```

Translate to low level with this pattern:

```
i := exp1;
loop: if i > exp2 then goto loopdone;
statement1;
statement2;
i := i + 1;
goto loop;
```

loopdone:

It's straightforward to complete the translation to assembly language.

Alternative syntax for for loops

In languages derived from C (C++, Java, C#, and many more) you will see for loops written like this:

```
for (i=x; i<y; i++)
    { S1; }
S2;</pre>
```

Example program ArrayMax

- A complete programming example
- The problem: find the maximum element of an array
- To do this we need to
 - Allocate an array
 - Loop over the elements
 - Access each element
 - Perform a conditional
- This example puts all our techniques together into one program

State what the program does

```
; John O'Donnell
;;
; The program finds the maximum element of an array. It is given
; * a natural number n, assume n>0
; * an n-element array x[0], x[1], ..., x[n-1]
; and it calculates
; * max = the maximum element of x
; Since n>0, the array x contains at least one element, and a maximum
; element is guaranteed to exist.
```

Program ArrayMax

High level algorithm

Translate high level code to low level "goto form"

It's easier to check that this low level is equivalent to both the high level algorithm and the assembly language, rather than translating all the way to assembly language in one giant step.

```
; Low level algorithm
     max := x[0]
     i := 1
 forloop:
     if i \ge n then goto done
     if x[i] <= max then goto skip
     max := x[i]
 skip:
     i := i + 1
     goto forloop
 done:
     terminate
```

Specify how the registers are used

The program is written in the "register variable style".

```
; Assembly language

; Register usage
; R1 = constant 1
; R2 = n
; R3 = i
: R4 = max
```

Block of statements to initialise registers

```
; Initialise
    lea R1,1[R0] ; R1 = constant 1
    load R2,n[R0] ; R2 = n
; max := x[0]
    load R4,x[R0] ; R4 = max = x[0]
; i := 1
    lea R3,1[R0] ; R3 = i = 1
```

Beginning of loop

Body of loop: if-then

End of loop

Finish

Data definitions

```
; Data area
         data
n
         data
max
         data
                18
х
         data
         data
                21
         data
         data
                40
         data
                25
```

Programming tips

Standard idioms for common programming problems

A useful convention

- The instruction set is designed to be regular, and to follow consistent conventions
 - This makes programming easier
 - ▶ It also helps with the hardware design!
- For most instructions, the operands follow the pattern of an assignment statement: information goes right to left
 - Assignment statement: reg1 := reg2 + reg3
 - Add instruction: add R1,R2,R3
 - ▶ The two operands on the right (R2, R3) are added, and placed in the destination on the left (R1)
 - ► Load instruction: load R1,x[R0] means R1 := x
- An exception: store
 - ▶ store R1,x[R0] means x := R1: the information goes from left to right
 - ▶ Why? Doing it this way makes the digital circuit (the processor) a little bit faster

Programming tip: Copying one register to another

- Here's a useful tip a standard programming technique
- Sometimes you want to copy a value from one register to another
 - ▶ R3 := R12
- There's a standard way to do it:
 - ▶ add R3,R12,R0 ; R3 := R12
- The idea is that R12 + 0 = R12!
- Why do it this way? It's actually more efficient than providing a separate instruction just to copy the register!

Using load and store

- A common error is to confuse load and store
- The main points to remember:
 - We need to keep variables in memory (most of the time) because memory is big — there aren't enough registers to hold all your variables
 - ► The computer hardware can do arithmetic on data in registers, but it cannot do arithmetic on data in memory
 - Therefore, to do arithmetic on variables, you must
 - ① Copy the variables from memory to registers (load)
 - ② Do the arithmetic in the registers (add, sub, ...)
 - Opp the result from registers back to memory (store)

goto









https://xkcd.com/292/