ADMIN ESSENTIALS FOR TENANTS, USERS, AND SYSTEM TRANSCRIPT

L00 - INTRODUCTION AND AGENDA

L00A-PRES: Introduction and Agenda (05m:24s)

00:00-01:00
Hi. Welcome to the *Stellar Cyber Administration Essentials for Tenants, Users, and System* training module. I'm Paul Levasseur of the Stellar Cyber Enablement and Training teams. The lessons in this module cover concepts, configuration, and demonstrations on how to configure tenants in the Stellar Cyber Open XDR platform, user privilege with scopes and role-based access control, two-factor authentication, certificate management to secure access to the platform UI for on premises or cloud deployments, and to secure access to other platform components for all deployment types, custom-branded logos used for the platform UI and reports, mail server settings to trigger emails from Alerts as response actions to trigger emails within automated threat hunting playbooks and to create notifications to email recipients, and System Action Center.

01:00-02:00
The lessons in this module also cover how to create rules in System Action Center to trigger notifications for important events as well as how to validate the platform is ingesting data from configured sensors and connectors. The lessons in this module are for platform administrators and are highly beneficial for security operation center administrators as well. I hope you enjoy and happy learning!

In the *Stellar Cyber Essential Administration for Tenants, Users, and System* training module, we will cover the following lessons and demonstrations:

- Multi-tenant Concepts and Configuration. This lesson explains the concepts and configuration of tenants in the Stellar Cyber Open XDR platform. Along with this lesson, there is a demonstration of creating and configuring a tenant and a tenant admin user that logs into the UI for their tenants secured with two-factor authentication.

02:00-03:00

- User Management with Role-Based Access Control. This lesson explains the concepts and configuration of user management with role-based access control by configuring privilege profiles. Along with this lesson, there is a demonstration of how to configure privilege profiles and assign them to a user. The demonstration shows the differences for the user when logged in to the UI using a more restrictive privilege profile.
- User Management with Multi-Tenant Architecture. This lesson explains the concepts, configuration, and administration of users to provide access to tenants and tenant groups by assigning scopes and privilege profiles used to provide role-specific access with two-factor authentication used to secure access to the Stellar Cyber platform. This lesson also describes generating tokens for API access, viewing the user activity log for audit purposes, and how to view session connections from active users on the Stellar Cyber platform.

03:00-04:00

- Tenant Assignment for Stellar Cyber Tools, Connectors, and Sensors. This lesson provides an overview of how Stellar Cyber investigation tools can be assigned to tenants as well as configuration details for assigning tenants to Stellar Cyber connectors and sensors. Along with this lesson, there is a demonstration of assigning tenants to saved queries dashboards, ATH playbooks, connectors and sensors.
- User Login Experience to Stellar Cyber Open XDR platform with 2FA. This lesson provides an example of the login experience for users logging into the Stellar Cyber Open XDR platform UI with two FA which is two-factor authentication, certificate management for the Stellar Cyber platform. This lesson along with the accompanying lesson demonstration explained the concepts, commands, configuration and settings needed to generate TLS certificates for the Stellar Cyber platform, custom-branded logos for the Stellar Cyber platform UI and reports.

04:00-05:00

This lesson and accompanying demonstration explained how to configure custom-branded logos for the Stellar Cyber platform UI and reports as well as tenant-specific logos for reports.

- Mail Server Settings and Recipients for Email Notification from the Stellar Cyber Platform. This lesson explains how to configure the Stellar Cyber platform with mail server settings and recipients to send email notifications from tools such as Alerts, ATH playbooks, and System Action Center. Along with this lesson, there is a demonstration showing the setup process and examples of how to validate email notifications by using System Action Center.
- System Action Center for System Monitoring and Notifications. This lesson and accompanying lesson demonstration explains System Action Center and how it can be used to monitor the status of the Stellar Cyber platform, system, sensors,

connectors, and Case management, and provide email notifications based on configurable notification roles.

05:00-05:25

- Validating Stellar Cyber Platform Data Collection/Ingestion. This lesson is a demonstration of ways to validate the Stellar Cyber platform is ingesting data from data sources. The lessons in this module help platform and SOC administrators with administration tasks essential for a successful Stellar Cyber deployment.

L01 - MULTI-TENANT CONCEPTS AND CONFIG

L01A-PRES: Multi-Tenant Concepts and Config (19m:22s)

00:00-01:00

The first lesson in *Administration Essentials for Tenants, Users, and System* is *Multi-Tenant Concepts and Configuration*. This lesson, *Multi-Tenant Concepts and Configuration*, explains the concepts and configuration of tenants in the Open XDR platform.

Hi everyone. In this lesson, I will describe the multi-tenant concepts and configuration in Stellar Cyber's Open XDR architecture. Stellar Cyber is a truly multi-tenant platform that provides multi-tenant security architecture for data segregation and unique operational views for different organizations, more precise analytics and anomaly detections through per tenant machine learning with different patterns organization to organization

01:00-02:00

and multi-tier multi-tenancy, which allows wholesale managed services through partners or allows distributed control in multi-layer organizations. To give you an example, if you look at the picture on the right, well, think of that whole thing as the Stellar Cyber platform. Different organizations can segment their data either as an MSSP for their customers so each customer would have a separate tenant, or for large enterprises that want to segment sites or different organizations throughout the company. Tenants were designed for these two main cases to implement the MSSP (managed security service provider) business model, where the serving organization operates and manages Stellar Cyber and provides security monitoring to any number of client companies.

02:00-03:00

The individual client companies are tenants and Stellar Cyber sees each company as a unique and separate entity with its own machine learning and its own data. We can even provide operational views into specific tenants. More on this to come. For larger organizations, multi-tenancy allows the delegation of security functions to subordinate departments. For example, a company with offices in different regions can assign each

branch its own Stellar Cyber tenant. The home office operates and manages the data processor, which is the Stellar Cyber platform, leaving the branches to focus locally. Looking at this picture I will start with the middle. The Stellar Cyber Open XDR architecture has quite a few components. It has the Stellar Cyber Open XDR platform. It has on the left starting with Modular Sensors.

03:00-04:00

The Modular Sensors have access to local security and identity infrastructure systems tools and services. They can connect either using connectors, or they can be off SPAN ports to collect network traffic, or they can receive logs from any of the security tools within the internal infrastructure. That information gets forwarded to the Stellar Cyber platform. Along with that there are Windows server sensors, and there are Linux Server sensors as well. Each of these sensors report back to the Stellar Cyber platform. Now for SaaS deployments, the very first thing that a platform administrator must do is actually create their first tenant. In this example, if this was an MSSP, I would create an MSSP tenant for my organization name. Then I would have my Modular Sensors assigned to that tenant.

04:00-05:00

I would have my Windows Server sensors tied to that tenant and I'd have my Linux Server sensors tied to this tenant. All those internal services that I'm running within my organization would be in the one tenant, which is for my organization itself, which is the MSSP. My other tenants would be for my customers. I could create another tenant called Customer1, and Customer1 would connect to the Modular Sensor at Customer1 site along with the Windows Server sensors and Linux Server sensors. That allows me to have access to all those security tools within the organization to collect data. All the data for the Customer1 tenant remains in Customer1. The machine learning also stays in the Customer1 tenant. For example, some of the machine learning is unsupervised, where it's going to learn the behavior of users.

05:00-06:00

For example, their locations and where they log in and their frequency of log in. That information stays local because it's different for each customer, potentially. When Alerts are generated from that content, that also stays within the Customer1 tenant. A SOC analyst can view just that Customer1 data. Likewise I do the same thing for the Customer2. The other thing that each tenant has is a connector to cloud services. For example, each tenant can have a connector to cloud identity and infrastructure systems, tools, and services. For example if I have EDR forms in the cloud, AWS GuardDuty, CloudTrail, any of those systems that are running in the cloud, can run from connectors within the tenant as well.

06:00-07:00

Again, the data remains local for each tenant. Another example is an on premises or essentially a private cloud deployment of Stellar Cyber. The big difference here is that there is a root tenant by default, and the root tenant actually doesn't even have a tenant ID. It's just the main system. If I was an enterprise deploying on premises for example, the root tenant would be all I would need to have. Unless I do have a large organization where I want to separate tenants for different sites. If I was an MSSP, my root tenant might just be my local network from my own devices. But then I would still create separate tenants for different customers. That's really the difference. When I have a root tenant I don't need to have a tenant ID for the installation of Modular Sensors or Windows Server sensors or Linux Server sensors

07:00-08:00

because everything is going to the root tenant. However, I then can create separate tenants for my customers Customer1 and Customer2 in this case. Just like in the SaaS deployment, I can do exactly the same thing where I have all the data stored locally within the tenant. I have connectors assigned to the tenant and I have Modular Sensors, Windows Server sensors, and Linux Server sensors all again assigned to specific tenants. Tenants for Stellar Cyber platform SaaS deployments do not have a tenant by default. There is no root tenant. The platform admin is assigned to all tenants and must create tenants to configure and deploy Stellar Cyber sensors and connectors for the main organization and customers.

08:00-09:00

Look on the right-hand side when you log in before you have created a tenant, you will see that there is not even a tenant selector box on the upper right-hand side. After I create my first tenants, on the upper right-hand side next to the logged in username there's a tenant selection. In the tenant selection I can select all tenants, which gives me an overview of all my tenants in one place, or I can select individual tenants In the Stellar Cyber platform on premises deployments or private cloud deployments, the root tenant exists by default and there is no tenant selection for the user. Creating additional tenants is optional, but it is a best practice for managed security service providers, or MSSPs, who create tenants for each of their customers.

09:00-10:00

After creating the first tenant, the tenant selection menu appears next to the logged in username and it's set by default to all tenants. That's what you see on the right hand side here as well. You'll see that on the very top, there is no tenant selector before a tenant is created, but then after creating a tenant you do see it. To create a tenant, a platform administrator can go to **System | Tenants**. From there, select **Create**, then enter the following. First there's the tenant name. The tenant name of course should be descriptive. You don't actually have to use the real customer name if you're an MSSP. For example, some

users have fake names for their customers that they then reference internally so that if someone were to see the name of the customer that they have been managed, no one would be able to determine the real customer name.

10:00-11:00

The next thing you have is the contact name. This is the contact at the site. Then the contact email at the site as well, so at the customer site. The contact phone and the address are optional, but they are very handy. Next, there is the custom DHCP lease period toggle. This could be turned on to specify a custom DHCP lease period for this tenant. Stellar Cyber uses this period to release IP addresses from the asset IDs. This prevents the accumulation of multiple asset IDs for a single asset, which can happen if the IP address changes. If you do not enable this, Stellar Cyber uses the global DHCP lease period. By default, the global DHCP lease period is 72 hours, but you can override it here if necessary.

11:00-12:00

What's important to note here is that this does not affect an actual DHCP lease, but what it does is gives the platform an idea of when the DHCP lease will change. The Stellar Cyber platform will have a better idea of not associating multiple asset IDs because the IP address has changed. This next setting retention group is only visible if you have an on premises or cloud deployment. This is used to override the default retention setting for data. The default retention group for on premises deployments has hot traffic for 30 days of retention, hot logs for 60 days of retention, hot security for 180 days of retention, and hot signals for 180 of retention.

12:00-13:00

If there's a need to change this requirement, it can be changed here by changing the retention group. The platform administrator can create retention groups. The next option is the ingestion target. You can use this field to create a target ingestion limit for this tenant. The value you specify here is for your reference only and is not enforced. You then select **Next**. The next setting is the authentication method. Set to default for the tenant to use the same settings as the global authentication set in system administration settings. If you select this option, no further configuration steps are required.

13:00-14:00

Set this setting to local if the server is globally using SSO or a single sign on, but you want a specific tenant to use the local authentication from the Stellar Cyber server. If you select this option, no further configuration steps are required. You set the authentication method to SSO (SAML). If you want the tenant to use a different SSO than the global configuration or the default configuration is local, but the tenant wishes to use SSO. You should reference the documentation at docs at StellarCyber.ai for details on the SSO configuration. Next is the

two-factor authentication option. It is definitely recommended to set the option to require 2FA for the users under this tenant. Now there's a troubleshooting note I've added here for you.

14:00-15:00

If you cannot enable two-factor authentication in the tenant, and you see a message to contact your provider to enable this feature, this is because the platform administrator must go to system settings and set the two-factor authentication setting to at least optional. Two FA will be configured on the tenant and user levels. If the setting and system settings are set to off, the administrator will not be able to add 2FA to a tenant. To save the settings, select **Submit**. The new tenant will appear in the list of tenants. You may have to search for it depending on how many tenants you have. Here in my example, Customer1 was the tenant name, which is on the top. There's also a tenant ID.

15:00-16:00

The tenant ID will be important for configuring Modular Sensors, Windows Server sensors, or Linux sensors, and even connectors to assign them to this tenant. So having that tenant ID available will be handy. If you don't see the tenant ID column, I have an example later on showing you how to add it. You can adjust the tenant management table and columns to your preferences. Select the stack line icon, which some people call the hamburger icon, and select auto size all columns. You can adjust the columns displayed by selecting the columns button on the left-hand side for deployments of sensors and connectors as I was mentioning. In some cases the tenant ID is needed. You can display the ID columns to view the tenant ID and you can even drag it to the top as well so that you have it first in line or very close to the front.

16:00-17:00

Now that you've seen how to create tenants here I will give you an overview of tenant specific collections and settings in the Stellar Cyber platform. As I've mentioned, Interflow records and events collected from sensors and connectors do remain with an attendant. Saved queries are tenant specific as well. The saved queries that one tenant user creates cannot be seen by users of the other tenants. If I look at the upper right, You can create a saved query from the filters sidebar in the Stellar Cyber platform. There's an option to add a query. And when I create a query which is going to search the Stellar Cyber platform for Interflow records, I can assign a tenant and save that. Therefore, this query is only associated with a tenant.

17:00-18:00

If I'm a root admin for example, and I have access to all the tenants, I can decide which tenants would then have access to a particular query by assigning that query to a tenant. I

could build a query for all tenants as well. I also have custom dashboards that are tenant specific. I can again create dashboards that are for all tenants, but I can create dashboards for specific tenants as well. Again, inside of the dashboard configuration, there is a tenant selector where I can select the tenant name. If I create a dashboard within a tenant as a tenant administrator, I will only have access to my single tenant in this selector.

18:00-19:00
Likewise, in the **Respond | Automation** (ATH playbooks) they are configured to run on all tenants, groups of tenants, or specific tenants, as you can see on the picture on the top right. This is the start of a configuration for automated threat hunting playbooks. One of the options is tenants. And here I can select multiple tenants where this ATH playbook can be run. Sensors are assigned to a tenant as well. When they generate Interflow records they are keyed to the tenant to which they belong. If you look at the bottom left is the sensor configuration. Inside the sensor configuration there's a tenant name where I can specify a tenant. You also specify a tenant during the installation process. And I will explain that as well in another lesson. Connectors are assigned to a tenant. If we take a look here at the bottom right, these are also assigned to a tenant and this will also be explained in more detail in another lesson.

19:00-19:05
Okay. Well that is it for the *Multi-Tenant Concepts and Configuration in the Stellar Cyber Open XDR Platform*. Thank you for watching. I hope to see you again in other lessons.

This lesson is complete. Thank you for watching.

L01B-DEMO: Multi-Tenant Concepts and Config (16m:00s)

00:00-01:00
This lesson is a demonstration for the lesson *User Management with Role-Based Access Control*. This lesson continues with a demonstration of creating a tenant and a tenant admin to access the tenant.

Hi everyone. In this lesson I will demonstrate how to create tenants and provide an overview of the use of tenants in the Stellar Cyber platform. To begin, I'm going to log in as a super admin. I'll have access to everything on the platform. The account I'm using is my paull-admin account. You really should not share admin accounts by the way. Everyone should have their own. The main reason you'll see in a minute, if I go to my password.

01:00-02:00
Here I'm asked for my two-factor authentication. I'm using Google Authenticator myself, but you can use Authy, the Microsoft Authenticator, OKTA Verify, or any of the standard

authenticator apps that you might have on mobile devices. I'll type in my authenticator here: 380169. I'll verify and now I'm in the platform. This account is the super admin of the platform. This account as well as any other account when accessing Stellar Cyber should have two-factor authentication enabled. Now the first thing I'll show you is what I can see as an administrator in the root scope. I'll take a look at my account. I'll go to **System | Users**, and let me look for my paull-admin account.

02:00-03:00

If I go over here and select the pencil, I can see that I have the–let me zoom in here so you can see better–I have a user scope of root. I have API access already configured, and I have two-factor authentication enabled. My user privilege is super admin. I have super admin and a user scope of root. This is why I have access to everything on the platform. If I look at the top right, I have a tenant selection box. Let me go over here first and take a look. This is my account. Over here I have the tenants. I can select the tenants. By default, I can use all tenants or select an individual tenant, as well as the root tenant itself.

03:00-04:00

All Tenants means that I see all a combination of every tenant in one place. Whereas the root tenant I only see what's assigned specifically to the root. Here I'll select All Tenants for now. If I go to **Investigate | Threat Hunting** as an example, I'll see the data for all the tenants in one place. If I go ahead now and select another tenant, such as Customer2, you'll see that now I have less data. Here I've just installed a Windows Server sensor and a Modular Sensor in this tenant, but I don't have the switch configured yet. I have very little records here to see. I'll go back to my root tenant.

04:00-05:00

My root tenant is used to manage my lab network. Therefore, I do have a lot more records available here. Again, I can switch to all tenants. Now I can assign users to specific tenants. I can assign users specifically for Customer1. When they log in they only see Customer1 data or same for Customer2 and so forth. An MSSP, as an example, will create accounts for their customers that will give them access just to their specific customer data. They could have analyst accounts or they could have admin accounts. It all depends on the relationship and what the MSSP provides for the customer. I could do the same thing as an enterprise. Instead of having customer tenants, I might have just regional tenants. This is maybe my UK office, and this would be my Asia Pac office, and then I would have my South American and North American.

05:00-06:00

You have your choice on how you want to use tenants. It all depends on how you want to delegate administrative access, or if you want to segment the data that you see along with

the machine learning for each of the tenants as well. Now to create a tenant, you just go to **System** and **Tenants**. It's a very simple process. Here I have my MSSP site that has Customer1 through Customer3 tenants. To create a tenant, I go over here and select **Create**. I start with a name. In this case, I will just say Customer4. I'll give a contact name, which in this case is me. I'll give a contact email, which is my lab's email. I'll give an email.

06:00-07:00

This should be the contact email for who is managing this tenant. I can put a phone in here as well. I'll just use a fake phone number. I could put a fake address: 50 Elm Street. I'll say San Jose, California. Now, the Enable Custom DHCP Lease. Here the lease period is for 48 hours, as an example. What this does is when the Stellar Cyber platform learns about assets, it will learn about a host on the network or an endpoint on the network. That endpoint has an IP address. If the endpoint gets a different IP address, we'll recognize that and create another endpoint as an asset with that new IP address.

07:00-08:00

Therefore, by default on the system, we will actually look at the DHCP lease time associated with that user. If the company's DHCP time is 48 hours, then we know that in 48 hours that asset could get a different IP address. Instead of creating a brand new asset and preserving that old IP address, we will then just replace that IP address for that asset. We know that it's not a new asset itself. Again, there's a global setting for this, but you can override it here for the specific tenant. If a tenant has a different DHCP lease period, you just want to find out what that is and add it here. There's also something called a Retention Group. You will only see the retention group if it's an on premises or cloud deployment. This specifies how long to keep the hot data as an example.

08:00-09:00

Then there's an Ingestion Target. For a tenant, you can say what they're expecting to see. Maybe this is what they have purchased. Maybe they've purchased 100 gigabytes of ingestion. Maybe you've specified that the customer can use 100 gigabytes of ingestion. This is just a marker so you have an idea. It is not used to enforce anything. It's just to visualize the ingestion target. You can go ahead and select **Next**. The first thing here is the authentication method. For the authentication method, this looks at whatever's configured at the global setting level in the Stellar Cyber platform. If the global settings, for example, use local authentication, which is essentially usernames and passwords stored in the platform...

09:00-10:00

...then I don't need to do anything. By default, this will use what the global setting is set to. If the global settings of the platform specify that the platform is using single sign on, or SSO

with SAML, then this default will use SSO with SAML. If you want to make the tenant different than what the global settings of the platform are using, I can override it here. Even if the platform is using SSO, I can specify that this tenant is using local. Or if the global settings of the platform are using local, I can decide to use SSO here. By default, it'll use whatever the platform has specified. The next thing is two-factor authentication. If you slide this on, that means all users under this tenant must use 2FA. There will be no option.

10:00-11:00

I will enable this option. Then all you have to do is **Submit**. Here I see the tenant and I have the Tenant ID column. If you don't have the Tenant ID column, I'll give you an example. I will remove this column. All you need to do is go to columns on the left side. You can search for ID. I can select it. I will hover over that and delete it. Now I have the ID column. There's this little grab box here. I can grab it and slide it to the top. I'll put it right after Name. I'll close the column here, and I will auto size all columns. Now I have the Tenant ID. This Tenant ID will be needed in the configuration of my sensors.

11:00-12:00

The Windows Server sensors, the Linux Server sensors, and the Modular Sensors, each will need this ID to assign this sensor to a tenant. If you don't have the ID, it can be done manually. But this makes it much easier if you do have it. By manually, I mean you can go to a sensor, edit the configuration of a sensor in the platform, and adjust the tenant. Okay. Next, I'll go to **Users**. Go over here to users and I will create a new user as well. I will call this user admin-customer4. If I'm on the SaaS platform, this will need to be an email address.

12:00-13:00

The Display Name, I will call it Admin Customer4. Again, this should be really someone's real name, but for now I'll just do this and then the password, put a strong password in here. I'm not making it super strong, so I can type it fast during these demos. I'll re-enter the password, but this is only a demo environment. I don't need to have any of this for now. I'll go ahead and specify that this is a tenant, and this tenant will have platform access, and the user will be assigned to Customer4. You'll see here that two factor is enabled. I cannot slide it off to disable it because at the tenant level I said this is mandatory. I'll go ahead now and select **Submit**. Oops. I am missing something. Do you see how this is grayed out right here?

13:00-14:00

You have to have the email address. Again, I will put admin-customer4@SClabs.ai. Now I can select **Submit**. Okay. I can now see my Customer4 account by using the filter. There it is. Now let me go ahead and exit out. Here I'll type in my name: admin-customer4. Select **Return**. The password is my secret password. What's that? Okay. Now I actually have to open up my Authenticator app and scan this code.

14:00-15:00
I'll go ahead and do that now. Let's see here. I will use Google Authenticator. Hit my little plus sign. I will scan the app. There we go. Now I will type in the pass I see, which is 960721. It's just that simple. I have a set of backup codes that I will copy and save to a secure place. I have a secure password manager. I'll add these two. I will read the agreement every line of it just to make sure that it is valid for my organization. And yep I'm a very fast reader, so that looks good to me.

15:00-16:00
I will accept. Now if you look right here, I am now in the Customer4 tenant, but you'll see I do not have a tenant selection. If I look over here to the right, I am in the Customer4 tenant. I don't see the fact that I have Customer4, but I'm in it. Now if I go to **System** and I go to **Sensors**, I don't have any sensors yet. If I go to **Investigate | Threat Hunting**, I don't have any data here yet because I don't have any sensors. You have to have sensors to collect data in the Stellar Cyber platform. But that just gives you an idea of the login experience. It's pretty simple. I will end this lesson here and see you in another lesson. This lesson is complete. Thank you for watching.

L02 - USER MANAGEMENT WITH ROLE-BASED ACCESS CONTROL

L02A-PRES: User Management with Role-Based Access Control (12m:05s)

00:00-01:00
The next lesson in *Administration Essentials for Tenants, Users, and System* is *User Management with Role-Based Access Control Using Privilege Profiles*. This lesson explains the concepts and configuration of user management with role-based access control by configuring privilege profiles.

Hi everyone. In this lesson I will cover user management with role-based access control, often called RBAC. You can use role-based access control to manage access to Stellar Cyber by assigning scopes and privileges to users. You assign user scope to specify which tenants the user can access. The options are Root, Partner, or Tenant. I will go into more details on these.

01:00-02:00

You assign the user privilege profiles to manage access to functions in the Stellar Cyber platform. I will go into more detail on both of these. Assign privilege based on role-based access control profiles to define the permissions the users have for features and functions within the Stellar Cyber platform. The default role-based access control privilege profiles include Super Admin, Platform Admin, Security Admin, and User. You assign the user privilege for a user to one of these profiles or a custom profile, which I'll talk about in a few moments. The best way to determine which profiles to use is to view the documentation.

02:00-03:00

Default RBAC privilege profiles are summarized in the documentation by going to docs.StellarCyber.ai and searching for role-based access control. If you scroll down in the document, you will find a table just like this. This table shows you the level of permissions each of the default privilege profiles have. For example, there's View Data Pages on the top left of the table. If there's a green checkbox, that means that privilege profile has full access. Here for View Data Pages, user has full access, security admin has full access, platform admin has full access, and super admin has full access. You keep on going through the list. The next one down is Global, which is Interflow actions, Alert filters, export running status. A user assigned to the user privilege profile would not have any access to those global functions.

03:00-04:00

The security admin has full access. The platform admin has full access and the super admin has full access. The next one in the line is Cases. For create and edit, a user has view only access only, and the rest of the profiles have full access. This is by default. We can create additional privilege profiles with different sets of permissions. As you go on through this table, we see that the user has the least privileges. Security admin has the second least. The platform admin right now has full permissions, but there's more to this table and the super admin has full permissions. Go on to the next page. There's also Respond and System. Here's where we see that the user and security admin and platform admin have restrictions for other respond actions in the system as well.

04:00-05:00

Any user that has super admin privileges can create, modify, or delete custom RBAC privilege profiles. To access role-based access control privilege profiles as a super admin, go to **System | Role-Based Access Control**. You'll see it there on the right-hand side. Based on the table in the documentation, for role-based access control privilege profiles, create additional profiles that meet your company needs. Now as an example, select **Security Admin**. Here if you look at the picture on the right, I'm within the Security Admin profile. I will select **Create New Profile from this Template**. If I want to go back to that previous page where that showed all the profiles, I can select **View Other Profiles**.

05:00-06:00
Next, you enter a name for the profile. I like to use the name of the profile that I inherited this profile from. Because I created this profile from Security Admin, I like to use security admin in the name. In this example, I am creating a security admin profile for my Stellar Cyber labs or SC labs. Hence, I have SCLABS Security Admin. The initial profile settings will be inherited from and it shows security admin, because that's what I selected to get here. Then the next case is behavior for new features and future releases. I'm going to choose **Inherit from Security Admin** at this point. I'll describe later what each of these options means.

06:00-07:00
Now, I'll go ahead and select **Save**. Now the first thing you see when you go into the new profile, is the very first line. It shows you the name of your profile. But it also shows you where you inherited this profile from. Here I can see that the profile was inherited from Security Admin. The other thing I can see is I have an option to create a new profile from this template or delete this profile. Now why would I want to create a new profile from this template? Well, the main reason is there are around 300 different options for configuring permissions. After I do that, I can create a new profile from this template, basically to create a backup, but also if there are some slight changes I want to make in the new profile, I can make those changes without having to adjust nearly 300 settings.

07:00-08:00
Okay. To enable a setting, you slide a box to the right. Next, if you want to enable an option or turn it on, you slide the lever to the right where it will turn green. You slide it to the left to turn that feature or function off, and the lever will turn gray. The top-level features for role-based access control include the Global settings, Cases, Alerts, Visualize, Investigate, Respond, and System. Then under each of those top-level feature categories are lots of other options. As I mentioned, there are approximately 300 privileges that can be enabled or disabled within a privilege profile.

08:00-09:00
For example, if I look at the privileges on the right, these are for enabling the ability to perform configuration options. Here, as an example, I can use queries. I can add queries, edit queries, but I can't delete queries. I can create recipients. I could add recipients, edit recipients, but I cannot delete recipients. There are scripts. I enable the **Saved Scripts** option. I can add saved scripts or edit saved scripts, but I cannot delete saved scripts. This is a pretty high-level user. But the goal here is to prevent a user from accidentally deleting some important options. The super admin will make sure of that. When you're all done with

your settings, you scroll to the bottom to decide the behavior to inherit for new features based on the profile this was inherited from.

09:00-10:00
For example, this profile was created from the Security Admin. If **Inherit from Security Admin** is selected, if a new feature is enabled in the security admin profile in the next release by our engineers, this profile will also have the feature enabled. You choose **Read-only** if you want to ensure users assigned to this profile will have read-only access to new features as they come out. You choose **No Access** if you want to ensure users assigned to this profile will not have access to new features until we go back in and modify it. Until the administrator goes back and modifies the profile. But in either case, the security admin can modify settings manually for new features within the profile to enable or disable for every release or anytime they see fit.

10:00-11:00
Select **Save Changes** when done. Even if done, a security admin and above can edit the profile to adjust settings as needed. Users will need to log out and log back into the platform for the changes to take effect. Users are assigned to a privilege profile by editing a user and changing the profile next to user privilege. Here you can see that I've assigned SCLab security admin as the user privilege for this user. Now here's an example of what it looks like. On the left-hand side top, if I look at the **Visualize** settings, you can see that all the levers are slid to the right, which means they're all on and they're all green.

11:00-12:05
If I log into the platform as a user with those privileges, I can see under the **Visualize** menu, I have all those same options available. Next, in this example, I have modified the privilege profile to minimize what I see in the **Visualize** menu. Here I have XDR Kill Chain enabled, Service Visibility enabled, and Network Visibility enabled. This profile is then assigned to the user. When the user logs into the Stellar Cyber platform, and they go to the **Visualize** menu, you can see here that only the XDR Kill Chain, the Network Visibility, and the Service Visibility are visible. That's based on the profile that's on the left. This works fantastically. As you can see there are many different possibilities for what you could do with role-based access control in the Stellar Cyber platform. I hope you enjoyed this lesson. I will see you in another lesson.

This lesson is complete. Thank you for watching.

L02B-DEMO: User Management with Role-Based Access Control (15m:56s)

00:00-01:00

This lesson is a demonstration for the lesson *User Management with Role-Based Access Control*. This lesson is a demonstration of user management by configuring users and assigning role-based access control privilege profiles and scope.

Hi everyone. In this lesson, I will cover user management with role-based access control privilege profiles. Now to begin, I am a super admin. I have access to everything on the platform. That allows me to create privilege profiles as well. One of the things I'm going to do is go to **System** and **Role-Based Access Control**. Here, I have four default privilege profiles.

01:00-02:00

If I look over here and zoom in a little bit more there's the Super Admin, the Platform Admin, Security Admin, and User. The Super Admin is the highest-level account that has access to the entire platform, and then it works its way down to User. I also have a custom privilege profile that I have already created. Now one of the best ways to understand what to do is to select the Help icon here or go to docs.stellarcyber.ai. Now here, from the configuring role-based access control page in the help, again, if I did not start from the platform, you can go to docs.StellarCyber.ai and search for role-based access. By doing that, I will actually see that as an option that appears.

02:00-03:00

Configuring role-based access control. It takes me to the same place. In the platform, it is context sensitive. But without the platform, you can get there quite simply as well. If you scroll down, you will see that there's an important table. This table–let me zoom in some–this table shows the default privilege profiles and their level of permissions compared to each other. If I take a look here, the first column shows what a user assigned to the user privilege profile has access to.

03:00-04:00

You'll see here that the user has the least amount of privileges than all the rest of the privilege profiles. This user, for example, can view data pages and they have full access to that. If you see a green check mark, that means that privilege profile has full access to whatever specified in the row. Over here, the red check mark means there are no privileges for the item listed on the left of the row. Here, for example, a user has no need to have Global configuration settings or Global settings. Therefore, it is a red check mark. For Cases, the user can view Cases only. They cannot edit Cases or modify them in any way. If you

keep on going down through the list, you'll see that there are different levels of permission and they're all mapped out here.

04:00-05:00
The next highest permission level is the Security Admin. The Security Admin has green check marks for the first four. That means they have full access to View Data Pages, the Global settings, Cases, and Alerts. However, for our Visualize and Investigate and Respond, the Security Admin starts to lose some of the privileges. Usually these privileges are the fact that they cannot delete certain items. They can create items, but they cannot delete them. For example, for Visualize they can view, create, and edit, but there's no delete privileges for custom dashboards or charts. This is more of a way of preventing mistakes from happening, and it ensures they cannot delete something that they shouldn't delete. If they do need to delete something, then they can ask the platform admin to go ahead and help delete it.

05:00-06:00
Going down through the list again there's just a few restrictions for the Security Admin. Many of the things we see here is that there are no delete options available. Now looking at the Platform Admin, the Platform Admin has green check marks all the way down to Respond. There's just some levels of configuration they cannot do at the system level. The main thing that a Platform Admin can't do is adjust the Data Processor, which are the platform settings for data management. In other words, the external storage. The other important thing that a Platform Admin can't do is that they cannot add, edit, or delete user profiles which are these privilege profiles we're talking about now.

06:00-07:00
To add, edit, or delete privilege profiles, you have to be a Super Admin. You see here the Super Admin has access to everything. Now on top of being assigned to a privilege profile, users have a scope. For example from a Platform Admin, but for a single tenant, then I will have these privileges only for that tenant. If I'm a Platform Admin for a partner, scope that's assigned to a tenant group that I then I have platform admin privileges for the tenants within the tenant group, and so forth. Now, I will create a privilege profile from the Platform Admin. I'll do that by selecting **Platform Admin**. If I go in here, you can see the profile configuration is Platform Admin.

07:00-08:00
If I want to go back to the other screen I was on, I can select **View Other Profiles**; that takes me back to here. I'll go back to Platform Admin. If you take a look, this shows you the default settings for nearly 300 different settings. There's quite a bit in here of settings that I can make for levels of privilege for a privilege profile. The good thing about this is that I can

create a profile right from another privilege profile. I don't have to make all the settings. I can use the document we just went through as a guideline. Over here if I want to create a Platform Admin, I will select **Create New Profile from this Template**. Doing this now, I will select a name for this. In this case, I will call it my MSSP...

08:00-09:00

...Platform Admin. I like to name the profile that I create or the privilege profile that I create. I like to give it a name including the name that it came from so there's no mistake as to the level of privilege it has. Okay. Next, is a question on what I can do for new features that come out in a release. For every new feature in a release, there is a setting that is defined by our engineers and our product management team to define what a Super Admin should have, what a Platform Admin should have, what a Security Admin should have, and what a User should have. The question is do do you want to just inherit from whatever we decide the platform management had, and then therefore every new feature will be added to this new privilege profile based on that,

09:00-10:00

...or you can select **Read-Only** that says, "Hey, every new feature will just be read only until this Super Admin goes back in here and modifies these privileges." Or I can specify **No Access** to new features that come out until the Super Admin has gone in here and modified the privileges. For now, I will select **Inherit from Platform Admin** and **Save**. Now these will be the exact same settings that were in the Platform Admin profile. If I look up here, I see exactly that. It says profile configuration, MSSP platform admin is the name, but inherits from platform admin. Once I'm done configuring this profile, I can even create a new profile from this template, or I have an option to delete this profile. Again, to go back to the main profile selector...

10:00-11:00

...I can select **View Other Profiles**. From here I can take a look at these settings. Now we can see what we want to adjust for this MSSP Platform Admin. If I scroll down for example, maybe for this Platform Admin, I don't want them to do response actions. Maybe I'll save that for another team. I'll go ahead and either remove this response or what I'll do to make it a little bit more interesting is I'll remove just some of the options. I'll remove response actions and reporting. I will keep automated threat hunting. I'll scroll down a little bit further. I'll go to the system and I'll say this Platform Admin cannot add sensors, but they can modify sensor profiles.

11:00-12:00

I'll go down a little bit further. I will say that this Platform Admin cannot delete connectors. If I scroll down a little bit further, I won't give them any access to the Data Processor itself. I'll

go ahead and remove that. Now I'll just scroll down to the bottom and **Save**. Again, you're given another option of whether or not you want to inherit from the Platform Admin for a new release, or make new features read only, or no access to the new features. I'll go ahead and save the changes. If you notice here I can reset back to what the Platform Admin had. That's a cool feature as well. I'll scroll back up to the top. Now from the **View Other Profiles**, I can see my new MSSP Platform Admin is created.

12:00-13:00
This doesn't take effect until I apply it to a user account. I'll go ahead and close this out. Go to **System | Users**. Here, I will adjust the admin MSSP account. I'll select edit this row. Here I'll adjust the user privilege to be my new MSSP Platform Admin, and I will **Submit**. To test this out, I will log out and log in as the admin MSSP. I type in my secret password and do my two factor: 013195.

13:00-14:00
Now I'm in. Now let's go ahead and take a look. Under **System**, notice I don't have sensors. I cannot view sensors. I can adjust sensor profiles, but I removed sensors. I'll go back now. If I go to **Connectors**, I have the connectors here, but you will see that I don't have a way of deleting a connector. There's no little trash can icon. Also under **Respond**, now I only have automation; I don't have the reports. This just gives you an idea of what you can do with the role-based access control. You can really decide how you want your users to use the platform.

14:00-15:00
Now, being a Platform Admin, there are some inherent restrictions that were in the original profile. For example, if I go to **System**, you'll see here that I can't add, remove, or delete privilege profiles. If I could I could go in and modify my privileges to give me better privileges than I have now, like modifying a privilege profile. That has been restricted. I need to be a Super Admin to create, modify, or edit privilege profiles. If I look over here as well, I will look at the activity log though that is there. I'll go to **Users** and **Activity Log**. As a Platform Admin, I can see the activity log of what's on the platform, but I can't remove the Activity Log. That's actually a really good thing here as well.

15:00-16:00
Just showing you this is a good reminder that if you don't use unique accounts. Then if a change is made or modified by someone, you're still not going to know who made that change unless you can tell by the IP address where they came from. Using 2FA helps prevent sharing accounts and it's a very good practice to make sure that every single administrator on the platform or every user on the platform uses a unique account so all their progress can be tracked. Well, that's the end of this demonstration of what you can

accomplish with role-based access control. I hope you enjoyed this lesson, and I'll see you in another lesson. This lesson is complete. Thank you for watching.

L03 - USER MANAGEMENT WITH MULTI-TENANT ARCHITECTURE

L03A-PRES: User Management with Multi-Tenant Architecture (26m:34s)

00:00-01:00

The next lesson in *Administration Essentials for Tenants Users and System* is *User Management with Multi-Tenant Architecture*. This lesson, *User Management with Multi-Tenant Architecture*, explains the concepts, configuration, and administration of users to provide access to tenants and tenant groups using scopes and privilege profiles, securing access to the Stellar Cyber platform with two-factor authentication, generating tokens for API access, viewing the user activity log for audit purposes, and how to view session connections from active users on the Stellar Cyber platform.

Hi everyone. In this lesson I will explain user management with Stellar Cyber's multi-tenant architecture. I will start with user management with tenants for on premises or cloud deployments.

01:00-02:00

This picture you see here is a representation of the tenants, the scopes, the privilege, and the tenant groups that are within a Stellar Cyber Open XDR platform. The very first user that gets created in Stellar Cyber when you first deploy an on-premises solution is the root user or the Super Admin. When you first deploy the Stellar Cyber platform, there is no tenant. Essentially, you have the root system and the root system is actually called the root tenant. If you look at the first row, on the right I have a user called MSSP Admin. The scope of the user is assigned to root. The user privilege is assigned to Super Admin.

02:00-03:00

That means that this is an all-powerful user. This user can do anything on the platform. There is no tenant assignment. This user can switch between tenants and has access to all tenants. If you look at the user on the left of the first row, this user is an MSSP Analyst. The scope of this user is a tenant and the user privilege I've assigned is User and the tenant is root tenant. In other words, in this root tenant I have created some Modular Sensors, some connectors, and some Windows Server sensors and Linux Server sensors as well. They're all

assigned to this root tenant. Maybe it's for my organization. If I'm an MSSP, this could be for my MSSP site.

03:00-04:00

Next, I have customers and my customers if I start on the second row, I create a tenant called Customer1. I then create a user called Customer1 Analyst. I really should use a real name, but this is just an example. The scope is tenant, which means that this user will only be able to access the tenant that's specified. Here I've specified the tenant is Customer1. When that user logs in they will only have access to Customer1 and no other tenant. The user privilege basically says what they're allowed to do. What are the features and functions within the Customer1 tenant? Next I have Customer1 Admin. The scope of this user is tenant as well...

04:00-05:00

...which means that even though I've set the user privilege to Platform Admin, this user is a Platform Admin only within the tenant. This user can create users within the tenant. This user can create connectors, can create sensors within the Customer1 tenant. I can rinse and repeat for all my other tenants as well. So if I have lots of other customers, I can create separate accounts for each of the tenants. I can create separate analyst accounts or for various other roles as well. As we just learned about, there are approximately 300 different settings for role-based access control that I can assign to users within each of the tenants as an example. Here at the bottom I've created what's called a tenant group.

05:00-06:00

A tenant group allows a user to access multiple tenants or have certain rights to multiple tenants. Maybe I have a SOC analyst that's assigned to multiple tenants. Maybe one SOC analyst is assigned to Customer1 and 2. Another SOC analyst is assigned to Customer3 and 4. It just allows you to group the tenants together for different levels of access. In this case, I've created a group called Partner-Group1. It has two tenants, Customer1 and Customer2. I have created an analyst user. The MSSP analyst group one is the name of the user. The scope is partner. When you assign a scope of partner, you must assign a tenant group. In this case that user is assigned to Partner-Group1. The privilege of User is again the lowest level of access, but the User privilege was all that was needed for this user to do their job.

06:00-07:00

To the right of that, I have Admin Partner Group1 user. It's the admin for this account. I have the scope partner. Since I assigned scope partner, again I must assign a tenant group. This is Partner-Group1, and the user privilege here is Sec admin. This user can add Modular Sensors to Customer1 and Customer2 or they can do other administrative tasks as well. It's a very very flexible architecture for managing tenants or groups of tenants, and the user

privileges are very well defined. Then throughout this lesson I will show you more detail on how to create users that match these settings. Next is an example if I have a SaaS deployment. Unlike an on premises or a cloud deployment, the SaaS deployment is managed by Stellar Cyber.

07:00-08:00
There is no root tenant for SaaS deployments. When a customer signs up for a SaaS deployment, like an MSSP customer as an example, they are given an account that is a Super Admin, but this Super Admin is not part of a root tenant. There are actually no tenants created. At first they would create a tenant for their own deployment. And then ensure that all the sensors and connectors are assigned to that tenant. Then it follows exactly how you would do if it was on premises. You would go ahead and create another tenant for each customer. The permissions are identical to what you would do if it was an on premises deployment so it exactly matches what I had on the previous slide.

08:00-09:00
The only difference between SaaS and on prem / cloud deployments is the fact that SaaS deployments do not have a root tenant but the root user with a scope of root has access to all tenants. Here is a picture of the Stellar Cyber platform with tenants and users created. This is just to start to let you know where we are going in this lesson. If I take a look here, I have the **Scope** column. For the users you can see whether it's scope of root or scope of tenant, and a scope of root essentially says this user has access to all tenants on the system...

09:00-10:00
...including the root tenant if it's an on premises deployment. A scope of tenant means that the user is assigned to a single tenant. A scope of partner means that that user is assigned to multiple tenants based on the tenant group. The **Privilege** column shows the level of access within the scope. You can go to **System | Role-Based Access Control** to view the privilege profiles to see what's in each of those. Then there's the **Tenant** column and the tenant shows which tenants the user assigned. If you don't see a tenant, that's because it's a root scope, which means they have access to all tenants. Then if you look at the **Tenant Group** column here I have one user that's in the partner group. The partner group has access to Customer1 and Customer2 as a Platform Admin.

10:00-11:00
It's a very handy table to go to. Again, you get here by going to **System | Users**. Next, users are assigned a user scope to define tenant accessibility. What does that mean? If I look at number one, this user has access to all tenants. Hence, at the very top, there is a tenant selector box. In the tenant selector box, I have a default set to all tenants. But if I select that

box I can scroll down and take a look and see that I have access to every single tenant there is. Number two this user has access to the partner. On step number two, this is a partner user, and the partner user has access to the partner group, which contains Customer1 and Customer2.

11:00-12:00

They can see an overall view if they select partner group. They can see all the data from both customers or they can select an individual customer just to see data for that one customer. For the data, this could be the reports, the user information, queries, anything that's assigned to the tenant as well as the Interflow records that are within the tenant as well. Then as number three shows, tenant has access to a specific tenant. However when this user logs in they will not have a tenant selector because they are assigned to a single tenant. Therefore, as you see in step number three, there is no tenant selection box. Now we'll create some users. To create a user, as a Super Admin go to **System | Users**. Then select **Create**. You then enter the following information.

12:00-13:00

There's a username or email address. When you create a user, the first field you see is the **User Name** field if it's an on premises or cloud deployment, or it will be the email address field if it is a SaaS deployment. Next there's the **Display Name** which is the full name of the user. Note that Super Admins have all the options for creating users. Users can be created by admins of lower privilege such as Platform Admins or Security Admins, but all the options may not be available, such as if you look at the very bottom there's the homepage option. That's available if you are a Super Admin creating a user. Okay. Now let's take a look at the next set of options. There's the password. Again, always enter a strong password.

13:00-14:00

The phone number here is optional, but it is handy to have if you do need to contact a user. The email address here is only shown if it's an on premises deployment. Otherwise, for SaaS deployments, the email address has already been provided. There's a language preference. This sets the display language for the Stellar Cyber UI. After you save the setting, the user must log out and log back in for the change to take effect. The supported languages are English, Spanish, Chinese, Japanese, and Korean. Next there's another option called Build a Query. This features for advanced use cases. You enable this option to create an Interflow query that limits the data available to this user.

14:00-15:00

You can build a complex query using standard and / or / not operators to match specified conditions and strings. That's pretty cool, but in most cases it's not needed. But there are cases where you might find this very useful. Next you define user scope. Different options

are available based on the selection. If you define root, the root has access to all tenants. Partner has access to tenants to find an attending group. You must define the tenant group, and then select that tenant group. Tenant has access to a specific tenant that also must be selected. Next is User Privilege. You select the User Privilege based on the custom or default privilege profile, such as Super Admin, Platform Admin, Security Admin, or User.

15:00-16:00

My recommendation here is to review the Stellar Cyber documentation for details or go to **System | Role-Based Access Control** to review the privilege profiles before deciding which profile to use for a user. User privilege is also defined by user scope, so essentially you're setting the user privilege within the scope of tenants. Next is something incredibly useful. It's the two-factor authentication option for a user. This option is available to be enabled if the platform admin has enabled mandatory or optional settings for two-factor authentication and system settings. For option one, I have a picture showing the system settings that a platform administrator can configure.

16:00-17:00

The way I have it set right now is optional. Optional means that 2FA or two-factor authentication will be configured on the tenant and user levels. Here, at the system level, I have 2FA or two-factor authentication set up to be configured on the tenant or user levels. I can go ahead and define them at the tenant level or define them at the user level. For number two in the tenant configuration, if a tenant requires two-factor authentication for all users in the tenant, then any user assigned to the tenant will have two factor enabled by default. For number two for this tenant, I have the option to require 2FA for all users under this tenant.

17:00-18:00

By having that option, there is no choice. All users that are assigned to this tenant will automatically have 2FA configured. For number three, in the user settings, two-factor authentication is available if enabled as an option in the system settings and is optional if two factor is not enabled in the tenant. Note, enabling two-factor authentication is highly recommended. I will get more into that in the next slide. By enabling two-factor authentication, this helps ensure user accounts are not shared. As the Authenticator app is on a user's device, and the Authenticator app is needed to log in. As I just mentioned, It is highly recommended to use two-factor authentication. This protects the users and it protects the customers of the platform as well.

18:00-19:00

But what's really cool to know, if the user does lose access to their Authenticator app, a Platform Admin can reset the two-factor authentication by selecting reset two-factor

authentication when editing a user account in **System | Users**. If you look at the bottom right, this is in a user account, if two-factor authentication is enabled, you can reset two-factor authentication by selecting that button. Next, if you are a Super Admin, there's one extra option called **Homepage**. This option is available to set the default page a user sees when they log in to the platform. Here, usually the default page is the XDR Kill Chain, but you can set it to any number of pages on the platform. This is just a small list here.

19:00-20:00

When finished with all the settings, you can go ahead and select **Submit** to save the settings. Now the visibility of users depends on who is going to **System | Users**. If I have root scope, and I look at **System | Users**, I can see all the users on the platform for any tenant as well. Or if I select a tenant, or if I have a user that has access to a tenant, if you go to **System | Users**, you will then see users assigned to that specific tenant. Or if I'm a user with partner scope I can also see the users assigned to the tenants I have access to in the tenant group.

20:00-21:00

Now speaking of tenant groups, a tenant group is created by Platform Admins by going to **System | Tenant Groups**. You then select **Create**. You enter a tenant group name. In my case it's Partner-Group1. Select and add tenant members to the tenant group. These are the tenants. In this case I have Customer1 and Customer2. Then you can select a logo that will appear in reports, so if I'm a tenant group member so in other words I'm a partner and maybe my partner has access to two of the tenants, when that partner generates a report, the logo will appear on that report. When you're done, go ahead and select **Submit**. Next, to create a user with access to tenants, within tenant groups as a Platform Admin go to **System | Users**, and select **Create**.

21:00-22:00

Then fill in the user details and set the user scope to partner. Once you will set the user scope to partner, you'll then be able to set the tenant group. In this case, I've set the tenant group to partner group and I've set the user privilege to Platform Admin. In other words now this user will have platform admin access to only the tenants within the tenant group, which is Customer1 and Customer2. When a user assigned to a tenant group logs in to the Stellar Cyber platform, they will have access to the tenants within their group as a view containing both, or they can select an individual tenant. If you look on the upper right if you select the tenant drop down. Here there's the Partner-Group1 that will show both tenants combined. Or if I select an individual tenant I will only see that tenant information.

22:00-23:00

Now another important task that people do is use APIs to access the Stellar Cyber platform. If you need to create an account for API access, this will be a privileged account. It is a Super Admin account. To create a user for API access, you actually must be a Super Admin to create it. As a Super Admin you go to **System | Users** and select **plus Create**. You then fill in the user details. Make sure that the password is really, really strong. Then set the user scope to Root and set the user privilege to Super Admin. This account needs full access to the Stellar Cyber platform. Be very careful with this account. Select **Submit**.

23:00-24:00
Now to get access to the API token, you actually have to edit the API account again. Select the pencil icon on the row of the API user account. There's a new section in the user account called API Access. To the right of that, there's a **Generate New Token** button. Go ahead and select **Generate New Token**. That will generate your token. You then must copy the API token and store it in a safe place. Again, this token has access to the full platform. So be very careful with this API token...Go ahead and select **Submit** once you've generated the token. Note you will not be able to view this token again from the user account after you select **Submit**.

24:00-25:00
So again, make sure you've copied it and stored it in a safe place. You will, however, be able to generate a new token if needed. To prove that point, the next time you go and edit the API user account, the API token will not appear as you see here. If you do not have your token, and no one else is using the token, you can generate a new token. This will remove access from the previous token. Again, if someone is actually using the previous token that will then be removed. There'll be no access using that token any longer. If you just want to remove API access altogether from this account, you can delete the active token. That's how you create a token for an API account. There is a lesson on accessing the Stellar Cyber platform with APIs. There'll be more details in that lesson as well.

25:00-26:00
Another important task that administrators can do on the Stellar Cyber platform is view the activity of users on the Stellar Cyber platform. By going to **System | Users** and selecting the **Activity Log** tab, you can see at a glance which accounts are performing which tasks in Stellar Cyber in a searchable, sortable way. Events such as user account lockouts and unlocks are reported here as our API calls. You can even export the activity log as a CSV by selecting **Export CSV** on the upper right-hand side of the table. You also have the ability to view the sessions that are accessing this Stellar Cyber platform by going to **System | Users** | **Current Sessions** tab. This will let you see a table of the active Stellar Cyber logins.

26:00-26:35

You can see at a glance which accounts are logged in to the system in a searchable, sortable table. You can export the session log as a CSV by selecting Export CSV on the upper right-hand side of the table. That is it. We have concluded the user management and Stellar Cyber's multi-tenant architecture. I hope you enjoyed the lesson and I'll see you in other lessons.

This lesson is complete. Thank you for watching.

L03B-DEMO: User Management with Multi-Tenant Architecture (06m:52s)

00:00-01:00
This lesson is a demonstration for the lesson *User Management with Multi-Tenant Architecture*. This lesson is a demonstration of creating a tenant group and an admin user with the scope and privileges to access the tenant group.

Hi everyone. In this lesson I will show you how to create tenant groups. I will log in as my root scope administrator. I'll use my app. There we go, and I'm now verified. Now here, a tenant group is important because it allows you to create a user that has access to multiple tenants.

01:00-02:00
Here, for example, I can see all tenants, but maybe I have SOC analysts that need to manage a few different customers or have administrators that need to manage a few different customers. Or if I'm an enterprise, I might need to manage a few different sites or locations or regions. To do this, you can create a tenant group and assign that to a user. Here's how that's done. To create a tenant group, go to **System** then **Tenant Groups**. I have a Partner-Group1 already. I'll go ahead and create a new group. The group here is...I'll call it Partner-Group2.

02:00-03:00
The Partner-Group2, will have access to Customer3 and Customer4. There's a tenant logo. I'll choose a logo. This will show up in reports. Go ahead and hit **Submit**. Now what I'll do is create a user. To do that I go to **System | Users**. I will select **Create** to create a new user. This user will be the Partner Admin for group two. I'll call this user Partner-Group2. This display name will be Partner-Group2.

03:00-04:00

I'll explain why it's partner in a second. The password–I'll give my secret password. I'll skip the phone number for now. You have a language preference, by the way. I'll discuss more of that a little bit later. Then the root scope would give access to all tenants. I don't want that. The partner scope gives access to tenant groups. I can have a tenant group, and I'll choose Partner-Group2. The privilege, I can say this is a Platform Admin or Super Admin. Here this admin will be a Security Admin. These are more of the security SOC analyst types. I'll enable two-factor authentication, and I'll select **Submit**.

04:00-05:00
It's gray. Do you remember why that is? Yes. I need to go ahead and set this name as well. For this email address, I will use partner-group2@sclabs.ai. Now select **Submit**. I'll check out my account and the filter. I see my account; it is partner-group2. I can see the email, the language, the scope of the partner the privilege of Security Admin, and the tenant group that's assigned and the tenant names. I can actually see those all from here. I will auto size all columns and now I see that as well. Now I will log out and log back in again with Partner-Group2.

05:00-06:00
I'll put in my secret password. I will scan the code in on my Authenticator app, and then type in the verification code that shows up on my app. I will copy these codes and store them in a secure password vault. Select **Accept** after reading the end user agreement. Since I just read it, I won't read it again. If I take a look over here I'll go to the top right. Here I can see that my user, Partner-Group2, is assigned the tenant group Partner-Group2.

06:00-06:51
Looking at Partner-Group2 I can either look at both tenants as a whole. If I do select Partner-Group2, and then I go to any of these menus **Investigate | Threat Hunting** or **View | Cases** or any of these screens, it'll be the combined data from both of the tenants in this group, or I can specify an individual tenant as well. But as of right now I don't have any data, so there's nothing to see here, but this is really about how to create the groups. Okay. Well I hope you found that pretty simple to do. I will see you in the next module. Thank you for watching.

This lesson is complete. Thank you for watching.

L04 - TENANT ASSIGNMENT FOR STELLAR CYBER COMPONENTS

L04A-PRES: Tenant Assignment for Stellar Cyber Components (17m:09s)

00:00-01:00

The next lesson in *Administration Essentials for Tenants, Users, and System* is *Tenant Assignment for Stellar Cyber Tools, Connectors and Sensors.* This lesson, *Tenant Assignment for Stellar Cyber Connectors and Sensors*, provides an overview of how Stellar Cyber tools such as queries, dashboards, and ATH rules can be assigned to tenants as well as configuration details for assigning tenants to Stellar Cyber connectors and sensors.

Hi everyone. In this lesson, I will explain how Modular Sensors, Windows Server sensors, Linux Server sensors, and connectors are assigned to tenants and the Stellar Cyber Open XDR platform.

01:00-02:00

Looking at this picture, I have in the middle the Stellar Cyber Open XDR platform with three tenants. There's the root tenant. There's Customer1 tenant, and Customer2 tenant. Why would I do this? Well, as a managed security services provider, I manage different customer networks. If I'm managing different customer networks, I want to keep every single customer's data contained within its own tenant. I want the machine learning to be applied for that tenant. I want all the data to be stored and segregated from any other tenant. I want separate login access and reporting everything to be contained within one tenant. If I have another customer, I can do the same thing for them as well. I might also have my own organization that I'm managing, and I can create a tenant for that.

02:00-03:00

If I'm on premises I can use the root tenant or I can create a tenant specifically for my own site as well. If I'm in a SaaS deployment, there is no root tenant. I would just create a tenant again to manage my own network or my own organization. I can segment all the data and machine learning from all the other tenants on my system. Looking at the top left as an example, I have an MSSP site that I manage, and I have Modular Sensors, Windows Server sensors, and Linux Server sensors. Those all are assigned to the root tenant in this case. And I also have a connector, which then connects to cloud security, identity, and infrastructure systems, tools, and services. The server cyber platform has hundreds of different connectors to these security systems and tools.

03:00-04:00
I want to make sure that the data I collect for my MSSP site itself from the connectors is stored within my own root tenant in this case. Likewise, for my customers, or if I'm an enterprise, I just might have different sites, or different countries, and I want to manage them all separately. I could create tenants for them. In this case, I'll just say Customer1 is a site. In this case I can have Those customers' Modular Sensors, Windows Server sensors, Linux Server sensors, as well as connectors that that site needs to talk to, all saved locally within Customer1's tenant. To do this, when I configure the Modular Sensors and Windows Server sensors and Linux Server sensors and connectors...

04:00-05:00
...I assign them to the Customer1 tenant. I do the same thing for Customer2. When I create the Modular Sensors, Windows Server sensors, Linux Server sensors, and connectors, I assigned them to Customer2. As a quick recap, this lesson is focused on connectors and sensors, but I want to show some other tools as well within the Stellar Cyber platform. Looking here, saved queries are tenant-specific. The saved queries that one tenant user creates cannot be seen by other users or other tenants. This is for security reasons. Likewise, custom dashboards are tenant-specific as well. If I am an administrator that has access to multiple tenants, when I create a saved query or a custom dashboard, I can select which tenant the query or dashboard is for.

05:00-06:00
However, if I am a user of a tenant or assigned to a tenant, when I create a saved query, only my tenant will be assigned. Therefore, no other tenant will be able to see the query. Likewise if I'm an administrator assigned to a tenant and I create a custom dashboard, I will only have access to my own tenant. Also for the **Respond | Automation** ATH playbooks, those are also specific to tenants. If I look on the upper right-hand side for an ATH playbook, I can assign multiple tenants or tenant groups as well. Sensors are assigned to a tenant when they generate Interflow records. They are keyed to the tenant to which they belong. As you can see on the bottom left picture, I can assign a tenant name...

06:00-07:00
...or I can see the tenant name that's assigned to the sensor. Sensor configuration for tenants is covered further on in this lesson. Connectors are also assigned to a tenant. If you look here on the bottom-right of this picture, I can assign a tenant to a connector and I'll go through that next. Here's some more detail. When creating connectors that run on the Stellar Cyber platform Data Processor or sensors, the tenant is configured by setting the tenant name in the connector configuration, as you see here. You get there by going to **System | Connectors** and then modifying a connector or creating a connector. If you decide you need to change the tenant within a connector, you can do that by editing the connector.

There are two methods that are common for adding sensors to tenants when the Stellar Cyber platform is deployed on premises or in the cloud.

07:00-08:00
In the first method, the tenant ID is configured from the command line with `set tenant ID` when installing a sensor. This is a Windows Server sensor, a Linux Server sensor, or a Modular Sensor. With this approach, a customer with admin access for their tenant can manage and authorize their sensor in the tenant. Because essentially when the administrator of a tenant goes to the **System | Sensors** page, they will see that they can authorize the sensor. In the second method, the tenant ID is not configured during a sensor install. With this approach, the Stellar Cyber platform admin with access to alternates needs to assign the tenant in the sensor-specific configuration settings.

08:00-09:00
In other words, the platform admin will edit the sensor after it has been added to the Stellar Cyber platform. Then they can assign the tenant there. After they do that, then the platform admin that's assigned to the specific tenant can see the tenant and authorize it. To obtain the tenant ID, as an administrator you go to **System | Settings**. Here, you copy the tenant ID for a tenant from the ID column on the row for a customer tenant. If you do not see the ID column, you can select the columns button on the left-hand side and you can add the ID column, after which, you can copy that ID. The best way to copy the ID is to right click the ID and there's an option to copy to clipboard.

09:00-10:00
Now the next step is if you are installing a Windows Server sensor, a Linux Server sensor, or a Modular Sensor, and your Stellar Cyber platform is on premises or in the cloud, then you can use the `set tenant ID` command from the CLI access. Again, each of these Server sensors, and the Modular Sensor has a command line you can access. Here I can type `set tenant ID` and then paste the tenant ID that I had copied from the tenant table. Again, this is only needed for non SaaS deployments. If you have a Modular Sensor, I like to do one extra step. The default hostname for a Modular Sensor is modular.

10:00-11:00
Therefore, I like to set the hostname before it appears in the Stellar Cyber platform. I do that by typing `set hostname` and then the hostname of the Modular Sensor. In this case, this Modular Sensor is connecting to Customer2, so I'm labeling it with Customer2 in the hostname. If you have a Windows Server sensor or a Linux Server sensor that will inherit the hostname from the server the sensor is running on, then you type `set cm`, which is the IP address of the Stellar Cyber platform Data Processor Data Lake. Then you can type in `show cm` and you see the connection is established. Again, this is for an on premises or cloud

deployment. Now as an administrator if you go back to the platform, you can verify that the Modular Sensor is in the proper tenant.

11:00-12:00

With an admin account you can access Customer2 tenant. If you look at the top right, I've selected Customer2, and then you go to **System | Sensors**. The sensor should then appear. So whether it's a Windows Server sensor, a Linux Server sensor, or a Modular Sensor, this will be the same procedure. Or if I have root scope access I can go to **System | Sensors** and look at the **Tenant** column to see which tenant the sensor is connected to. After that, I can select the **Manage** button to authorize the sensor, or the customer with admin access for their tenant can do that as well. As I just mentioned before, if I am an admin user, with root scope access, I can select all tenants.

12:00-13:00

If I see here the **Tenant Name** column, I see that the Customer2 Modular Sensor is in the Customer2 tenant. Now if a Modular Sensor, Windows Server sensor, or Linux Server sensor has already been added to this Stellar Cyber platform that is deployed on premises or in the cloud, that tenant name can be set in the sensor configuration. That's important because if the person with CLI access to the Modular Sensor when installing does not type in the tenant name, have no fear. The sensor will appear in the root tenant if it's an on-premises deployment, and then the administrator can move that sensor from the root tenant to a specific customer.

13:00-14:00

For SaaS deployments, this procedure is different. In a SaaS deployment, you go to **System | Sensor Installation**. Then from the **Sensor Installation** page, step number one you select the **Tokens** tab. Step number two you select **Generate**. Step number three, you select a tenant name. This is done when you generate a token. The tokens are always generated in a tenant. On SaaS there is no root tenant. A sensor must be assigned to a tenant. You cannot move that sensor later. The only way to re-add a sensor to a different tenant is to delete it and re-add it. Next, from the **Sensor Installation** page on step number one, you select the tokens tab.

14:00-15:00

Step number two, select **Generate**. On step number three, you select a tenant name. Here there is no root tenant. All tokens that are generated must be assigned to a tenant. Therefore, all sensors will be assigned to a tenant during the installation process. If later you need to assign the Sensor to a different tenant you will have to generate a new token in the new tenant and then reassign it. On step number four you generate the token. On step number five you copy the token. Then on step number six you select **X** to close the generate

installation token. Now as an administrator installing the sensor, I can set the token string on the command line of a sensor.

15:00-16:00
This will automatically set the CM, which is the configuration management connection for the Stellar Cyber Open XDR platform, and will assign the sensor to the tenant associated with the token. Like I did with the on-premises deployment, when installing Modular Sensors, I like to set the hostname on the Modular Sensor first. In this case this Modular Sensor is going to the Customer1 tenant. I'm sending the hostname with a name of Customer1-Modular Sensor so I can identify it. On Windows Server sensors and Linux Server sensors, I can't set the hostname because it inherits it from the server itself. I then need to set the token string, and this is copied from the token I just created. This is a very long string. Type `set token string` then you paste the string you copied.

16:00-17:10
This will automatically connect the sensor to the Stellar Cyber SaaS platform and it will be in the right tenant. Now as an administrator or as someone with access to the Customer1 tenant, I can select the Customer1 tenant. Then if I go to **System | Sensors**, I will see the sensor appear and it will automatically be authorized because the token does the authorization as well. Here I see that the Customer1 Modular Sensor hostname has also been set. Great. This is now complete. As you can see, setting the tenant is quite a simple process. For on premises deployments, you set the tenant ID when installing a sensor. For SaaS deployments, you set a token which then sets the tenant. That's it. Alright. I hope to see you in another lesson. Thank you for participating.

This lesson is complete. Thank you for watching.

L04B-DEMO: Tenant Assignment for Stellar Cyber Components (22m:29s)

00:00-01:00
This lesson is a demonstration for the lesson *Tenant Assignment for Stellar Cyber Sensors and Connectors.* This lesson is a demonstration of assigning tenants to save queries, dashboards, ATH playbooks, connectors, and sensors.

Hi everyone. In this lesson I will demonstrate how to assign tenants to save as query, to dashboards, to automated threat hunting playbooks, to connectors, and sensors on both SaaS and cloud deployments. If we look over here, I will go to **Investigate | Threat Hunting** and I will start with a saved query. Saved queries are under **Filters**. If I expand the **Filter** menu on the left-hand side, I have **Queries** here.

01:00-02:00
Next to **Queries** I can select this little icon here. That is to create a new query. Here, I will select a new query and I will keep it simple. Maybe I'm creating a query called, "Public to private from malicious." If I look over here, when I create the query since I'm a Super Admin, and I'm using the root scope, I can actually create this query for any of the tenants. Let's say I will create it for Customer2. When I create the query, let's go ahead and add a condition, and the field that will just be a very simple source IP type, Is, and I'll say this is a public IP address.

02:00-03:00
I'll add another condition as well, where the field is a desk IP type and this will be a private IP address. I'll add a condition for source IP reputation. It does auto complete for you. Is malicious. Okay? Hopefully I spelled that right. I'll go ahead and select **Save**. I'll close this out. Now if I go over here I'll type in public, and I have here the query public to private from malicious. Being in the root scope I can see another query here as well. But now let me go ahead and select Customer2. Now that I'm in Customer2, I no longer see that other query.

03:00-04:00
This is only public to private from malicious, the one I created. If I go back to the other one, let's see why I didn't see it. If I take a look at the private IP to public query, I can select it from here. I'll say private. There it is right here. If I edit this one, you'll see that this one was only for Customer1. If I go into Customer1 and I type in there it is right here. I can see the query at this point. Here you see that queries can be tenant-specific. If I am a user of that tenant, in other words, I'm a Customer2 tenant, and I create a query, I don't need to assign it to a tenant. It will automatically be in that tenant. Now I'll provide another example.

04:00-05:00
Go to **Visualize** and **Dashboards**. Here looking at dashboards, if I do create a dashboard, I'll look at **Add New Dashboard**. You'll see when I create a dashboard I can assign it to a tenant. I'm not going to create a large dashboard here, I'll just give an example. I'll give this a name: Customer1-Dashboard and I'll submit this. There's really nothing in this dashboard. It's just to show you that you can assign it to a tenant. Now I'll select the dashboard here and I see the Customer1-Dashboard. If I go to Customer2 and go to **Visualize | Dashboards**, I'm actually there now. You'll see that I do not have that Customer1-Dashboard. Dashboards are also assigned to tenants. Now I'll go back to all tenants again...

05:00-06:00
...and go to **Respond | Automation**. Here from the **Respond | Automation** is where I create automated threat hunting playbooks, also called ATH Playbooks. These are also assigned to

tenants. Notice the **Tenants** column. Here I can see in the **Tenants** column that all the playbooks I have so far are assigned to all tenants. I think for this example, first of all, I want to auto size all columns so I can see. Here I'll take the Windows account lockout Alert and I will clone it for Customer1 and Customer2. I'll give it a new name. For Customer1-2-Windows Account Lockout Alert. I'll remove the time at the end here and clone. Okay.

06:00-07:00

Now that this is a clone let's see if I can find it right here. I will edit this one and change the tenants. Here I can see that the ATH playbook is assigned to all tenants. I'll remove that. I'll take a look here If you see in the drop-down list I can assign it to all tenants or tenant groups, or tenants. Here I'll select Customer1 and Customer2. I will submit this one. Now if I go to Customer1 as my Super Admin account with root scope, I'll extend the column, and I see the Customer1-2 Windows Account Lockout Alert. Don't forget the other ATH Playbooks were assigned to all tenants. Now I'll go to Customer2.

07:00-08:00

Here I also see the ATH playbook, but now if I go to Customer3, it no longer exists. I only see the ones for all tenants. ATH playbooks is another place where I see the tenant selection. Okay. Now I'll go back to all tenants. Next, I'll show you how to set tenants for connectors. Here I'll go to **System | Connectors**. Stellar Cyber has hundreds of integrations with cloud based or on premises security infrastructure, identity, and platform systems, and tools.

08:00-09:00

These integrations could be to collect logs or assets or perform response actions such as containing an endpoint or blocking an IP address on a firewall, but I can also assign these on a tenant basis as well. If a customer is using one of these security platforms, we want to pull in that data for that tenant. Therefore, the connectors should be associated with that tenant. When you create a connector I'll go ahead and select something simple, maybe Cloud Security. I'll choose Prisma Cloud. I'll select a name. I'll call it Customer1 Prisma. Over here I'll select the tenant name. I'll choose Customer1. Then I'll select **Next**.

09:00-10:00

Here's where I would configure the connector settings. I'll just make it up right now. I'll make up a username and a password. This isn't actually going to work, but I just wanted to make sure that I just configured a connector. I'll go to **Next** and **Submit**. Now I have a connector, improperly configured, but I have the connector. Now if I go to **All Tenants**, and then select Customer1 and here from the connector overviews again there was system connectors inside of Customer1, I do see that connector here. However, if I go to Customer2, you will see that it's not here.

10:00-11:00

Again, the connectors remain within tenants as well. Next, I will demonstrate how to apply tenants to sensors. To go to Sensors, we go to **System | Sensors**. Here I will auto size all columns. Right now my tenant selector is set to All Tenants. Therefore, I can see all the tenants on my system. Here I see that three of them are in the root tenant and one is in the Customer2 tenant. This is an on-premises Stellar Cyber Open XDR platform. I'll also demonstrate what you need to do on a Stellar Cyber SaaS instance. Over here I want to add a sensor to a tenant. The first thing I need to do is get the tenant ID. I'll go ahead and go to **System** and **Tenants**.

11:00-12:00

I want to add this sensor to Customer1. The ID is right here and I will right click this and I can copy the clipboard. As I've shown before, if you don't see the **ID** column, I can go to **Columns** and I can search for **ID** and add it here. Now that I have the ID, I've already installed a Stellar Cyber Modular Sensor on my VMware ESXi environment, and it's on my local network. Now from my Mac terminal window, I will use `ssh`, which is a secure shell. To access my Modular Sensor, which is on the same network.

12:00-13:00

I'll type in my secure password for the sensor. Here, I will first see if the sensor is connected to the Stellar Cyber Open XDR platform. I'll type `show cm`, which is the configuration and management connection. I do not have one. The first thing I'm going to do here is set the tenant ID. `Set tenant_ID`. Then I will paste it here. But in case I didn't know what command to do, I do `set ?`. Here I see that I have tenant ID. I'll go ahead and do that again. `Set tenant ID`, and I will paste the tenant ID. Next, I like to set the hostname so that when it appears on the Stellar Cyber platform, it has the right hostname.

13:00-14:00

`Set hostname`. I'll call this one, Customer1 Modular Sensor. Next you do the `set cm` command. This is set cm, which is the `192.168.1.175`. This is the IP address of my Stellar Cyber platform Data Processor Data Lake. I could type in `show cm` and the connection is down. Let's see if it comes up. It's established. Let me go back to the platform. Now what I'll do is go to **System | Sensors**.

14:00-15:00

I see that I have the sensor in Customer1, but it's not authorized. There's a couple of ways we can do this. One, as an administrator with root scope, I do have the ability to authorize this sensor. However, you might want to make it so that the customer themselves can authorize the sensors within their environment. Here if a customer has access to their Customer1 tenant, and they have role-based access privileges to authorize a sensor, then they can go

to **Manage** right from their tenant, go to **Authorization**. They select this, and then add it. I'll add the IDS license and the malware sandbox license. The log forwarder is automatically selected. Now that the sensor has been authorized, it should turn green in a few moments.

15:00-16:00

Here it is. It's green. Just to make sure we also see the hostname that I set as well, Customer1-modular sensor. That's how you assign a Modular Sensor to a tenant using the `set tenant ID` command on the Modular Sensor command-line interface. The other way this can be done, let's say for instance I'm an All Tenants. I realized that the installer of the Modular Sensor didn't assign the tenant ID. I, as an administrator, can go to edit this Modular Sensor, and then here I can assign the tenant right from here and then submit.

16:00-17:00

There are a couple of ways this can happen. But if you want the customer to be essentially autonomous to let them do their own thing, you can give them the tenant ID and then they can add the sensor themselves. This applies as well to Linux Server sensors and Windows Server sensors. Now I will show you from a SaaS platform. Alright. Here I'm on a Stellar Cyber SaaS platform. Here I'm logged in as Paull@sclabs.ai. My user scope is partner, and I'm assigned to the tenant group called MSSP Tenants. Here, I have access to Customer1 and Customer2 tenants. Together, if I select **MSSP Tenants**, which is the group I can see both tenants at once. However, I can go ahead and select Customer1 just to see the Customer1 tenant.

17:00-18:00

I'll go to **System | Sensors** and we see here that I have no sensor. I will go back to my main attending group called MSSP Tenants. To begin to add a sensor, I have to go to **System**, then **Sensor Installation**. Here, as a Super Admin, I would have the ability to download the images for sensors. I could download a Modular Sensor image that I can install on VMware at ESXi. I can download a Windows Server sensor image and a Linux Server sensor image. You cannot take an image that's not downloaded from the platform and connect it to SaaS. You must get them from the platform. I've already done that for my Modular Sensor. The next step is to go to **Tokens**.

18:00-19:00

I have to generate a new token. At this point is where I can assign a tenant. I will assign Customer1. Then I will select **Generate** to generate a token. This token is big. I'm going to copy this token, then I'll go to the CLI of my Modular Sensor that was downloaded from my SaaS platform. Here I'll `SSH aella@192.168.1.161`. Type in my password. If I do a `show interface` there's my IP address. Do a `show cm`, and we see that I am not connected to the platform. Now what I like to do here is, as I usually do, is set the hostname.

19:00-20:00
I'll set it to `Customer1-modular-sensor`. Then you type in `set` and `token`. But if I don't know, I do a question mark. At the bottom here I see that I have set token. I could type in set token. If I don't know the next step I'd do a question mark. Instead you type in `set token` without a question mark. Here I see that he's `set token string`.

20:00-21:00
Set token string, then I paste my key and this is very large. I'll hit **Return**. It says the sensor token is successfully set. Let's see if I can see right now if it sets the cm. I meant `show cm`. Yes. It assigned it to the SaaS platform. But the status is still down. Let's see if it comes to established. Yes, it's established now on port 443. Now I'll go back over to here and go to **System | Sensors**. Sure enough, I see the sensor. If I go to my Customer1, I see the sensor here. It will have the right hostname. Let me expand the columns: Customer1-modular-sensor. It's automatically authorized. That's the difference between an on-premises deployment where I have to manually authorize. Here, because I'm using a token, the sensor's already authorized.

21:00-22:00
If I wait a second, refresh the screen and I'll just wait for it to turn green. Here we go. It's now turned green. Let's check. If I'm at Customer2, I no longer see the sensor. That's how you add sensors to the SaaS platform. There's also another difference. If I go to **Sensors** over here as all or MSSP tenants, and I edit the sensor, notice that I cannot adjust the tenant name. This is because that is part of the token. I would have to set a new token and a new tenant to change the tenant for this sensor. Okay. Well, I hope you enjoyed this lesson. We've covered quite a bit.

22:00-22:30
In this lesson we have covered how to assign tenants, to queries to ATH playbooks, to dashboards, and to connectors and Modular Sensors. I hope you enjoyed this lesson. I will see you in another lesson.

This lesson is complete. Thank you for watching.

L05 - USER LOGIN EXPERIENCE WITH 2FA

L05A-PRES: User Login Experience with 2FA (04m:12s)

00:00-01:00

The next lesson in *Administration Essentials for Tenants, Users, and System* is *User Login Experience to the Stellar Cyber Open XDR Platform with Two-Factor Authentication*. This lesson, *User Login Experience to Stellar Cyber Open XDR Platform with Two-Factor Authentication*, provides an example of the log-in experience for users logging into the Stellar Cyber Open XDR platform UI with two-factor authentication.

Hi everyone. Now that I've explained tenants and user configuration in the Stellar Cyber platform as well as two-factor authentication and role-based access control, I want to show you the user experience as well.

01:00-02:00
For the customer user to access their tenant, they will need to connect to the Stellar Cyber platform hostname. This can be a hostname of the SaaS deployment of Stellar Cyber or the hostname of the on-premises or cloud-hosted Stellar Cyber platform. Once they have access to the hostname, they will then enter the username that they were provided. Now as a customer, I will enter the username provided. In this case, analyst-customer1, and then I'll select **Next**. Next, I'll enter the password. Hopefully it's very long, as it should be, and complicated. Then I'll select **Sign In**. If two-factor authentication, or 2FA, is enabled by the administrator, the user needs to download or use their existing authenticator app...

02:00-03:00
...such as Google Authenticator, Authy, Microsoft, OKTA Verify, or any common authenticator app they prefer. The user selects **Scan a QR code** and points the camera of the mobile device towards the QR code on the login screen After which the user then enters the code from the Authenticator App for Stellar Cyber into the Verify section in the login page, and they select **Verify**. Now as the user I should copy and save the backup verification codes in a safe place. Then select **Continue**. Now the user, or I in this case, must accept the end user agreement before entering this Stellar Cyber platform. The user will now have access to their tenant...

03:00-04:15
...based on the role they were given by the administrator. Note if 2FA is enabled, after the first time a user successfully authenticates into the Stellar Cyber platform, the two-factor authentication will appear after the password is validated as shown in the picture here on the right. There will no longer be a QR code. Just enter your two-factor authentication. They go to their app and then paste it in here, then select **Verify**. Now if the user device no longer has the authenticator app, such as if the user gets a new mobile device, the administrator can reset the two-factor authentication by editing the user account, then selecting **Reset Two-Factor Authentication**. After this the user will need to re-authenticate. As you can see,

it's quite simple for a user to use two-factor authentication. It should be enabled for all accounts.

This lesson is complete. Thank you for watching.

L06 - CERTIFICATE MANAGEMENT FOR THE STELLAR CYBER PLATFORM

L06A-PRES: Certificate Management (19m:28s)

00:00-01:00
The next lesson in *Administration Essentials for Tenants, Users, and System* is *Certificate Management for the Stellar Cyber Platform*. This lesson, *Certificate Management for the Stellar Cyber Platform,* explains the concepts, configuration, and settings needed to generate a TLS certificate for the Stellar Cyber platform.

Hi everyone. In this lesson, I will cover certificate management for when the Stellar Cyber platform is installed on premises or in a private cloud. Certificate management for the UI is not needed for SaaS deployments. By default, Stellar Cyber uses a built-in self-signed certificate.

01:00-02:00
It's used for the UI server, which is for HTTPS communication for management on the Stellar Cyber open XDR platform. It's used by the receiver, which receives Interflow records from sensors over TLS. It's used when you perform sensor upgrades. This is the update connection to the Stellar Cyber platform, which occurs over TLS. It's used for the configuration management connection from sensors to the Stellar Cyber platform over TLS. If you look on the right at the picture, this is a picture of the certificate that is installed in the Stellar Cyber Open XDR platform by default. It is issued to the common name cyber security organization Stellar Cyber AI, and organizational unit cybersecurity management. It was issued by the common name cyber security organizations Stellar Cyber AI, and organizational unit cybersecurity management.

02:00-03:00
This certificate was not issued by a public CA. Therefore, when you access the UI using https, the connection will give you a warning message. Stellar Cyber provides its own certificate for the Stellar Cyber Open XDR platform because to generate a public certificate, we do need to know the host name of the Open XDR platform that you are installing. Because we do not know that in advance, we leave that to the customer to purchase their own

certificate for managing the Stellar Cyber platform. By default, if you try to access the Stellar Cyber UI via web browser using HTTPS, you'll get a certificate warning, as you see here. This is an example using Chrome. Other browsers provide different warning messages.

03:00-04:00

This is resolved by adding a publicly signed certificate or a trusted enterprise certificate for your organization in the Stellar Cyber platform and server settings. I will provide an example of this entire process. This example is for generating a public TLS or SSL certificate, which will require purchasing a certificate from a certification authority of your choice. If the Stellar Cyber platform is not publicly accessible, your IT team can generate a private signed certificate that could be uploaded to the Stellar Cyber platform. The matching public certificate can be distributed to security teams within your organization that will be accessing this Stellar Cyber platform Note, the terms SSL, or secure sockets layer, and TLS, transport layer security, are often used interchangeably.

04:00-05:00

But TLS is actually the successor to SSL. The SSL protocols are now considered obsolete and insecure and modern secure communication over the internet uses TLS protocols. However, TLS certificates are more frequently called SSL certificates because that's what we've used as a name forever. We will use them in this course as well interchangeably. Even some of the programs we run, like OpenSSL, it's not called Open TLS. The first step in creating an SSL or TLS certificate is to create an RSA private key and a certificate-signing request known as a CSR. A CSR contains information including common name, organization, and country, the certification authority, or CA, will use in the creation of the certificate.

05:00-06:00

I remember early on in my career, I, like many people, used the term certificate authority instead of certification authority. But in reality, a CA is not an authority on certificates. It's an authority on certification, it's to validate that you are who you say you are. I will keep on referencing this as certification authority. The CSR will be generated to include an RSA public key match for the RSA private key that you will need to keep secret, as it is a private key. You can create an SSL certificate for a fully qualified domain name such as OpenXDR.sclabs.ai or a wildcard domain name such as *.sclabs.ai. That could be used for securing communication to any server with the same domain name.

06:00-07:00

In this example I will be using a wildcard example. The following is an example of using open SSL on a Mac or PC to generate a private key used in an SSL or TLS certificate to secure the wildcard domain *.sclabs.ai. Open SSL comes on a Mac by default. It is a command-line program that you can run. You can also obtain for Windows and Linux; it's free for those

platforms as well. For step number one, generate a private RSA key for the fully qualified domain name or wildcard domain name of the on-premises or cloud-hosted Stellar Cyber platform. SaaS deployments have TLS certificates installed already. The command is: `openssl genrsa -out wildcard_sclabs_ai.key` and then the size of the key, which is `2024` bits.

07:00-08:00

Step number two, the name of the key does not matter, but it is common to end the name in dot key so you know it is the key. This will create a file in this example called wildcard_sclabs_ai.key. In other words, the file we used in the command above. Next on step number three, we generate the certificate signing request using the private key you just created. When specifying the common name, which is the FQDN, the fully qualified domain name of the server, such as openxdr.sclabs.ai or a wildcard such as *.sclabs.ai, ensure you are using the wildcard if you are using a wildcard. Replace the hostname and domain name with your actual hostname and domain name or wildcard with your domain name.

08:00-09:00

The name wildcard itself is only a reference for you to know that this is a wildcard certificate. The command is: `openssl req -new -key wildcard_sclabs_ai.key`. That's the name of the key file that you just generated. Then `-out wildcard_sclabs_ai.csr` for our certificate signing request. Step number four, you will be prompted to enter important information for the certificate. If you make any mistakes in typing, use the backspace key to correct. Or, if you make a mistake, you will have to hit **control c** and start the process again. Here is an example. The entries in bold and orange below are the responses to the questions you are asked in this process.

09:00-10:00

If we look over here, for the country name, use the two-letter code for your country. The State or province, enter the full name for that. The locality name is the city. The organizational name is the name of your company. The organizational unit is your department. Ours is customer and partner enablement. The common name here is the fully qualified domain name that you are going to name the Stellar Cyber Open XDR platform, or in this case, the wildcard domain name, which is *.sclabs.ai. Then enter an email address for who to contact from this certificate. When you're done entering the email address, you are then prompted to enter some extra information. This information is not needed, so you can hit **Return** to get past each of these items until you are done.

10:00-11:00

Once you are done, the CSR is created and you will have two PEM encoded files. In step number six if you view these PEM encoded text files, they look like the picture on the right. On the top I have the private key, which starts with, “BEGIN PRIVATE KEY,” and ends with, “END PRIVATE KEY.” If you ever need to copy the contents of these files, you always need to copy starting with the dashes before they begin all the way to the dashes at the end either of the key or the request. The private key is very important. That is essentially the security of the certificate. This private key needs to be stored in a secure location. It should only be uploaded to servers you are installing this certificate on.

11:00-12:00

For step number seven, ensure the private key is securely stored. This will need to be uploaded with the certificate created from the certificate authority to the Stellar Cyber platform. For step number eight, the next step is to choose a reputable certification authority vendor that creates public SSL or TLS certificates. Single domain name certificates cost less than wildcard certificates. You can also choose domain validation, which is DV, or organizational validation, which is OV certificates, based on your security needs. With OV certificates the certification authority does a more extensive validation of the information in the CSR before granting a certificate. This will cost more money. Once the CSR is validated in step number nine and signed by the certification authority, you'll be provided a certificate for your server...

12:00-13:00

...or wildcard as certificate along with the certification authority certificates, which will include intermediate CAs and the root CA. In step number ten, the certificates obtained from the certification authority in this example were the wildcard certificate, which is `STAR_sclabs_ai.crt`, and the CA and intermediate CA certificates where the Sectigo, the user trust, and the AA certificate services certs. Note, the extension .crt is a PEM-encoded certificate file, which may also have an extension called .PEM. Also note on a Mac, you can view the certificate using finder. Select the name of the certificate with a .crt or .pem extension and press the spacebar. Then the certificate pops up and you can view it.

13:00-14:00

On a PC, if it's called CRT, you can also double click it to view it as well. After you have the certificates, to upload your server or wildcard certificate to the Stellar software platform, as a super admin, log in to the Stellar Cyber platform and go to **System | Certificates**. Then select **Upload**. Step number one, enter a name for the certificate and key. Mine is called SCLABS SSL Certificate. For number two, ensure you select **Server Certificate**. This is not a CA certificate. We do not need the CA certificate as it is a public certificate that I am uploading. Trusted root CAs are already embedded in this Stellar Cyber Open XDR platform.

14:00-15:00

For step number three, **Choose file** and upload your new wildcard or server certificate. For step number four, **Choose file** and upload your matching certificate private key that you have stored in a secure place. For step number five, select **Submit.** To assign the SSL or TLS certificate to the Stellar Cyber platform services, as a super admin, go to **System | Settings**. Number two, set the UI server certificate, receiver certificate, sensor upgrade certificate, and CM certificate to the name of the new certificate that was uploaded in **System | Certificates**. If you want to try it out first, you can start with just the UI certificate and then go back in and add the receiver and sensor and CM certificate after.

15:00-16:00

Note the certificate is created from a public certification authority. The CA certificate is not needed as built-in public CAs are included and embedded inside the Stellar Cyber Open XDR platform. Next, under the certificate selections, select **Submit** as you see in step number three. For step number four, this process for loading the new certificates takes a few minutes while the UI server reboots. If you are in a maintenance window where users are not depending on the UI access for the next few minutes, it is okay to select **YES** in the confirmation pop up. You will then see a message showing the UI server reboot has initiated successfully, but you now have to wait.

16:00-17:00

It does take a few minutes for the UI server to reboot. If you try going too soon, you will see an error message, something like this. Like the soc-internal.sclabs.ai when I tried going there. You get an error connect or ECONNREFUSED. Just wait a few minutes if you see this. After a minute or two, when you attempt to connect, the connection will be secure. However, for a certificate to work, you do need to connect to the Stellar Cyber platform using the fully qualified domain name of your Stellar Cyber instance. If you were to try using an IP for example, that will not be able to be validated inside the certificate. Therefore, you'll have a similar error that you had before. Other than that, if you take a look on the right here, I no longer have a warning message.

17:00-18:00

My connection is now secure to my Stellar Cyber Open XDR platform. Now if you access the platform, and you still get a certificate error in your browser, I will go through a little bit of troubleshooting for you. This is usually caused by caching in the browser. Step number one: The first option, select the security information settings to the left of the URL and verify that the certificate you see is correct and not the default certificate. When you look at my picture here on the right, I have an arrow pointed to that little circle, or it could be a lock. There's usually some sort of SSL icon or TLS icon to the left of the URL. Select that and then you can take a look and see which certificate is installed.

18:00-19:00
You do want to make sure that the certificate has the same common name or wildcard common name that you are trying to access. In this case, I'm going to soc-training.sclabs.ai. Therefore, my certificate must have soc-training.sclabs.ai or a wildcard, such as *.sclabs.ai. If it doesn't, I will have an error. Number two, quit your browser ensuring all browser windows are closed and the application itself is closed. Then start your browser again and connect to the Stellar Cyber platform URL. Hopefully that clears it up. If not, if that still doesn't work, for number three, try to access the Stellar Cyber platform URL with a private or incognito browser mode. That's a browser mode that does not cache any settings.

19:00-19:30
If that still doesn't work, try a different browser that you have not used to access the Stellar Cyber platform URL. For example, if you're using Chrome, try using Safari or Firefox. Okay. That's it. I hope you found this lesson useful, and I will see you again in another lesson. Thank you for taking the time to watch.

This lesson is complete. Thank you for watching.

L07 - CUSTOM BRANDED LOGOS FOR PLATFORM UI AND REPORTS

L07A-PRES: Custom Branded Logos for Platform UI and Reports (06m:51s)

00:00-01:00
The next lesson in *Administration Essentials for Tenants, Users, and System* is *Custom-Branded Logos for the Stellar Cyber Platform UI and Reports*. This lesson, *Custom-Branded Logos for the Platform UI and Reports*, explains how to configure custom-branded logos for the platform UI and reports as well as tenant-specific logos for reports.

Hi everyone. In this lesson, I will demonstrate how to set custom-branded logos for the platform UI as well as for reports. Stellar Cyber gives customers and partners the ability to replace the Stellar Cyber platform logo, as well as the logo that appears in reports with a customer- or partner-branded logo.

01:00-02:00

If we look at the top right, I have a picture of the login screen. The login screen has the first logo that you see. In this case, it's the Stellar Cyber logo. Also, if you look at the picture right below that, that's the platform UI and in the upper left is also this Stellar Cyber logo. But what if you want a different logo if you are a customer or partner? Second, there are also custom logos that could be created for reports. The Stellar Cyber report logo appears on a scheduled report or an exported report that is generated as a PDF. As an example, to export a report you go to **Respond | Reports**, select a report, then you select **Export**. Here's where you would see the logo on the upper-left side. Here you can see that's the Stellar Cyber logo on the upper left.

02:00-03:00

First I'll start with custom logos for the platform UI. Changing the Stellar Cyber platform UI logo requires a user with user scope set to root and privileges to add and edit settings, such as with a Super Admin. Go to **System | Settings**, scroll down to **System Logo** and select **Choose File**. You then select a dot PNG file no larger than one megabyte that will be adjusted to fit within a 17:4 aspect ratio or 170 by 40 pixels. When you select a .PNG file, let's say the picture is narrow. In other words, it's not horizontally long. It's taller than longer.

03:00-04:00

Then what it's going to do is it's going to fit the picture within the vertical space, in other words up and down. Then you might have more gaps on the left and right side. If you have a picture that's very wide, it'll expand it as high as it can to fit vertically. I think this will make more sense when you see it next. Here I have a square logo so the logo just fits vertically up and down, and you'll see that there's a lot of gap on the left and right and that's okay. You don't need to have a big picture there. After you upload the logo, select **Submit** and the logo changes immediately. You will also see next to the logo, it will display: Powered by Stellar Cyber. This new logo will appear on the login page and in the Stellar Cyber platform UI.

04:00-05:00

The first picture you see on the left is the login page. The picture on the right is the platform UI. Both of them have logos. That's it. That's all there is to it. If you want to go ahead and remove that logo, you can go back to **System | Settings**, hover over the right-hand side of the logo and you'll see a little trash can icon where you can then select that. Then after you do that, you must select **Submit**. After selecting **Submit**, the logo goes away. A custom logo can be created for tenants with tenant groups as well. A tenant group is created by platform admins by going to **System | Tenant Groups**. As a Platform Admin or the permissions to add tenant groups, go ahead and select **Create**.

05:00-06:00

You enter a tenant group name, such as Partner-Group1 in this case. Then you select and add tenant members to the tenant group, which are the tenants. In this case I have Customer1 and Customer2 tenants. You then select a logo that will appear in the reports. This does not change the platform UI logo in the Stellar Cyber platform. It only changes the report logo. Then go ahead and select **Submit**. Then any user that has access to a tenant that is assigned to a tenant group can generate a report to see the logo. To view a report with the logo, log in to the Stellar Cyber platform with a user that can select the tenant or is assigned to the tenant by default. In this example, Customer1. If you look on the upper right-hand side, I have selected Customer1 in the tenant drop-down list.

06:00-06:51
Then you can go to **Respond | Reports** and select a report such as XDR Kill Chain and select **Export**. This will export as a PDF. The new logo in the report will appear in the top-left corner and the logo will also appear for scheduled reports for the tenant within a tenant group. The logo doesn't just appear for exported reports. The logo will also appear for scheduled reports for the tenant within a tenant group. That's it. That's all there is to it. I hope you enjoyed this lesson and I will see you in another lesson. Thank you.

This lesson is complete. Thank you for watching.

L07B-DEMO: Custom-Branded Logos for Platform UI and Reports (06m:48s)

The next lesson is a demonstration for the *Custom-Branded Logos for the Stellar Cyber Platform UI and Reports* lesson. This lesson continues the *Custom-Branded Logos for the Stellar Cyber Platform UI and Reports* lesson with a demonstration of how to create custom-branded logos for the Stellar Cyber platform UI and custom-branded tenant-specific logos for reports using tenant groups.

Hi everyone. In this lesson, I will demonstrate how to add a customer- or partner-branded logo to the Stellar Cyber platform user interface. As well, I will show you how to create a customer- or partner-branded logo for tenants that use reports in the Stellar Cyber platform.

01:00-02:00
When you export a report, that report will have the Stellar Cyber logo. First, I will log in with an account that has root scope and privileges to edit the settings of the platform. Here I have my admin account, I log in with my super secret password. Of course I have my two-factor authentication. There we go. The next thing I do is go to **System** then **Settings**.

From **System | Settings**, I can scroll to **System Logo**, which is right here. I can choose a file, and the file I will use is this logo here. It's a PNG file.

02:00-03:00
That's less than one megabytes in size. The logo will fit vertically first, so up and down. Then whatever's left over goes on the left or right. If it's a very tall logo, the left and right space will be more. If it's a wide logo, again they'll fit vertically first, and then whatever's left over fills up the space on the left and right. All you have to do now is select **Submit** and you'll see here that...I'll close this down. The global settings have been updated successfully. But you see the logo is now changed. I'll zoom in here. There's my logo. If I log out and log back in, the logo is now on the login page. You'll see it's also powered by Stellar Cyber. If I go over here I'll log in again.

03:00-04:00
Enter my two factor. I'm in. That's it. That's all there is to change in the logo. However, if I want to get rid of the logo, I can go back to **Settings** and scroll down here. You'll see when I hover over it, the trash can icon appears. I can select that trash can icon. Select **Submit**, and the logo is gone. It's just that simple. Alright. The next thing I will show you how to do is add a customer- or partner-branded logo to a report for a tenant. To do that, you go to **System | Tenant Groups.** Here I will assign a logo for two of my tenants: Customer3 and Customer4.

04:00-05:00
I could assign a logo for all of them and add them all to one tenant group as well. I select **Create**. I'll give it a name, Partner-Group2. Go ahead and add Customer3. Add Customer4. **Add**. Now I choose a logo. The same one I had before. Then you just select **Submit**. This does not change the platform UI for those users of those tenants. It just changes the exported report. As an administrator with root scope I have access to all tenants, but if I had a user that was assigned to a tenant like Customer3 or Customer4, then when they export a report it will have that logo I just added. Or if I have a partner that is assigned to partner scope and is assigned to Partner Group2 as the tenant group...

05:00-06:00
...then they can select either Customer3 or Customer4. When a report is generated and exported, it will also have that logo. I'll show you what I mean here. I'll go to Customer3. Now that I'm in Customer3, if you look up to the top here the tenant I'm in. Then I go to **Respond | Reports**. Here I'll choose the *XDR Kill Chain Summary* report. In this report if I take a look, if I select **Export | Export as PDF**, you'll see that the logo now appears here. However, if I go as Customer 1, now for the same report, as a user in Customer1...

06:00-06:50

...I'll go ahead and export this report. As this user is not in the same tenant group, this user has the default Stellar Cyber logo. Okay. It's just that simple to change logos for reports for specific tenants. This also applies to scheduled reports. If I look at the report here and I look at the option here I can schedule a report. When I schedule a report, it will also have the logo for that specific tenant. Okay. That's it. Well I hope you enjoyed this lesson and I'll talk to you in another lesson. Thank you.

This lesson is complete. Thank you for watching.

L08 - MAIL SERVER AND RECIPIENTS FOR EMAIL NOTIFICATION

L08A-PRES: Mail Server and Recipients for Email Notification (07m:00s)

00:00-01:00

The next lesson in *Administration Essentials for Tenants, Users, and System* is *Mail Server Settings and Recipients for Email Notification*. This lesson, *Mail Server Settings and Recipients for Email Notification from the Stellar Cyber Platform*, explains how to configure the Stellar Cyber platform with mail server settings and recipients to send email notifications from tools such as Alerts, ATH playbooks, and System Action Center.

Hi everyone. In this lesson, I will explain how to set up the email notifications from the Stellar Cyber platform. This will require that you have an email server and an account on that server that can act as an SMTP gateway. Let's go ahead and do this now.

01:00-02:00

The first thing you do on the Stellar Cyber platform is as a Super Administrator, you go to **System | Mail Server**. Then you select the little pencil icon in the upper right where it says mail server setup to modify the settings. Ask your IT department for access to an SMTP server to use as an email gateway. In my example, I have my own domain with its own email. There are some email gateways out there. If you have Google Workspace, you can create an app password for configuring it uh mail gateway. You can't just create an email on Google for example and use that. You need to have Google Workspace. But other than that, the process is pretty simple. First, you have the account name. The account name will be the displayed name for the email address used as the from address in the notification.

02:00-03:00

Here I have Notification SCLABS. For the account name, this is the displayed name for the email address used as the from address in the notification. The account email address must be a valid email address and this is also...this will be the from email in the notification. You can use an email account if it exists, like no reply at your domain or stellar-notification at your domain like I'm using here. For the outgoing mail server, this is the fully qualified domain name of the mail server. It's usually like mail dot the domain or SMTP dot the domain. For the server port that's usually 465 for SSL or TLS. This works for many mail servers that exist out there. If it's not 465, look at our documentation...

03:00-04:00

...or the documentation for your mail server. For the Authentication Method, you can use log in with plain text. For the User Name, this is the email address you will be using for authenticating with the email server. For the Password, enter the password for the email address that's entered right above. Now, here's a very important note. The checkbox for **Change Password** is selected by default. The first time you enter a password it will be checked. The next time you enter the mail server setup from inside the Stellar Cyber platform, if you have a check mark in the change password box and you select **Submit**, the password will be erased. If you do not intend to change the password, the next time you enter the mail server settings, leave the **Change Password** unchecked.

04:00-05:00

Next, select **Submit**. You'll be prompted to send a test email confirmation. Select **Yes**. Then enter an email address to send a notification to. Then select **Submit**. If the test is successful, a green box will appear letting you know the test was successful. If you get a red box, check the message to determine the problem, such as an invalid host name or invalid account. The email address specified in the test will receive the notification email. Here I see the notification is from notification SCLABS. That was the display name for my email account, and it was to Security Mail Receiver, which was myself. Congratulations! You have successfully configured your email server. Great! Everything is working fantastically.

05:00-06:00

Now you need to make sure you have recipients for notifications in the Stellar Cyber platform. You can do that by going to **System | Recipients**. From **System | Recipients**, select **Create**. Then add the following. You have the name. This is the name of the user to receive notifications from the Stellar Cyber platform. If the user is assigned to a specific tenant, I can use that. This could be a customer's email address. In many cases, the recipient is not a user on the Stellar Cyber platform. That's why it's kept separately. Message type I could put an email. Email address is the email address of the person to receive the notification. Then select **Submit**. Note for message type there are other types such as Slack

and Webhook that does require some additional configuration and you can check our documentation for more details on that.

06:00-07:00
Once the recipient's name is created along with this email, the recipient's name can now be selected for notifications when creating a response action for an Alert. It can be seen in System Action Center notification rules, and in ATH playbooks as an example. Here if we look at the pictures, I have an example of Alert Response action. At the bottom you can select an action and then select **Trigger an Email**. In the System Action Center, on the upper right, we could see that I can specify a recipient for a notification. In the ATH playbooks as well I can select a recipient or multiple recipients. In each of these cases, I can specify multiple recipients.

This lesson is complete. Thank you for watching.

L08B-DEMO: Mail Server and Recipients for Email Notification (13m:16s)

00:00-01:00
The next lesson in *Administration Essentials for Tenants, Users, and System* is a demonstration for the lesson, *Mail Server Settings and Recipients for Email Notification.* This lesson is a demonstration of how to configure mail server settings and recipients for sending email notifications from the platform.

Hi everyone. In this lesson, I will show you how to configure the Stellar Cyber platform to be able to send email notifications. To do this, you go to **System** and then **Mail Server**. I'll zoom in so you can see it better. Here in the mail server setup, I select the pencil icon. Now going through this I have the Account Information, the Server Information, and the Logon Information.

01:00-02:00
The **Account Name** up here is the sender email name. The **Account Name** for the sender email for the notification. The **Account Email Address** is a valid email address that appears as the sender for the notification. It appears in the from. Here I have stellar-notification@sclabs.ai. I've used this valid email address that we actually have an account for just to know that this email is coming from Stellar Cyber. Some people use no reply at their domain or something like that. The **Outgoing Mail Server** I have here is the fully qualified domain name of my mail server.

02:00-03:00

You would use your own mail server here. If it was Google, you would use SMTP.Google.com. Just note that if you're using a free Google account, that will not work. You need to have at least Google Workspace to be able to enable an app password to enable the mail relay, to enable being able to send email from another server such as the Stellar Cyber platform. Here I have the **Server Port** of 465. This is the SSL port of the mail server. Sometimes the **Server Port** is 587. Looking over here as well the **Connection Security**. Most commonly it's SSL or TLS. The STARTTLS is another method, and that might require a different port. The **Authentication Method** is login or plain text. For the **User Name** this is an account that can log into the Mail server.

03:00-04:00

Emails will not be from this account. This is just the account for the authentication. Then of course you need to have a password for the account to be able to log in to the mail server. Here I will select **Change Password** so I could enter in my password. Now I'll select **SUBMIT**. Let me zoom out. Here, you'll see a send test email confirmation. For this I want to say, **Yes** and I'll put in an email address to test. I'll use paul@sclabs.ai and I will **Submit**. You want to see this green box, letting you know that, "Hey! Everything was successful."

04:00-05:00

If I go to my email server now, let's see if I get a new email. Right now it is 3:30 PM. There it is. Just came in. Here's what it says: "Congratulations! You have successfully configured your email server." Yay! Right? It's from the Notification SCLABS. It is to Security Mail Receiver, and it was received now. Okay. The subject is email server settings test. Okay. Now I'll go back over to here. I also want to show you what happens if you do something wrong. I will edit the configuration again. Notice when I edit the configuration and there's a **Change Password** is selected right here by default, not always, and now if I submit instead of canceling...I'll go to Send an Email Confirmation and I'll put in my email address again.

05:00-06:00

Go ahead and **Submit**. Now I have an error. Wait a minute. I just configured this a second ago and it should work. The reason why I had an error is because...let me close that down...is because **Change Password** was on and it's putting in nothing for the password. Here I need to put my password back. If you're going to submit, you have the **Change Password** selected. I mean zoom in so you can see better. If you have the **Change Password** selected, you have to make sure to put in a password. Go ahead and **Submit**. I'll put in my email. Now I'm successful. That red warning box or that red message will let you know what the problem is.

06:00-07:00

For example, if I go in here as well and I will put in an invalid email here. I'll get rid of the dash in stellarnotification. I will unselect **Change Password**. It will keep my current password and **Submit**. So yes, type in an email here. Go ahead and **Submit**. It's letting me know. Look, the stellarnotification at SC Labs–there is no such user. That email must be a valid email here. Now I'll enter in a valid email for testing and **Submit**. Now I'm back to being good again. Okay.

07:00-08:00
Just that red error message will give you a lot of information that is helpful. Now that I've successfully configured the mail server settings on the Stellar Cyber platform, you now have to configure recipients. To do that you go to **System**–I'll zoom in so you can see better–**Recipients**. Here I have a couple recipients already in use. You'll see here that I have this user here, paul@sclabs. Here I see it's assigned to Case assigned and SC Modular sensor offline. If it's already assigned, I cannot remove this user. I'll just go ahead and create another user. Here you enter a recipient name. I'll just call this one Paul SCLABS2.

08:00-09:00
For the tenant, the tenant can be the individual tenant for a customer. Oftentimes maybe the management team or the SOC team at a Customer needs to receive a notification if the sensor is offline or some other important task. By being able to set the tenant, I can go ahead and do that to make sure that they only receive notifications for their specific tenant. Right now I'm an administrator of all tenants, so I'm going to leave this as All Tenants. For the message type it can be an email, a Slack, or a Webhook. For the Slack and Webhook I recommend you look at our documentation for the settings on how to do that. For this example, I will use email. For the email address I'll type in another user on my system.

09:00-10:00
Go ahead and select **Submit**. Now the user is created. Now this email actually isn't valid. I will show you my real working email. Here's the one I'm using right now. You'll see it's just missing one "L" on the Paul. Okay? Now that the recipients are configured, the next thing you do is you can try them out. One of the easiest ways to test the recipient is to go to **System | System Action Center**. Here I have Case Assigned, Case Management. I can just go ahead and assign a Case. For this one what I'll do is I'll modify this existing rule.

10:00-11:00
This Case Management rule will create a notification when a Case is assigned. That's really easy for me to do. Go ahead and select **Next**. It can **Send to Case assignee**. This is the only Case that does not require configuring a recipient. This will actually send it to the user on the system that's assigned a Case, but I'm going to go one step further. I'm going to say anytime a Case is created on the system, send an email to the recipient. Here I can select

recipients. You'll see here this is the new recipient that I just created and you select it off the box to close the selection window. I will give a subject Stellar Cyber Notification for Cases. I'll put in. Okay. Next, I'll zoom out a little bit. Those are my settings. I will **Submit**.

11:00-12:00
This is a very simple thing to do now. I'll just go to the **Cases** menu over here. I will select any Case. I will assign the Case to–let me type in my user here. It doesn't matter who I assign it to. I'll assign to admin-mssp. That's it. The Case is now assigned. Again the System Action Center rule basically says anytime it's assigned, not just to me, but anytime the Case is assigned, let me know. Now that would be a lot of notifications. But this makes it really easy to test. Now I'll go back to my email. Go to the inbox. Oops. Go to the inbox, and I have the email server test settings I just did. Now refresh the screen.

12:00-13:16
Here we go. I just received the notification. Go ahead and select that. Let's see what it's from. Oh, the subject is Stellar Cyber Notification Cases. It is from this Notification SCLABS email. It's to this Paul@sclabs.ai, today at five o'clock. Right now and it's today. The emails from today and what it says (is): "just wanted to let you know the following Cases have been assigned." It shows me the Case. It provides me a link to the Case, and it was assigned to admin MSSP. Now going back to the **Recipients** page, that's all there is to it. If you need to send email notifications, make sure you go to **System | Recipients**. Okay? Well, thank you for watching. I appreciate your time. Thank you for watching. I appreciate you taking the time.

This lesson is complete. Thank you for watching

L09 - SYSTEM ACTION CENTER

L09A-PRES: System Action Center (09m:59s)

00:00-01:00
The next lesson in *Administration Essentials for Tenants, Users, and System* is S*ystem Action Center for System Monitoring and Notifications*. This lesson, S*ystem Action Center for System Monitoring and Notifications* provides an overview of System Action Center and explains how to use System Action Center to send notifications for events being monitored, such as when Cases are assigned to a user, and Modular Sensors are offline.

Hi everyone. In this lesson, I will show you how to set up a System Action Center for system notifications. You use System Action Center to create and manage rules that specify when

system notifications are triggered and where they are sent. To do this you go to **System | System Action Center**.

01:00-02:00
In System Action Center, we can set up notifications for Cases when a Case is created, the status of the cluster health, for connector monitoring, for data storage capacity, for disk capacity–these are both on on-premises installations or private cloud–and Modular Sensor monitoring, also known as Device Sensor. When you go to the **System Action Center** page from **System | System Action Center**, you'll see that there are a lot of rules already created. You can modify one of the existing rules by selecting the pencil icon on the row for the rule, or you can go ahead and create your own new rule.

02:00-03:00
Creating or modifying System Action Center rules requires an administrator account with root scope and access to System Action Center in the privilege profile. Here's some System Action Center tips for you. You can keep the **Name** column for System Action Center pinned to the right or left by selecting the stacked line icon in the **Name** column, then select pin column, pin left as this example shows. This way the name of the rule is always on the left even if you scroll through the columns. Likewise, you can keep the **Status** icon for the System Action Center pinned to the right or left by selecting the stacked line icon in the **Status** column, then select pin column, pin right as shown in this example. This way, the **Status** slider or box that you see for enabling or disabling a rule is on the right, even if you scroll through the columns.

03:00-04:00
One of the best ways to see what System Action Center does is to see an example. So as an example, a Notification rule will be created if a Device Sensor, which could be a Modular Sensor that is a virtual or hardware appliance, has a status of offline. As of the writing of this course server sensor monitoring is not available in System Action Center. Next, you select **Create**, then **Device Sensor Monitoring**, then **Device Sensors Offline**. Each System Action Center notification rule has the following tabs. There's **General**. This is the name and description of when a notification will be sent based on the component being monitored. Some of the rules have an **Advanced** tab depending on the category for the rule...

04:00-05:00
...additional settings might be required such as with Cases to send email notifications to Case assignees and with Modular or Device Sensors to send an interval for checking status, how long to mute after a notification is triggered, or to exclude selected sensors for monitoring, if desired. There's **Actions** for selecting the notification type. The default notification type is to send a platform notification. Or you can select **Add Configuration** for

sending an email notification to a recipient configured in system recipients. Then there's **Done**. This provides a summary for what you just configured, and then you must submit to save the changes. Next enter a name describing the rule. After selecting **Create**, enter a name describing the rule In this case it's SC Modular Sensor offline. Select a tenant or **All Tenants**.

05:00-06:00

In this case, I will use All Tenants. Enter a description or keep the default description. The description here I have is get notified when any device sensor is offline. That's fine with me. Then go ahead and select **Next**. Optionally, select the box next to **Exclude Sensors** to exclude any sensor that you know will be offline to prevent unwanted notifications. If I have a test sensor that I take on and offline, I will put it here and exclude sensors. **Interval**, specify how often to have the system check the status of the sensor and generate a notification if the status is offline. Here I'm putting in five minutes. You also have the Mute Interval. Based on the interval, let's say in five minutes I detect that the system is down. I've received a notification.

06:00-07:00

I don't want to keep on receiving notifications every five minutes. I already know that the sensor is down. I can mute the sensor notification from triggering by the **Mute Interval**. I'll say mute it for one hour or more depending. This way I know I should have the sensor back online within an hour. Okay. I'll go ahead and select **Next**. Select **+ Add Configuration** to add email notification recipient. Select the box next to **Recipients** to select email recipients. Recipients are configured again in **System | Recipients**. As recipients may not be administrators or users on the Stellar Cyber platform, the configuration of email recipients is configured separately than the email sitting in user accounts on the platform.

07:00-08:00

Note, that the system mail server settings must be configured for email notifications. Otherwise only notifications accessible from the top menu bar bell icon will show notifications. Enter a subject for the email notification. In this case Stellar Cyber notifications sensor offline, then go ahead and select **Next**. Review your settings. Everything looks good to me, and then select **Submit**. The new SC Modular Sensor offline notification rule is ready and enabled. You see the status that's pinned there on the right? It does show enabled. The status of the Modular Sensor is available by going to **System | Sensors**. In this example, the SC Modular Sensor has been turned off in VMware ESXi.

08:00-09:00

Note this is a training Modular Sensor. That is not critical. It's okay for me to turn it off. Within the five-minute interval, the notification appeared in my email letting me know the SC

Modular Sensor is offline. If I take a look here on the right, the system notified me: Hi. Just wanted to let you know that the following device sensors have been offline for five minutes." The related rule is the SC Modular Sensor offline. I can see the device sensor name, the device sensor ID, and the tenant name for where the sensor actually is connected to. After that, I took immediate action to get the training Modular Sensor up and running again. If you look at the picture on the bottom left, you'll see now that the status is green and everyone is happy again.

09:00–10:00

If you are not receiving notifications, verify the **Message** column. If the **Message** column is not there you can actually add it. In this example, there is a message stating failed to execute action type_email, failed to send email, request failed with status code 500. Mail server has not been set up. For example, if you haven't set up the system mail server settings, this is the message you'll get. There are other messages you'll get as well that you know why, for example, the email isn't working. Maybe the account is invalid or something like that. But in either case the message is the way to go to see what the problem is. Alright I hope that troubleshooting helped a little bit as well. For the rest of the System Action Center settings, they're very similar. Go ahead and look through them all and decide what you want to enable. Thank you very much. I appreciate your time.

This lesson is complete. Thank you for watching.

L09B-DEMO: System Action Center (11m:06s)

00:00-01:00

The next lesson in *Administration Essentials for Tenants, Users, and System* is *System Action Center for System Monitoring and Notifications*. This lesson is a demonstration of how to create a notification for Cases and offline sensors in System Action Center.

Hi everyone. Now that you've seen how to configure the mail server settings so that the Stellar Cyber platform can send notification emails and I've shown you how to create recipients, the next thing I want to go into a little bit more detail on is the System Action Center. The System Action Center is a very powerful monitoring tool that can send notifications based on events on system activity.

01:00-02:00

As an example, let me go over here. You go to **System** then **System Action Center**. I'll zoom in, and I'll also make this column a little bit better. I'll make this column a little bit bigger for you. I'll auto-size all columns. I'll start over here on the left. We have some predefined rules already created for System Action Center. For example, when a Case is assigned, a Case is closed, a Case is escalated. We scroll down. If the cluster health is red for on-premises deployments, Data-based storage has reached a cap, again for on-premises deployments.

We go down a little bit further. No data from connectors. No data from device sensors which are Modular Sensors either a virtual appliance or a hardware appliance. Again, the root disk is reaching the limit. These are on premises-deployment notifications. There are slightly different rules for SaaS deployments. Here's a rule I created while creating the presentation. If I look over here now, I showed you a previous example of a Case assigned. I want to give a little bit more detail on that. If I go over to the right, I'll just create a new one. Create Case management, Case assigned. Here I can give a name.

03:00-04:00

This one will be, "Case assigned to..." and I'll give it to Paul L. That's just to me. I will give a notification, "Notify user a Case has been assigned to them by the SOC Administrator," just so you can see how this works. Go ahead and select **Next**. Here I can send an email notification to the Case assignee. I'll go ahead and do that. Select **Next**. Since I've configured the recipient in **System | Recipients**, I will have the selection here. I will choose Paul SCLABS. You can put multiple lines here and Stellar Cyber notification for Case assignment.

04:00-05:00

If I wanted to have another, I can select another configuration. Add another recipient with a different subject. Get rid of that for now. Go ahead and select **Next**. This is what we've seen before, but now I'm going to go into a little bit more detail. I'll go ahead and select **Submit**. I will go ahead and remove myself from the other one. I'll go to this one. Go to **Actions**, and I'll remove this recipient. Click **Next** and **Submit**. Now I'll go ahead and assign myself a Case. There'll be something a little different here and I'll show you what the difference is. I'll go to **Internal Firewall Denial** and I will assign it to another user. Let's see if that works.

05:00-06:00

I'll do another one as well. I'll go back to the **Cases** view and maybe this one. A lot of these have already been assigned. I'll just reassign them. Now I will check my emails. I'll go over here. I've already seen the email here. Stellar Cyber notification for Case assignment. If I select this email, here I can see the Cases assigned. Again, it's from Notification SCLABS to me. Now here's the big thing we did not discuss. There's a link inside this email. If I select this link, I can have it go to my internal server. If I scroll this down a little bit here I'll just show you here.

06:00-07:00

This is going to SOC internal. But let me show you another email that I received from earlier on in our tests. Here let me go to one of my previous Stellar Cyber notification Cases. Here I have this Case, and if I select this one, and I scroll down you'll see that there's no URL. The main reason for that is that we don't know where users are accessing the platform from. If you are accessing the Stellar Cyber platform from the public, and the Stellar Cyber platform

is internal with a private IP address, if the user receives an email, maybe they have to be on a VPN to get access, or maybe you permit them to access from the internet.

07:00-08:00
To do that, you have to specify the URL that will be sent in a notification message. To do that we go back to the platform. You go to **System** and then you go to **Settings** as an administrator or the super admin. If I scroll down and there could be other admins as well, but you need to have permissions. Here, I put in SOC-internal.sclabs.ai. Now that gets added to the URL. Now that we've configured the publicly accessible authority, this will appear in the links. Let me show you one more time. Okay. Just to refresh your memory, if I go now and select this link, the link itself when you select it by default, it will look like this.

08:00-09:00
It'll just have Cases / Case. There's nothing in front. If I manually type in the host name, SOC-internal.sclabs.ai/ this actually takes me to the right place. By adding the setting here, for the publicly accessible authority, it's going to automatically send this in the link, or prepend it in the link. If I go back to this email and I'll go to a newer one after I've configured that setting for the publicly accessible authority. Now if I select that link, and I'll scroll this down so you can see it actually takes me right to the right place. That's how you ensure the links will work.

09:00-10:00
Now I have a few other tips for you when using System Action Center or really the UI in general. If I want to add a column here, let me just add a few other columns, and you'll see that they start to fill up. Now I will **Autosize All Columns**. But now by doing this, if I scroll to the left, I lose the column name. If I scroll to the right or left I might lose the status. I can prevent that from happening. By selecting this icon here and specifying pin column. I could pin it left. Now if I move, the column stays to the left. Then I can go over here and select the **Status** column. Pin I can pin that to the right. Now everything in the middle will move but the Status and I have the Actions staying pinned. Okay?

10:00-11:10
That's something that can be helpful to know. You can also export this table as a CSV. I can search as well. If I want to search for my Modular Sensor, type in modular, and I can see it here as well. The other thing about System Action Center is that when you do get a notification along with the email notifications if you have them configured, there's also a bell up here with notifications. If I select this, I can also see the notifications here. I'll just mark these as read, and I'll go ahead and close those out. Now my bubble inside, show me the number of notifications goes away. Okay. Well, I hope you found this lesson useful. I will see you again in another lesson. Thank you.

This lesson is complete. Thank you for watching.

L10 - VALIDATING INGESTION DATA SOURCES

L10B-DEMO: Validating Ingestion Data Sources (05m:30s)

00:00-01:00
The next lesson in *Administration Essentials for Tenants, Users, and System* is a demonstration of validating Stellar Cyber platform data collection and ingestion. This lesson is a demonstration of ways to validate that the Stellar Cyber platform is ingesting data from data sources.

Hi everyone. In this lesson, I want to give a recap of how to validate that data is being ingested by the Stellar Cyber platform. Each individual component is covered in separate lessons. For example, for connectors, there's connector lessons, for sensors there's sensor lessons, for traffic forwarding, or for log forwarding, all those are separate lessons. But here I just want to put them in one place for you.

01:00-02:00
One of the first places I go to validate that data is being ingested, is by going to **Visualize**–and I'll scroll in so you can see–then the **Ingestion** dashboard If I scroll over here, oh let me zoom back out. Looking at this dashboard, I will auto-size all columns. Here I can see that I have connectors. I have connectors on three of my Windows servers. I have three Windows server connectors. I have a connector for Tenable. Here I see the previous 24 hours of ingestion. In some of these cases their test lab environment. I don't always receive data. I see them as zero bytes. I also have the previous 30 days of ingestion and most of these do have ingest. But this is one of the best places to look.

02:00-03:00
What you may not realize though is that you can keep on scrolling down. If I go over to here and I scroll down further, I have **Log Ingestion Usage**. I can see the logs from various devices. Again, I'm looking for the 24 hours in the last 30 days. I can actually auto-size all these columns as well. I go down a little bit further. I also have **Log Ingestion Users by Source and Log Port**. I can see my destination port for my logs. Again, over here I have the previous 24 hours and the average previous 30 days. I go down further, there's **Sensor Ingestion Usage**. If I scroll to the right here, I can see the sensor ingestion. This is for any sensor, so it's the Modular Sensors as well as the Windows and Linux Server sensors.

03:00-04:00

Okay. Those are it. Okay. Just realize you can scroll down and get lots of data on ingestion. Likewise, I can go to the individual components. If I go to **System | Sensors**, I can select a sensor. Again, I will expand this menu here and look at my Modular Sensor. If I scroll down, I can see that I do have input. I do have log forwarder stats. I do have a log forwarder summary. Here I can see the ports, if I scroll in here the ports used as well as how much ingestion per port. Okay. Then I can go as well to **System | Connectors**. Then on the connectors, I can select a connector. Likewise, if I scroll down, I have the **Connector Ingestion Over Time**.

04:00-05:00
Here I do see that I am ingesting data on those. Alright. Those are some of the main places you go to validate that you do have ingestion coming in. Right? You can always go to **Investigate | Threat Hunting** and look for the indice as well. Here I can actually see the components in the legend here: the Modular Sensor and the Windows Server sensor and the pfsense firewall and the Linux agent, which is the Linux Server sensor. The Windows agent is the Windows Server sensor and the Sophos Firewall connector. I can see the top log sources. But that's one of the best ways to know that things are happening. But as I mentioned in a previous session as well, the System Action Center—if I go over to here and say auto-size all columns...

05:00-05:30
...I can, for example, look if a Connector does not have any data coming in right or if a sensor is offline, or no data is coming in from sensors. Those are the main places you go to check and see if you have ingestion coming into the platform. Okay. That's a really quick lesson, but I just wanted to ensure that from one place, you can just tie it all together. Okay? Thank you for taking the time. I hope to see you in another lesson.

This lesson is complete. Thank you for watching.