
Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Automox Connectors 6.0.0

This connector allows Stellar Cyber to ingest logs from Automox and add the records to the data lake. It integrates with Automox APIs to query several content types.

Note the following rate limit in the Automox documentation:



Rate Limiting

Automox makes use of a number of rate limiting configurations to safeguard our APIs against bursts of traffic to maximize the stability and reliability of the platform.

How rate limits are applied

Automox associates all authenticated API requests to the user's account and not to individual API keys. For most APIs, Automox allows 100 authenticated requests per second and 15 unauthenticated requests per second. For unauthentciated requests, the rate limits are tracked per client IP address and are not associated to a user account.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Automox

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **8 hours**

Collected Data

Content Type	Index	Locating Records
Audit Logs	Syslog	msg_class:
Devices	Assets (for Devices)	`automox_audit_logs`
Events		`automox_devices`
Policies		`automox_events`

Content Type	Index	Locating Records

Prepatch Report
Users
		`automox_policies`
		`automox_prepatch_report`
		`automox_users`
		
		msg_origin.source:
		`automox`
		
		msg_origin.vendor:
		`automox`
		
		msg_origin.category:
		`it_mgmt`

The Automox Audit Logs API may occasionally experience reliability issues. In cases where endpoint problems occur, data retrieval can be delayed for extended periods. As a result, the connector may temporarily stall and have difficulty catching up on missed data.

Domain

<Base URL>

where <Base URL> is a variable from the configuration of this connector

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Base URL and API Token

Adding an Automox Connector

To add an Automox connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

For a limitation on filtering APIs, see Filtering APIs on Automox Connectors.

Obtaining Automox Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following Automox credentials. Follow the guidance in the Automox documentation.

- Base URL—The base URL for API access. The default is https://console.automox.com.
- API Token—The API t for Authorization, for example:

  `"Authorization": "Bearer <API_TOKEN>"`

  where you replace `<API_TOKEN>` with the token value
- (Optional) Organization ID—The ID for the organization, which is the last part of your console URL, for example, 0000:


  `https://console.automox.com/dashboard?o=0000`

  The Organization ID is a number, not a UUID. When an Organization ID is provided, the connector will only collect data for the specified organization.


Adding the Connector in Stellar Cyber

To add an Automox connector in Stellar Cyber:


1. Log in to Stellar Cyber.
2. Click **System** | **INTEGRATIONS** | **Connectors**. The **Connector Overview** appears.



3. Click **Create** and select **Connector**.



   The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.
4. Choose **IT Management** from the **Category** dropdown.
5. Choose **Automox** from the **Type** dropdown.




   The asterisk (*) indicates a required field.
6. For this connector, the supported **Function** is **Collect**, which is enabled already.

7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.




   The asterisk (*) indicates a required field.

12. Enter the **Base URL**, for example: https://console.automox.com.
13. Enter the **API Token** you noted above in Obtaining Automox Credentials.
14. (Optional) Enter the **Organization ID** you noted above.
15. Choose the **Content Type** you would like to collect. The logs for **Devices**, **Audit Logs**, **Events**, **Policies**, **Prepatch Report**, and **Users** are supported.

    The **Devices** content type is always selected and cannot be removed from the configuration as it is required for host information.

16. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to, otherwise, it is not a good security practice and may expose the connection to security risks.
17. Click **Next**. The final confirmation tab appears.



18. Click **Submit**.

The new connector is immediately active.


Testing the Connector

In addition to testing for connectivity, the **Test** button for the Automox connector tests that the Base URL and API Token are correct and data requests for the requested content types return successful responses.

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:
   - Change the **Indices** to **Syslog**.
   - For **Devices** only, change the **Indices** to **Assets**.

   The table immediately updates to show ingested Interflow records.

Filtering APIs on Automox Connectors

Some vendor APIs integrated through Stellar Cyber connectors do not support time-bounded querying (for example, using start_time, end_time, or equivalent filters), and may lack time-series metadata on records. As a result, Stellar Cyber is required to pull the entire dataset during each polling cycle, regardless of whether the data has changed.

Potential Impact

- Performance Overhead: The absence of time-based filtering may lead to increased load on the Stellar Cyber ingestion pipeline and degrade collection performance over time.
- Inefficient Polling: The connector must fetch and process all available records each cycle, leading to longer collection durations and higher resource usage.
- Scalability Limitations: For large or growing datasets (for example, alerts, logs, or assets), this limitation may result in delayed data availability or collection timeouts.
- Data Inconsistency: Data may be duplicated or missed due to the quantity of data.

When working with connectors that have this limitation, consider the potential impact on performance and collection efficiency.

Recommendation

Where possible, we recommend working with your vendor to improve or add time range filtering capabilities to their APIs.

Automox Connector Content Types

The Automox connector content types impacted by this limitation are as follows:

- Device (asset)
- Users
- Policies
- PrePatch Report
- Events (filter by date only)
- Audit Logs (filter by date only)

The Device, Users, Policies, and PrePatch Report content types can only be pulled for their entire dataset (no time range filter).

For the Events and Audit Logs content types, each time the connector is sent a request to get data, it will request it with full a day filter (for example, 2025/07/22) instead of an hour/minute time range (for example, 2025/07/21 23:50 ~ 2025/07/22 00:00).

© 2026 Stellar Cyber . All rights reserved.