Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Bitdefender Connectors

A Stellar Cyber Bitdefender connector allows you to Contain hosts (Isolate Endpoints) using an API call to the Bitdefender server managing those hosts.

Connector Overview: Bitdefender

Capabilities

- Collect: **No**
- Respond: **Yes**
- Native Alerts Mapped: **Yes**
- Runs on: **DP**
- Interval: **N/A** (applies only to Collect)

Collected Data

Bitdefender's API does not support pull of data, so that option is not offered in the Stellar Cyber Bitdefender connector. For collection, you set up Bitdefender to push data to a Stellar Cyber sensor configured to ingest httpjson over TLS. (Bitdefender's PUSH event JSON RPC messages are listed in their online documentation). The received logs are is ingested to the **Syslog** index. From there, Stellar Cyber runs alert integrations and maps certain records (see below) to the Alert Index. A detailed list of how to locate the ingested event types is provided in the section below on Locating Records.

Domain

<Access URL>

where <Access URL> is a variable from the configuration of this connector

Response Actions

Action	Required Fields	API
Contain (Isolate) Host	`computer_id` or `endpointId`, and endpoint is type	https://< Access URL>/api/v1.0/jsonprc/incidents {params} where • **Access URL** is the value obtained from your Bitdefender GravityZone Control Center API configuration page. • **Parameters** are:

Action	Required Fields	API

	bitdefender	◦ endpointId value
		◦ jsonprc version (2.0)
		◦ action to perform (either createIsolateEndpointTask or createRestoreEndpointFromIsolationTask)
		◦ uuid of the request
		Example:
		`https://cloud.gravityzone.bitdefender.com/api/v1.0/jsonrpc/incidents`
		with params:
		`{ "endpointId" : "62ba2eeafb978f545505e687" },"jsonrpc": "2.0","method": "createIsolateEndpointTask","id": "301f7b05-ec02-481b-9ed6-c07b97de2b7b"}'`

Third Party Native Alert Integration Details

Of the different record types you can configure to push to Stellar Cyber's httpjson parser, the 11 below are normalized and enriched as they are added to the Syslog index. The records are evaluated against existing records in the **Alert** index. Those that do not already exist are directly and mapped to the XDR Kill Chain and the **Alert** Index. For details, see Integration of Third Party Native Alerts.

The other records are run through the ML/SA pipeline, which may generate alerts based on those algorithms. They are assigned a description of *The Bitdefender endpoint agent reported an anomaly* along with the indicated fields below.

Bitdefender Event Stellar Cyber Label	Stellar Cyber TTP*	Bitdefender Fields	Reported Fields
Advanced Threat Control (ATC)	1	module, computer_fqdn, computer_ip, exploit_type	event.type, host.name,

***TTP mapping legend**

- XDR Malware; XDR Misc Malware
- Execution; Exploitation for Client Execution
- Impact; Data Manipulation
- Impact; Data Encrypted for Impact
- Initial Access; Phishing
- XDR NBA; XDR Firewall Anomaly

Bitdefender Event Stellar Cyber Label	Stellar Cyber TTP*	Bitdefender Fields	Reported Fields
			host.ip, threat.name
Antiexploit Event	1	module, computer_fqdn, computer_ip, detection_threatName	event.type, host.name, host.ip, threat.name
Antimalware	1	module, computer_fqdn, computer_ip, malware_name	eve

***TTP mapping legend**

- XDR Malware; XDR Misc Malware
- Execution; Exploitation for Client Execution
- Impact; Data Manipulation
- Impact; Data Encrypted for Impact
- Initial Access; Phishing
- XDR NBA; XDR Firewall Anomaly

Bitdefender Event Stellar Cyber Label	Stellar Cyber TTP*	Bitdefender Fields	Reported Fields
			nt.type, host.name, host.ip, threat.name
Hyper Detect event	1	module, computer_fqdn, host.ip, malware_name	event.type, host.name, host.i

***TTP mapping legend**

- XDR Malware; XDR Misc Malware
- Execution; Exploitation for Client Execution
- Impact; Data Manipulation
- Impact; Data Encrypted for Impact
- Initial Access; Phishing
- XDR NBA; XDR Firewall Anomaly

Bitdefender Event Stellar Cyber Label	Stellar Cyber TTP*	Bitdefender Fields	Reported Fields
			p, threat.name
Sandbox Analyzer Detection	1	module, computerName, computerIp, threatType	event.type, host.name, host.ip, threat.name
User Control / Content Control	2	module, computer_fqdn, computer_ip, url	event.typ

***TTP mapping legend**

- XDR Malware; XDR Misc Malware
- Execution; Exploitation for Client Execution
- Impact; Data Manipulation
- Impact; Data Encrypted for Impact
- Initial Access; Phishing
- XDR NBA; XDR Firewall Anomaly

Bitdefender Event Stellar Cyber Label	Stellar Cyber TTP*	Bitdefender Fields	Reported Fields
			e, host.name, host.ip, url
Data Protection	3	module, computer_fqdn, computer_ip, url	event.type, host.name, host.ip, url
Storage Antimalware	3	module, computer_name, malware_name	event.typ

***TTP mapping legend**

- XDR Malware; XDR Misc Malware
- Execution; Exploitation for Client Execution
- Impact; Data Manipulation
- Impact; Data Encrypted for Impact
- Initial Access; Phishing
- XDR NBA; XDR Firewall Anomaly

Bitdefender Event Stellar Cyber Label	Stellar Cyber TTP*	Bitdefender Fields	Reported Fields
			e, host.name, host.ip, threat.name
Ransomware activity detection	4	module, computer_fqdn, computer_ip, attack_source	event.type, host.name, host.ip, src.ip

***TTP mapping legend**

- XDR Malware; XDR Misc Malware
- Execution; Exploitation for Client Execution
- Impact; Data Manipulation
- Impact; Data Encrypted for Impact
- Initial Access; Phishing
- XDR NBA; XDR Firewall Anomaly

Bitdefender Event Stellar Cyber Label	Stellar Cyber TTP*	Bitdefender Fields	Reported Fields
Antiphishing	5	module, computer_name, computer_fqdn, aph_type	event.type, host.name, host.ip, url
Firewall	6	module, computer_name, computer_ip, source_ip	event.type, host.name, host.ip, sr

***TTP mapping legend**

- XDR Malware; XDR Misc Malware
- Execution; Exploitation for Client Execution
- Impact; Data Manipulation
- Impact; Data Encrypted for Impact
- Initial Access; Phishing
- XDR NBA; XDR Firewall Anomaly

Bitdefender Event Stellar Cyber Label	Stellar Cyber TTP*	Bitdefender Fields	Reported Fields
			cip

***TTP mapping legend**

- XDR Malware; XDR Misc Malware
- Execution; Exploitation for Client Execution
- Impact; Data Manipulation
- Impact; Data Encrypted for Impact
- Initial Access; Phishing
- XDR NBA; XDR Firewall Anomaly

Required Credentials and Configurations

To **Respond**, an Access URL and API key are required from an administrative account in the Bitdefender GravityZone CLOUD Control Center. The API key must be enabled for the following settings: Network API, Reports API, Incidents API, Quarantine API, and Event Push Service API. The account must have licensing that supports Bitdefender's Isolate action.

Locating Records

Use the following fields as a guide to query for records.

Field details

msg_origin.source: `bitdefender`

All of the indicated modules contain endpoint data; those that are alert-related are additionally mapped to the Alert index.

Bitdefender Module / Stellar Cyber event.type	Bitdefender Event / Stellar Cyber Label	Stellar Cyber msg_class	Stellar Cyber msg_origin.category	Mapped to Alert Index
adcloud	Cloud AD Integration	`bitdefender_cloud_ad_integration`	`endpoint`	
antiexploit	Antiexploit Event	`bitdefender_antiexploit_event`	`endpoint`	yes
aph	Antiphishing	`bitdefender_antiphishing`	`endpoint`	yes
av	Antimalware	`bitdefender_antimalware`	`endpoint`	yes
avc	Advanced Threat Control (ATC)	`bitdefender_advanced_threat_control`	`endpoint`	yes
device-control	Device Control	`bitdefender_device_control`	`endpoint`	

Bitdefender Module / Stellar Cyber event.type	Bitdefender Event / Stellar Cyber Label	Stellar Cyber msg_class	Stellar Cyber msg_origin.category	Mapped to Alert Index
dp	Data Protection	bitdefender_data_protection	endpoint	yes
endpoint-moved-in	Endpoint moved in	bitdefender_endpoint_moved_in	endpoint	
endpoint-moved-out	Endpoint moved out	bitdefender_endpoint_moved_out	endpoint	
exchange-malware	Exchange Malware Detection	bitdefender_exchange_malware_detection	email	
exchange-organization-info	Exchange License Usage Limit Has Been Reached	bitdefender_exchange_organization_info	endpoint	
exchange-user-credentials	Exchange User Credentials	bitdefender_exchange_user_credentials	endpoint	
fw	Firewall	bitdefender_firewall	endpoint	
hd	Hyper Detect event	bitdefender_hyper_detect_event	endpoint	yes
hwid-change	Hardware ID Change	bitdefender_hardware_id_change	endpoint	
install	Install Agent	bitdefender_install_agent	endpoint	
modules	Product Modules Status	bitdefender_product_modules_status	endpoint	
network-monitor	Network Attack Defense Event	bitdefender_network_attack_defense_event	ndr	
network-sandboxing	Sandbox Analyzer Detection	bitdefender_sandbox_analyzer_detection	endpoint	yes
new-incident	New Incident	bitdefender_new_incident	xdr	
ransomware-mitigation	Ransomware activity detection	bitdefender_ransomware_activity_detection	endpoint	yes
registration	Product Registration	bitdefender_product_registration	endpoint	
storage-antimalware	Storage Antimalware Event	bitdefender_storage_antimalware_event	endpoint	yes
supa-update-status	Outdated Update Server	bitdefender_outdated_update_server	endpoint	

Bitdefender Module / Stellar Cyber event.type	Bitdefender Event / Stellar Cyber Label	Stellar Cyber msg_class	Stellar Cyber msg_origin.category	Mapped to Alert Index
sva	Security Server Status	bitdefender_security_server_status	endpoint	
sva-load	Overloaded Security Server	bitdefender_overloaded_security_server	endpoint	
task-status	Task Status	bitdefender_task_status	endpoint	
troubleshooting-activity	Troubleshooting activity	bitdefender_troubleshooting_activity	endpoint	
uc	User Control/Content Control	bitdefender_user_control_content_control	endpoint	yes
uninstall	Uninstall Agent	bitdefender_uninstall_agent	endpoint	

Adding a Bitdefender Connector

To add a Bitdefender connector:


1. Configure Bitdefender API access
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Configuring Bitdefender API Access

You must configure obtain the following information from your Bitdefender GravityZone console before you add the connector in Stellar Cyber:

- Access URL
- API Key

1. Log in to the Bitdefender GravityZone CLOUD Console as an administrative user.
2. Access your account settings.



3. Locate and save the **Access URL** information for use in the next section (for example: `https://cloud.gravityzone.bitdefender.com`).

   Do not include `/api` at the end of the URL.

4. Select the option to **Add** an **API Key**.
5. Create the key with at t these options:

   Network API

   Reports API

   Incidents API


   Quarantine API

   Event Push Service API
6. Save the API key.
7. Locate the new key in the API keys table and save the value for use in the next section.


Adding the Connector in Stellar Cyber

To add a Bitdefender client connector in Stellar Cyber:


1. Log in to Stellar Cyber.
2. Click **System** | **INTEGRATIONS** | **Connectors**. The **Connector Overview** appears.



3. Click **Create** and select **Connector**.



   The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.
4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **Bitdefender** from the **Type** dropdown.




   The asterisk (*) indicates a required field.
6. For this connector, the supported **Function** is **Respond**, which is enabled already.

7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. This is the Stellar Cyber tenant allowed to use this connector.
9. Choose the device on which to run the connector.
10. Click **Next**. The **Configuration** tab appears.



    The asterisk (*) indicates a required field.

11. Enter the **Access URL** you noted above in Configuring Bitdefender API Access (for example: https://cloud.gravityzone.bitdefender.com).

    Do not include /api at the end of the URL.

12. Enter the **API Key** you noted above.
13. Click **Next**. The final confirmation tab appears.
14. Click **Submit**.


The new connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.

3. Click **Test** at the right side of that row. The test runs immediately.

Note that you ma[illegible]n only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota	The server or user license/quota will eventually recover. The connector will periodically retry the

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
		is exceeded.	query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

Use these steps to verify the records related to Bitdefender are in Stellar Cyber:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** to **Syslog**.

   The table immediately updates to show ingested Interflow records.

For **Respond** actions, refer to Understanding Event Details to understand how work with the Contain Host feature.

© 2026 Stellar Cyber . All rights reserved.