Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring CODA Footprint Connectors 6.1.0

This connector allows Stellar Cyber to ingest logs from CODA Intelligence's CODA Footprint and add the records to the data lake. It integrates with the CODA Footprint API to get scan results and associated vulnerabilities.

Due to a limitation on time window filtering in the CODA API, this connector will produce duplicate data, which may be critical for device vulnerabilities data. Some simple local filtering has been added to this connector, but it is best effort (not guaranteed) and may decrease connector performance.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: CODA Footprint

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **8 hours**

Collected Data

Content Type	Index	Locating Records

Alert
Device
Device Application
Device Vulnerability
	Syslog (for Alert and Device Application)
	Scans (for Device Vulnerability)
		msg_class:
		`coda_footprint_alert`
		`coda_footprint_device`
		`coda_footprint_device_application`

Content Type	Index	Locating Records

	Assets (for Device)	`coda_footprint_device_vulnerability`
		
		msg_origin.source:
		`coda_footprint`
		
		msg_origin.vendor:
		`coda`
		
		msg_origin.category:
		`scan`

Domain

<Base URL>

where <Base URL> is a variable from the configuration of this connector

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- For API Keys Auth Method: Base URL, and API Key
- For JWT Auth Method: Base URL, Username, and Password

Adding a CODA Footprint Connector

To add a CODA Footprint connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

For a limitation on filtering APIs, see Filtering APIs on CODA Footprint Connectors.

Obtaining CODA Footprint Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following CODA Footprint credentials.

For API Keys authentication method:

- Base URL—The base URL for API access. The default is https://demo.codacloud.net. You can modify the URL, for example to https://footprint.codacloud.net.

- API Key—The credentials for the API Keys authentication method.

For JWT authentication method

- Base URL—The base URL. The default is https://demo.codacloud.net. You can modify the URL, for example to https://footprint.codacloud.net.
- Username and Password—The credentials for the JWT authentication method.

Obtaining API Key

Follow the guidance in the API Keys section in the CODA Intelligence documentation.


Obtaining Username and Password

Follow the guidance in the JSON Web Tokens section in the CODA Intelligence documentation.


Adding the Connector in Stellar Cyber

To add a CODA Footprint connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



   The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.


4. Choose **Vulnerability Scanner** from the **Category** dropdown.
5. Choose **CODA Footprint** from the **Type** dropdown.



   The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.
8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.




   The asterisk (*) indicates a required field.
12. Choose the **Auth Method** to use **API Keys** or **JWT**.

    For **API Keys** Auth Method:

    a. Enter the **API Key** you noted above in Obtaining CODA Footprint Credentials.

    b. (Optional) Enter the **Tenant ID**. Use this field if you want to get data from a specific CODA tenant.

    For **JWT** Auth Method:



    The asterisk (*) indicates a required field.

    a. Enter the **Username** and **Password** you noted above in Obtaining CODA Footprint Credentials.


    b. (Optional) Enter the **Tenant ID**. Use this field if you want to get data from a specific CODA tenant.
13. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to,

otherwise, it is not a good security practice and may expose the connection to security risks.

14. Choose the **Content Type** you would like to collect. The logs for **Device**, **Alert**, **Device Application**, and **Device Vulnerability** are supported.

    The **Device** content type is always selected and cannot be removed from the configuration as it is required for host information.

15. Click **Next**. The final confirmation tab appears.



16. Click **Submit**.

The new connector is immediately active.


Testing the Connector

In addition to testing for connectivity, the **Test** button for the CODA Footprint connector tests that the Base URL and API Key or Username and Password are correct and data requests for the requested content types return successful responses.

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

> The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:

   - For **Alert** and **Device Application**, change the **Indices** to **Syslog**.
   - For **Device Vulnerability** change the **Indices** to **Scans**.
   - For **Device** change the **Indices** to **Assets**.

   The table immediately updates to show ingested Interflow records.

Filtering APIs on CODA Footprint Connectors

Some vendor APIs integrated through Stellar Cyber connectors do not support time-bounded querying (for example, using start_time, end_time, or equivalent filters), and may lack time-series metadata on records. As a result, Stellar Cyber is required to pull the entire dataset during each polling cycle, regardless of whether the data has changed.

Potential Impact

- Performance Overhead: The absence of time-based filtering may lead to increased load on the Stellar Cyber ingestion pipeline and degrade collection performance over time.
- Inefficient Polling: The connector must fetch and process all available records each cycle, leading to longer collection durations and higher resource usage.
- Scalability Limitations: For large or growing datasets (for example, alerts, logs, or assets), this limitation may result in delayed data availability or collection timeouts.
- Data Inconsistency: Data may be duplicated or missed due to the quantity of data.

When working with connectors that have this limitation, consider the potential impact on performance and collection efficiency.

Recommendation

Where possible, we recommend working with your vendor to improve or add time range filtering capabilities to their APIs.

CODA Footprint Connector Content Types

The CODA Footprint connector content types impacted by this limitation are as follows:

- Device (asset)
- Device Application (filter by device ID)
- Device Vulnerability (filter by device ID)

The Device Vulnerability and Device Application content types are pulled depending on the number of devices pulled when the Device content type was ingested. The Device content type can only be pulled for the entire dataset (no time range filter).



© 2026 Stellar Cyber . All rights reserved.