Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Azure AD B2C SSO: Complete Configurations on Stellar Cyber

After you have configured your Azure AD B2C server, use the information from your configuration steps to complete setup on your Stellar Cyber server.

Upload Certificates

If the Stellar Cyber certificate and key file you obtained initially are not already loaded into the Stellar Cyber, load them now.

1. Locate the pem and key file you obtained as the first step of this process.
2. Log into Stellar Cyber as an administrative user.
3. Access **System | Saved Objects | Certificates**.
4. Select **Upload**.
5. In the dialog box that opens, specify a **Name** to help you identify the certificate is associated with your Azure AD B2C SSO.
6. Select the option for **Server Certificate**.
7. In the field for **Certificate**, browse to and select the **pem** file associated with the pfx you uploaded to Azure AD B2C in the previous section.
8. In the field for **Private Key**, browse to and select the **key** file you received that matches this pem file.
9. Click **Submit**.
10. Now, associate the certificate to the Data Processor. Access **System | ORGANIZATION MANAGEMENT | Settings | Data Processor Settings.**
11. In the **Server Certificate** section, select the certificate you uploaded above.
12. Select **Submit**.

Configure Users

If you have configured SSO with **Authentication and Authorization**, skip this section. For all other cases, including for tenant-specific SSO Authentication, you must add the user accounts to Stellar Cyber, using the User Principal Names you obtained in the previous section **as both the user name and email address.**

Follow guidance in **Managing Users** to add users, if they are not already in Stellar Cyber with matching User Principal Names.

User Principal Names and email addresses in Azure AD B2C are case sensitive.

Complete SSO Configuration

The steps to complete SSO configuration are slightly different when you are configuring it for the whole Stellar Cyber DP or just a specific tenant. Complete the steps in the applicable section.

Azure AD B2C Final SSO Steps for Global DP

1. Log into Stellar Cyber as an administrative user.
2. Access **System | ORGANIZATION MANAGEMENT | Settings**.
3. Locate the section for **Authentication**.
4. For **Authentication Method**, select **SSO (SAML).**
5. For **SSO Configuration Method**, select **Metadata URL**.

   Manual configuration is supported, but this example procedure is specifically for use with the metadata URL workflow.

6. For **Issuer URL**: Enter the URL for your Stellar Cyber DP (for example, `https://testdp.stellarcyber.ai`). You must include **http://** or **https://** in the **Issuer URL** field.
7. For **Metadata URL**: Enter the URL Enter the URL you copied to your worksheet when you completed uploading the policies (example: `https://stellarpmb2c.b2clogin.com/stellarpmb2c.onmicrosoft.com/B2C_1A_signup_signin_saml/samlp/metadata`)
8. For **Use IDP for**, set this to the method you prepared Azure AD B2C to support, either **Authentication only** or **Authentication and Authorization**.
9. Select **Allow Clock Skew** to allow for system time differences between Stellar Cyber and Azure AD B2C. Authentication messages have an expiration. If the system times on Stellar Cyber and Azure AD B2C are not synchronized, the messages might expire before they even get to Stellar Cyber. The result is that users cannot log in, because they cannot authenticate.
10. Set the **Two-Factor Authentication** strategy.

    - The overall Global Settings for 2FA affect authentication for partners and tenant users. For example, if 2FA is **Mandatory**, all users must use 2FA.

- Enabling 2FA here is independent of what you have configured on your SSO service. Enabling it here causes a separate 2FA prompt to be displayed upon logging in to Stellar Cyber.
- The 2FA page from Stellar Cyber refers to use of Google Authenticator, but other authenticator applications also work.


10. Click **Submit**.

Azure AD B2C Final SSO Steps for a Specific Tenant

Use this set of steps if you are configuring SSO authentication only for a specific Tenant.

1. Navigate to **System | ORGANIZATION MANAGEMENT | Tenants**.
2. Locate the tenant you want to configure for SSO then click the edit button.
3. In the dialog that displays, select **Next** to display the Authentication page of the **Edit Tenant** dialog.

   This screen enables you to configure tenant-specific overrides to the global authentication strategy.



4. Select the **SSO (SAML)** as the Authentication Method.

- A Global selection of **Authentication and Authorization** applies to all users (root, partner, and tenant), so the option to change authentication method for a specific tenant is not applicable when the Global method is set to **Authentication and Authorization**. You cannot log in to Tenant SSO when Global SSO is set to **Authentication and Authorization**. If you want to use SSO but also allow local users and tenant override, you must set the Global authentication method either to **Local** or to use the IdP with **Authentication Only**.
- Although you can customize SSO configuration on a per-tenant basis, the **Authorization** capability is only supported at the global level. Overrides you make at the tenant level are for **Authentication** only, so the toggle for **Authentication and Authorization** is not offered in the tenant editor.
- The authentication method for partners is the same as that for root users. Any authentication overrides for tenant-level users in a tenant group have no effect on the authentication method for the partners who manage the group.

5. Choose **Metadata URL** as the configuration method.

Manual configuration is supported, but this example procedure is specifically for use with the meta URL workflow.

6. For **Issuer URL**: Enter the URL for your Stellar Cyber DP (example `https://testdp.stellarcyber.ai`)
7. For **Metadata URL**: Enter the URL Enter the URL you copied to your worksheet when you completed uploading the policies (example: `https://stellarpmb2c.b2clogin.com/stellarpmb2c.onmicrosoft.com/B2C_1A_signup_signin_saml/samlp/metadata`)
8. Select **Allow Clock Skew** to allow for system time differences between Stellar Cyber and Azure AD B2C. Authentication messages have an expiration. If the system times on Stellar Cyber and Azure AD B2C are not synchronized, the messages might expire before they even get to Stellar Cyber. The result is that users cannot log in, because they cannot authenticate.
9. Set the **Two-Factor Authentication** for the users of this tenant.

   - The overall Global Settings for 2FA affect authentication for partners and tenant users. For example, if 2FA is **Mandatory**, all users must use 2FA.
   - Enabling 2FA here is independent of what you have configured on your SSO service. Enabling it here causes a separate 2FA prompt to be displayed upon logging in to Stellar Cyber.
   - The 2FA page from Stellar Cyber refers to use of Google Authenticator, but other authenticator applications also work.

10. Click **Submit** to save the tenant changes.

© 2026 Stellar Cyber . All rights reserved.