Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!


Configuring Active Directory Federation Services SSO

These instructions explain what to configure in Active Directory Federation Services (AD FS) and in Stellar Cyber so that AD FS can authenticate Stellar Cyber administrative users. It's assumed that you've already deployed AD FS and are using it to authenticate users on your network. If not, see Deploy and configure AD FS. It's also assumed that user accounts for Stellar Cyber administrative users have already been added to Active Directory and that each account has an email address and password. AD FS will use these to authenticate users during login.


If you use domain names in the authentication settings for Stellar Cyber (the relying party), use domain names in the configuration for AD FS (the identity provider). Similarly, if you use IP addresses in Stellar Cyber, use IP addresses on AD FS.

Active Directory Federation Services

1. Log in to Server Manager and view the Dashboard.
2. Select **Tools | AD FS Management**.




This opens the AD FS management console.




AD FS Server: Create a Relying Party Trust

1. Select **Add Relying P Trust** in the right panel or access the context menu for **Relying Party Trusts** in the left panel and select **Add Relying Party Trust** there.

   To access the context menu when using a mouse, right-select **Relying Party Trusts** in the left panel. To access it when using a handheld device, long-press (press and hold) **Relying Party Trusts**.

   The Welcome to the Add Relying Party Trust Wizard appears.

2. Leave **Claims aware** selected and then **Start**.
3. In the Select Data Source step, select **Enter data about the relying party manually** and then select **Next**.
4. In the Specify Display Name step, enter a name for the relying party such as `Stellar Cyber AIO CE`, optionally enter any notes for future reference, and then select **Next**.
5. Skip the Configure Certificate step and select **Next**.
6. Select **Enable support for the SAML 2.0 WebSSO protocol** and enter the **Relying party SAML 2.0 SSO service URL**. The exact URL depends on the type of Stellar Cyber deployment (on premises or SaaS) and whether the SSO applies to the entire Stellar Cyber system or to a single tenant.

   If you are configuring SSO for the entire Stellar Cyber system:


   - **Relying party SAML 2.0 SSO service URL**: Use the Stellar Cyber Platform URL, appended with `/saml/login/callback/org_id/<org-id>`. The format is `https://<your.stellar.cyber.address>/saml/login/callback/org_id/<org-id>`, where `<org-id>` is the **Organization ID** on the license page. For example: `https://192.168.24.110/saml/login/callback/org_id/0c5b67d2e9e54398be1e4d1cff1edc3`

   If you are configuring SSO for a tenant:

   - **Relying party SAML 2.0 SSO service URL**: Use the Stellar Cyber Platform URL, appended with `/saml/login/callback/org_id/<org id>/cust_id/<tenant-id>`. The format

is `https://<your.stellar.cyber.address>/saml/login/callback/org_id/<org-id>/cust_id/<tenant-id>`, where `<org-id>` is the **Organization ID** on the license page. For example: `https://192.168.24.110/saml/login/callback/org_id/0c5b67d2e9e54398be1e4d1cff1edc3d/cust_id/59125044`

This is the URL where ADFS sends SAML assertions to Stellar Cyber after a successful authentication. An assertion contains a user's authentication details and attributes.



The **Relying party SAML 2.0 SSO service URL** in the ADFS UI is the URL to which ADFS sends its SAML authentication response. Different identity providers use different names for this URL as shown in the following table:

Identity Provider	Term for the Assertion Consumer Service (ACS) URL
Active Directory Federation Services	Relying party SAML 2.0 SSO service URL
Microsoft Entra ID	Reply URL
Okta	Single sign on URL
OneLogin	Assertion Consumer (ACS) URL
Rippling	Assertion Consumer Service URL

7. When done, select **Next**.
8. For the **Configure Identifiers** step, enter the Stellar Cyber URLs that will communicate with Active Directory. For example:

   `https://your.stellar.cyber.address`
9. Skip the **Choose Access Control Policy** step and select **Next**.
10. Skip the **Ready to Add Trust** step and select **Next**.
11. Leave **Configure claims issuance policy for this application** selected and **Close**.

AD FS: Add Rules

Create transform rules to define where Active Directory authenticates users and what attributes it returns to Stellar Cyber after a successful user authentication.

Rule 1

1. In the Relying Party Trusts page, access the context menu of the relying party trust you just made and **Edit Claim Issuance Policy**.

   To access the context menu when using a mouse, right-select the relying party trust name. To access it when using a handheld device, long-press (press and hold) the relying party trust name.


2. **Add Rule** to check the email address on an incoming claim against the Name IDs in the Active Directory attribute store.
3. Leave the claim rule template as **Send LDAP Attributes as Claims**, and then select Next.
4. Enter the following in Add Transform Claim Rule Wizard and then select **Finish**:

   Claim rule name: Enter a name such as **NameID**.

   Attribute store: **Active Directory**

   LDAP Attribute: **E-Mail-Addresses**

   Outgoing Claim Type: **E-Mail Address**



   After AD FS (the identity provider) authenticates a user, this rule instructs it to take the value of the email attribute in the user's Active Directory account and transform it into an E-Mail Address claim in the token it sends to Stellar Cyber (the relying party).

Rule 2

1. **Add Rule** to transform the incoming claim type of E-Mail Address to an outgoing claim type of Name ID.

   The value (for example, user@yourdomain.com) remains the same; it's just the claim type that changes.
2. For the claim rule template choose **Transform an Incoming Claim** and then select **Next**.
3. Enter the following in Add Transform Claim Rule Wizard and then select **Finish**:

   Claim rule name: Enter a name such as `Transform Name ID`.

   Incoming claim type: **E-Mail Address**

   Outgoing claim type: **Name ID**

Rule 3

1. **Add Rule** to set the scope of the Stellar Cyber user as Root.
2. For the claim rule template choose **Send Claims Using a Custom Rule**, and then select **Next**.
3. Enter the following in Add Transform Claim Rule Wizard and then select **Finish**:

   Claim rule name: Enter a name such as `Stellar Scope (Root)`.

   Custom rule: `=> issue(Type = "stellar_scope", Value = "root");`

Rule 4

1. **Add Rule** to set the scope of the Stellar Cyber user as a tenant.

2. For the claim rule template choose **Send Claims Using a Custom Rule** and then select **Next**.
3. Enter the following in Add Transform Claim Rule Wizard and then select **Finish**:

   Claim rule name: Enter a name such as `Stellar Scope (Tenant)`.

   Custom rule: `=> issue(Type = "stellar_scope", Value = "tenant");`

Rule 5

1. **Add Rule** to set the scope of the user as a Stellar Cyber partner.
2. For the claim rule template choose **Send Claims Using a Custom Rule** and then select **Next**.
3. Enter the following in Add Transform Claim Rule Wizard and then select **Finish**:

   Claim rule name: Enter a name such as `Stellar Scope (Partner)`.

   Custom rule: `=> issue(Type = "stellar_scope", Value = "partner");`

Rule 6

1. **Add Rule** to set the administrative privilege of the Stellar Cyber user as Super Admin.
2. For the claim rule template choose **Send Claims Using a Custom Rule** and then select **Next**.
3. Enter the following in Add Transform Claim Rule Wizard and then select **Finish**:

   Claim rule name: Enter a name such as `Stellar Privilege (Super_Admin)`.

   Custom rule: `=> issue(Type = "stellar_privilege", Value = "super_admin");`

Rule 7

1. **Add Rule** to set the Stellar Cyber tenant name for the user.
2. For the claim rule template choose **Send Claims Using a Custom Rule** and then select **Next**.
3. Enter the following in Add Transform Claim Rule Wizard and then select **Finish**:

   Claim rule name: Enter a name such as `Stellar Tenant (tenant-name)`.

   Custom rule: `=> issue (Type = "stellar_tenant", Value = "tenant-name");`

   Replace `tenant-name` with the actual name of the tenant.

4. To save the set of rules, select **OK**.

Stellar Cyber

Configure Stellar Cyber to authenticate users using SSO (SAML) with Active Directory Federation Services.

1. Log in to Stellar Cyber and select **System | ORGANIZATION MANAGEMENT | Settings**.

2. In the **Authentication Settings** section, select **SSO (SAML)** as the **Authentication Method**.
3. Select **Metadata URL** or **Manual Config**:

   If you select **Metadata URL**:

   - **Issuer URL**: If this setting is present, enter the Stellar Cyber URL.
   - **Metadata URL**: Paste the URL you copied from the IdP. The URL must begin with either `https://` or `http://`. Different vendors use different names for the Metadata URL:

Identity Provider	Term for Metadata URL
Active Directory Federation Services	Federation Metadata URL
Microsoft Entra ID	App Federation Metadata URL
Okta	Metadata URL
OneLogin	Issuer URL
Rippling	Metadata URL

   If you select **Manual Config**:

   - **Issuer URL**: If this setting is present, enter the Stellar Cyber URL.
   - **Entry Point**: Paste the entry point URL you copied from the IdP.

     You must include **http://** or **https://** before the URLs. Different vendors use different names:

Identity Provider	Term for Entry Point URL
Active Directory Federation Services	SAML Endpoint
Microsoft Entra ID	Login URL or SAML-P Sign-on Endpoint
Okta	Sign on URL
OneLogin	SAML 2.0 Endpoint (HTTP)
Rippling	SAML 2.0 Endpoint (HTTP)

   - **IDP Certificate**: Upload the certificate file you downloaded from the IdP.
4. Select **Require Signed Response** only if the IdP requires it.

   Verify whether your IdP requires signed SAML responses. Some IdPs, such as Okta, require them by default. If so, then enable **Require Signed Response** here as well.
5. Select **Allow Clock Skew** to allow for system time differences between Stellar Cyber and your IdP. Authentication messages have an expiration. If the system times on Stellar Cyber and your IdP are not synchronized, the messages might expire before they even get to Stellar Cyber. The result is that users cannot log in, because they cannot authenticate.
6. Choose your IdP setting: **Authentication Only** or **Authentication and Authorization**. Note the following:

- A Global selection of **Authentication and Authorization** applies to all users (r partner, and tenant), so the option to change authentication method for a specific tenant is not applicable when the Global method is set to **Authentication and Authorization**. You cannot log in to Tenant SSO when Global SSO is set to **Authentication and Authorization**. If you want to use SSO but also allow local users and tenant override, you must set the Global authentication method either to **Local** or to use the IdP with **Authentication Only**.
- Although you can customize SSO configuration on a per-tenant basis, the **Authorization** capability is only supported at the global level. Overrides you make at the tenant level are for **Authentication** only, so the toggle for **Authentication and Authorization** is not offered in the tenant editor.
- The authentication method for partners is the same as that for root users. Any authentication overrides for tenant-level users in a tenant group have no effect on the authentication method for the partners who manage the group.

- Choose **Authentication Only** for Stellar Cyber to authenticate users from your IdP, but manage scope and privilege locally. If you choose this, you must create the user in Stellar Cyber before adding them to your IdP.
- Choose **Authentication and Authorization** for Stellar Cyber to authenticate users from your IdP, along with their scope and level of privilege. You must configure authorization on your IdP before enabling this, otherwise users cannot log in. If you choose this, you do not need to create the user in Stellar Cyber. Stellar Cyber creates the user and assigns scope and privilege based on the information passed from the IdP.

  When Global Settings is configured for **Authentication & Authorization**, the option to **Create** new users manually is hidden because new users must come from the IdP source.

7. Choose a **Two-Factor Authentication** option that matches your IdP configuration:
   - **Off**: If you choose this option, Stellar Cyber user accounts are not offered a 2FA option.
   - **Mandatory**: If you choose this option, all users for every tenant are required to use 2FA when logging in to Stellar Cyber.
   - **Optional**: If you choose this option:
     - The 2FA option can be customized for individual tenants under **System | ORGANIZATION MANAGEMENT | Tenants**.
     - Individual users can choose to enable 2FA under their **User Profile** in the Stellar Cyber UI.
     - You can enforce 2FA for specific users under **System | ORGANIZATION MANAGEMENT | Users** when adding or editing a

user



- The overall Global Settings for 2FA affect authentication for partners and tenant users. For example, if 2FA is **Mandatory**, all users must use 2FA.
- Enabling 2FA here is independent of what you have configured on your SSO service. Enabling it here causes a separate 2FA prompt to be displayed upon logging in to Stellar Cyber.
- The 2FA page from Stellar Cyber refers to use of Google Authenticator, but other authenticator applications also work.

8. Review your settings and then **Submit** them.

© 2026 Stellar Cyber . All rights reserved.