
Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Converting Sensor Storage to Use Encryption in AWS


This topic describes how to convert the storage volume for a sensor deployed in AWS from unencrypted to encrypted. You do this by taking a snapshot of your sensor's unencrypted storage volume, creating a copy of it, reconfiguring the copy to use encryption, and then replacing the existing storage volume with the encrypted volume you just created. Use the following procedure:

1. Log in to the AWS EC2 Console and navigate to **Instances**.
2. Click the **Instance ID** for the sensor instance whose storage you want to encrypt.
3. Click on the **Storage** tab and then click the instance's **Volume ID**.




   The **Elastic Block Store | Volumes** page appears.


4. Click the **Volume ID** in the list.
5. Select **Create snapshot** from the **Actions** dropdown.




6. Supply a description for your snapshot and click Create snapshot to save it to the list.




7. Once the snapshot has been created, select its entry in the **Snapshots** list and choose **Copy snapshot** from the **Actions** dropdown.




8. Check the **Encrypt this snapshot** option in the Copy snapshot dialog box.




The new snapshot appears in the list with an entry of **Encrypted** in the **Encryption** column.




9. Select the entry for your encrypted snapshot and choose **Create volume from snapshot** from the **Actions** dropdown :




10. Note that the **Encrypt this volume** option is checked in the dialog box that appears and click **Create volume**.




The new encrypted volume appears in the **Volumes** list.




11. Navigate to the **Instances** list, select the entry for your sensor, and choose **Stop instance** from the **Instance state** dropdown.




12. Return to the **Volumes** list, select the entry for the unencrypted volume currently in use, and choose **Detach volume** from the **Actions** dropdown. Then, click **Detach** on the confirmation prompt that appears.




13. Return to the **Instances** list, click the entry for your sensor, and select the **Storage** tab. Notice that the **Block device**s list shows no attached block devices.




14. Return to the **Volumes** list, select the entry for the encrypted volume, and choose **Attach volume** from the **Actions** dropdown.



15. The **Attach Volume** dialog box appears. Use the **Instance** dropdown to select the sensor instance where you want to attach the encrypted volume. Ensure that **Device name** is set to **/dev/sda1** and click **Attach volume**.



16. Return to the **Instances** list, select the entry for the sensor with the new encrypted volume, and select **Start instance** from the **Instance state** dropdown to start it.



© 2026 Stellar Cyber . All rights reserved.