Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Deep Instinct Connectors

Connectors allow Stellar Cyber to collect data from external sources and add it to the data lake. Review the content in this topic to understand what type of data can be collected and acted upon for this connector type.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Deep Instinct

Capabilities

- Collect: **Yes**
- Respond: **Yes**
- Native Alerts Mapped: **Yes**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	API
Devices	Syslog, Assets	`https://<customername>.customers.deepinstinctweb.com/api/v1/devices`
Events	Syslog, Alerts	`https://<customername>.customers.deepinstinctweb.com/api/v1/events/`
Suspicious Events	Syslog	`https://<customername>.customers.deepinstinctweb.com/api`

Content Type	Index	API
		`/v1/suspicious-events/`

Domain

https://<Hostname>

where <Hostname> is a variable from the configuration of this connector

Response Actions

Action	Required Fields	API
Contain (Isolate) Host	`deep_instinct_asset` and `deep_instinct.id` or `deep_instinct_suspiciousevent` and `device_id` or `deep_instinct_maliciousevent` and `device_id`	`https://<customername>.customers.deepinstinctweb`

Action	Required Fields	API
		.com/api/v1/devices/actions/isolate-from-network https://<custo

Action	Required Fields	API
		mernname>.customers.deepinstinctweb.com/api/v1/devices/actions/

Action	Required Fields	API
		release-from-isolation

Third Party Native Alert Integration Details

Devices	This content is not applicable for alerts.

Events	Yes. Records with MITRE | ATT&CK values are de-duplicated, enriched with Stellar Cyber fields, and mapped to the Stellar Cyber `xdr_event` record. If the incoming Tactic or Technique are blank, the following values are assigned in Stellar Cyber:
	`tactic_name= XDR Malware`
	`technique_name = XDR Miscellaneous Malware`

Suspicious Events	No.

For details, see Integration of Third Party Native Alerts.

Required Credentials and Configurations

- Hostname and API Token
  - For Collect, the API token must be created with at least READ_ONLY permission
  - For Respond, READ_AND_REMEDIATION permissions are required

Locating Records

Use the following to query for records:

- **msg_origin.vendor**: `deep_instinct`
- **msg_origin.category**: `asset`, `endpoint`
- **msg_origin.source**: `deep_instinct`
- **msg_class**: `deep_instinct_asset`, `deep_instinct_maliciousevent`, `deep_instinct_suspiciousevent`

Adding a Deep Instinct Connector


To add a Deep Instinct connector:

1. Obtain a Deep Instinct API token
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion


Obtaining a Deep Instinct API Token

As part of this procedure, you specify the credentials of an account on the Deep Instinct server that will be used to retrieve data.


1. Log into your **Deep Instinct Dashboard** as an administrative user. Make note of the **fully qualified domain name** portion of the URL you used to log in (e.g., just mycompany.customer.deepinstinct.com). You will need this when you configure the Stellar Cyber connector.
2. From the **Dashboard** navigation pane, select **Integration & Notification**.




3. In the pane that loads, click the link for **API Connectors**, shown above.
4. Click the button to Create an API Connector.



5. In the **Add API Connector** dialog, create a name, select the Tenants you want to be able to use this API connector with Stellar Cyber and specify the Permissions. The minimum permission required is READ_ONLY. For Respond actions , you must include READ_AND_REMEDIATION permissions.
6. Click **OK** to save the settings and create the API Key. The API Connectors pane displays.




7. Click the API key you created to display it, then copy the key. Save that key for use when you configure the Stellar Cyber connector.




Adding the Connector in Stellar Cyber

To add the Deep Instinct connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System** | **INTEGRATIONS** | **Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **Deep Instinct** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. Choose whether you want to only **Collect** or also **Respond**.
7. Enter a **Name**.

Notes:


- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.

12. Enter the **Hostname**. This is the FQDN portion of the URL you used for your Deep Instinct dashboard login, above (for example, mycompany.customer.deepinstinct.com).
13. Do not include https in the field.
14. In the **API Token** field, enter the API key you created above.
15. Choose the **Interval (min)**. This is how often the logs are collected.
16. Choose the **Content Type**. The logs for **Devices**, **Events**, and **Suspicious Events** are supported.
17. Click **Next**. The final confirmation tab appears.



18. Click **Submit**.


The new connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Set the **Indices** to match the type of content you collected:

   - For **Devices**, change the **Indices** to **Syslog** or **Assets**. Note that hosts discovered through this connector show Deep Instinct as a data source.
   - For **Events**, change the **Indices** to **Syslog** or **Alerts**.
   - For **Suspicious Events**, change the **Indices** to **Syslog**.

© 2026 Stellar Cyber . All rights reserved.