Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Duo Security Connectors 6.3.0

This connector allows Stellar Cyber to collect data from external sources and add the records to the data lake.

Integrating Duo with Stellar Cyber provides advanced identity and access management capabilities, enabling organizations to manage user access and security policies across their network, and providing enhanced security controls and compliance features. By combining Duo's multi-factor authentication with Stellar Cyber's advanced security analytics and machine learning algorithms, organizations can effectively defend against cyber threats.

Note that the API for Duo Security is not supported for deployments configured to communicate through an HTTP proxy.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Duo Security

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **Yes** 6.3.0
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records
Administrator Authentication Telephony	Syslog	msg_class: `duosecurity_administrator`

Content Type	Index	Locating Records

Trust Monitor		`duosecurity_authentication`
		`duosecurity_telephony`
		`duosecurity_trust_monitor`
		
		msg_origin.source:
		`duosecurity`
		
		msg_origin.vendor
		`cisco`
		
		msg_origin.category:
		`endpoint`

Domain

N/A

Response Actions

N/A

Third Party Native Alert Integration Details 6.3.0

This connector ingests logs from Duo Security to get the raw alerts that are stored in the Syslog index. Select the Trust Monitor content type.

Stellar Cyber maps Duo Trust Monitor events. The events are read from the Syslog index, enriched with Stellar Cyber fields, and mapped (with deduplication) to the Alerts index.

Deduplication is by `duosecurity.sekey`.

For details, see Integration of Third Party Native Alerts.

Required Credentials and Configurations

- Hostname, Integration Key, and Security Key

Locating Records 6.3.0

To search the alerts in the Alerts index or the Original Records in the Syslog index, use the query: `msg_class: duosecurity_trust_monitor AND _exists_:event.threat.name`

Adding a Duo Security Connector

To add a Duo Security connector:


1. Configure Duo Security application protection
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Configuring Duo Security Application Protection


To configure Duo Security application protection:

Use our example as a guide, as you might be using a different software version.


1. Log in to Duo.
2. If you don't have the **Admin API** application available, contact Duo technical support and request access. When you get access, continue.
3. Click **Applications**. The **Application** menu expands.




4. Click **Protect an Application**. The **Protect an Application** page appears.



5. Find **Admin API**. If you start typing in the search bar, the available applications narrow to match the text you type.
6. Click **Protect** on the **Admin API** row. The **Admin API** page appears.



7. Copy the **Integration key**, **Secret key**, and **API hostname**. You need all of these when configuring Stellar Cyber.
8. Configure the **Settings**. At a minimum, select the following permissions: **Grant read information**, **Grant read log**, and **Grant read resource**.




9. Click **Save**.


Adding the Connector in Stellar Cyber

To add a Duo Security connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



   The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **IdP** from the **Category** dropdown.
5. Choose **Duo Security** from the **Type** dropdown.




   The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.

11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.


12. Enter the **Hostname**. This is the Duo API hostname you noted above in Configuring Duo Security Application Protection.

Do not include https in this field.

13. Enter the **Integration Key** you noted above.
14. Enter the **Security Key** you noted above.
15. Choose the **Interval (min)**. This is how often the logs are collected.

Note that default setting is 5 minutes, which is the minimum recommended interval for this connector type.

16. Choose the **Content Type** you would like to collect. The logs for **Administrator**, **Authentication**, **Telephony**, and **Trust Monitor** are supported.
17. Click **Next**. The final confirmation tab appears.



18. Click **Submit**.


The new connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** to **Syslog**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.