Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Microsoft Defender for Endpoint Connectors

Microsoft Defender for Endpoint connectors allow Stellar Cyber to ingest logs or issue response actions with Microsoft Defender for Endpoint and add the records to the data lake. There can be any number of Microsoft Defender for Endpoint connectors active.

This connector requires one of the following Microsoft endpoint security plans: Microsoft Defender for Endpoint Plan 1 (P1) or Microsoft Defender for Endpoint Plan 2 (P2). To learn about plans, refer to Compare Microsoft endpoint security plans.

There may be two data sources for third party native alerts if you have integrated both Microsoft Defender for Endpoint (this connector) and Windows Defender Antivirus (free version).

If a tenant is using the Microsoft Defender for Endpoint connector and the status of the connector in **System | INTEGRATIONS | Connectors** is green, alerts from Windows Defender Antivirus will be suppressed in order to remove duplicate logs. If the status of the connector is not green, alerts from Windows Defender Antivirus will not be suppressed.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Microsoft Defender for Endpoint

Capabilities

- Collect: **Yes**
- Respond: **Yes**
- Native Alerts Mapped: **Yes**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records
Alerts	Syslog	msg_class: `microsoft_defender_alerts`
Host	Assets (for Host)	`microsoft_defender_host`

Vulnerabilities	Scans (for Vulnerabilities) 6.1.0	`microsoft_defender_vulnerabilities`
		
		msg_origin.source:
		`microsoft_defender`
		
		msg_origin.vendor:
		`microsoft`
		
		msg_origin.category:
		`endpoint`

Domain

https://login.microsoftonline.com
<API Endpoint URL>
where <API Endpoint URL> is a variable from the configuration of this connector

Response Actions

Action	Required Fields
Contain Host (for Host and Alerts)	`microsoft_defender.id` (for Host data) `microsoft_defender.machineId` (for Alerts data)

The required permission for response actions is `Machine.Isolate`.

Third Party Native Alert Integration Details

The Microsoft Defender ATP alerts are mapped to the Stellar Cyber Syslog Index. Select the Alerts content type.

Deduplication is by `tenantid`, `host.ip`, `host.name`, and `microsoft_defender.id`.

For details, see Integration of Third Party Native Alerts.

For full alert integration of Microsoft Defender for Endpoint, the following licenses are required:

- Microsoft Defender for Endpoint Plan 1 (P1)
- Microsoft Defender for Business

Required Credentials and Configurations

- Office 365 Subscription Plan, API Endpoint URL, Client ID with permissions enabled (for permissions see, Creating an App in Microsoft Entra ID), Directory ID, and Client Secret

Locating Records

Use the following to query for records:

- **msg_origin.source**: `microsoft_defender`
- **msg_class**: `microsoft_defender_alerts`

To search the alerts, use the query: `msg_class: microsoft_defender_alerts AND (microsoft_defender.detectionSource: WindowsDefenderAv OR microsoft_defender.detectionSource: WindowsDefenderAtp)`

Adding a Microsoft Defender for Endpoint Connector

To add a Microsoft Defender for Endpoint connector:

1. Create an app
2. Gather information
3. Add the connector in Stellar Cyber
4. Test the connector
5. Verify ingestion

Creating an App in Microsoft Entra ID

You must create an app in Microsoft Entra ID (formerly Azure Active Directory) that can access Microsoft Defender for Endpoint. Refer to the following article: https://docs.microsoft.com/en-us/windows/security/threat-protection/microsoft-defender-atp/exposed-apis-create-app-webapp.

Enable the following role for the API:

- `Vulnerability.Read.All`

Also enable the following roles for the application:

- `Machine.Isolate`
- `Event.Write`
- `Machine.Scan`
- `Url.Read.All`
- `Ip.Read.All`
- `Ti.ReadWrite`
- `User.Read.All`
- `Machine.ReadWrite.All`
- `Machine.StopAndQuarantine`
- `Alert.Read.All`
- `File.Read.All`
- `Machine.Read.All`
- `Alert.ReadWrite.All`
- `AdvancedQuery.Read.All`

Gathering the Microsoft Entra ID Information

The following is the Microsoft Entra ID (formerly Azure AD) information to gather as you create the app:

- **API Endpoint URL**—this is the API URL for the server closest to your region:
  - https://api-us.securitycenter.microsoft.com


- https://api-eu.securitycenter.microsoft.com
- https://api-uk.securitycenter.microsoft.com
- https://au.api.securitycenter.microsoft.com
- https://swa.api.securitycenter.microsoft.com

- **Client ID**—this is the Application (client) ID
- **Directory ID**—this is the Directory (tenant) ID
- **Client Secret**—this is the token you generated


Adding the Connector in Stellar Cyber

With the access information handy, you can add a Microsoft Defender for Endpoint connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **Microsoft Defender for Endpoint** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. Choose the **Function**: **Collect** to collect logs; **Respond** to contain hosts. If you want **Respond**, choose both **Collect** and **Respond** because **Respond** uses fields present in Alerts and Host data to perform the Contain Host action.
7. Enter a **Name**.

Notes:
- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name. If you create an automated response action, note that the Tenant for this connector (Collect and Respond) must be within the Tenant for the action. You can use All Tenants or match specific tenants.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.

12. Select the applicable **Office 365 Subscription Plan** from the menu and the **API Endpoint URL**:

- **Enterprise Plan**—Select the **API Endpoint URL** for the server closest to your region for the best performance as listed in Gathering the Microsoft Entra ID Information
- **GCC Government Plan**—Select the **API Endpoint URL** (the URL is: https://api-gcc.securitycenter.microsoft.us)
- **GCC High Government Plan**—Select the **API Endpoint URL** (the URL is: https://api-gov.securitycenter.microsoft.us)
- **DoD Government Plan**—Select the **API Endpoint URL** (the URL is: https://api-gov.securitycenter.microsoft.us)

To learn about Office 365 government plans, refer to the following documentation: https://learn.microsoft.com/en-us/defender-endpoint/gov?view=o365-worldwide

13. Enter the **Client ID** you noted above.
14. Enter the **Directory ID** you noted above.
15. Enter the **Client Secret** you noted above.
16. Enter the **Interval (min)**. This is how often the logs are collected.

    If data is not being pulled, you can increase the interval, for example, to 10 minutes.


17. (Optional) Choose the **Lookback Time (hr)**. This is how far back in time, in hours, the connector will pull data when it either starts or restarts. (Configuring this field has no impact when the connector is running, only when the connector is started for the first time or when it is stopped and restarted.) This field is for the **Alerts** and **Vulnerabilities** content types since the **Host** content type already looks back in time. The default is 720 hours, or one month. The minimum is 1 and maximum has no limit. 6.0.0

    Use caution if setting the **Lookback Time** to a high value. It may take a long time to pull the data and may result in old alert types being retriggered.

18. Choose the **Content Type** you would like to collect. The logs for **Alerts**, **Host**, and **Vulnerabilities** are supported.

    The **Vulnerabilities** content type is sent to the **Assets | Asset Analytics** page, which shows the relationship between assets and vulnerabilities.

19. Click **Next**. The final confirmation tab appears.



20. Click **Submit**.


The new connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:

   - For **Alerts**, change the **Indices** to **Syslog**.
   - For **Host**, change the **Indices** to **Assets**. Hosts discovered through this connector show Microsoft Defender for Endpoint as a data source.
   - For **Vulnerabilities**, change the **Indices** to **Scans**.

   The table immediately updates to show ingested Interflow records.

If you configured the connector Respond actions, refer to **External Actions: Contain Host** to understand how to work with the Contain Host feature.

© 2026 Stellar Cyber . All rights reserved.