Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

# Configuring Mimecast API 1.0 Connectors

This connector allows Stellar Cyber to ingest Mimecast logs and add the records to the data lake.

Mimecast integration with Stellar Cyber provides advanced threat detection and response capabilities, combining Mimecast's email security solutions with real-time threat intelligence and automated response workflows to improve incident response and threat mitigation.

There can be any number of Mimecast connectors active.

This connector uses Mimecast API 1.0.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

## Connector Overview: Mimecast API 1.0

### Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **Yes**
- Runs on: **DP**
- Interval: **5 minutes**

### Collected Data

| Content Type | Index | Locating Records |
|---|---|---|
| MTA Log | Syslog | msg_class:<br>`mimecast_email`<br>`mimecast_email_attachment_protect_log`<br>`mimecast_email_av_log` |

| Content Type | Index | Locating Records |
| --- | --- | --- |
| |  | `mimecast_email_impersonation_protect_log`<br>`mimecast_email_internal_email_protect_log`<br>`mimecast_email_url_protect_log`<br><br>msg_origin.source:<br>`mimecast_email`<br><br>msg_origin.vendor<br>`mimecast`<br><br>msg_origin.category:<br>`email` |

## Domain

https://api.mimecast.com/api/login/discover-authentication

## Response Actions

N/A

## Third Party Native Alert Integration Details

This connector ingests logs from Mimecast (API version 1.0) to get the raw alerts that are stored in the Syslog index. Select the MTA Log content type.

Stellar Cyber maps Mimecast alerts. The alerts are read from the Syslog index, enriched with Stellar Cyber fields, and mapped (with deduplication) to the Alerts index.

Deduplication is by the following fields:

- Attachment Protect and AV/AntiVirus—`tenantid`, `srcip`, `file.hash.md5`, `email.sender.address`, and `email.recipient.addresses`
- Impersonation Protect, Internal Email , and Malicious Receipt Log—`tenantid` and `mimecast.aCode`
- URL Protect—`tenantid`, `srcip`, `url`, `email.sender.address`, and `email.recipient.addresses`

For details, see Integration of Third Party Native Alerts.

## Required Credentials and Configurations

- App ID, App Key, Access Key, Secret Key, and Administrator Email

## Locating Records

To search the alerts in the Alerts index, use the query `msg_class: mimecast_*`

To search the Original Records in the Syslog index, use the `msg_class` and alert key fields (refer to Key Fields for Third Party Native Alert Types):

- Attachment Protect logs: `msg_class.keyword: mimecast_email_attachment_protect_log`
- AV logs: `msg_class.keyword: mimecast_email_av_log`
- Impersonation Protect logs: `msg_class.keyword: mimecast_impersonation_protect_log`

- Internal Email Protect logs: `msg_class.keyword: mimecast_email_internal_email_protect_log`
- Receipt logs: `_exists_: mimecast.Virus AND _exists_: mimecast.aCode AND msg_class.keyword: mimecast_email`
- URL Protect logs: `msg_class.keyword: mimecast_email_url_protect_log`
- Other logs: `msg_class.keyword: mimecast_email`

# Adding a Mimecast Connector

To add a Mimecast connector:

1. Configure Mimecast logs
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

# Configuring Mimecast Logs

You must configure Mimecast logs before you add the connector in Stellar Cyber.

To configure Mimecast logs:

1. Log in to Mimecast.
2. Follow the Mimecast online instructions to Enable logging for your account.
3. Refer to the following site (https://community.mimecast.com/s/article/Managing-API-Applications-505230018) for guidance preparing for use of the Mimecast API and gathering the info below:
    - App ID
    - App Key
    - Access Key
    - Secret Key


Refer to the following recommendations:

- Generate the Access Key and Secret Key before adding the user to any Basic Administrator role.
- If the Access Key and Secret Key need to be generated, first remove the user from any Basic Administrator role and add the user back after obtaining the new keys.


# Adding the Connector in Stellar Cyber

To add a Mimecast connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.




The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Email** from the **Category** dropdown.
5. Choose **Mimecast API 1.0** from the **Type** dropdown.





The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

Notes:


- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.




The asterisk (*) indicates a required field.

12. Enter the **App ID** you noted above in Configuring Mimecast Logs.
13. Enter the **App Key** you noted above.
14. Enter the **Access Key** you noted above.
15. Enter the **Secret Key** you noted above.
16. Enter the **Administrator Email**.
17. Choose the **Content Type** you would like to collect. The logs for **MTA Log** are supported.
18. Click **Next**. The final confirmation tab appears.




19. Click **Submit**.

The new connector is immediately active.


A new Mimecast connector automatically collects logs for the last 7 days. It can take a few days for the logs to be current.

# Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !




Failure with summary of issue:




Show More example detail:




If the test fails, the common HTTP status error codes are as follows:

| HTTP Error Code | HTTP Standard Error Name | Explanation | Recommendation |
|---|---|---|---|
| 400 | Bad Request | This error occurs when there is an error in the connector configuration. | Did you configure the connector correctly? |
| 401 | Unauthorized | This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API. | Did you enter your credentials correctly?<br>Are your credentials expired?<br>Are your credentials entitled or licensed for that specific resource? |
| 403 | Forbidden | This error occurs when the permission or scope is not correct in a valid credential. | Did you enter your credentials correctly?<br>Do you have the required role or permissions for that credential? |
| 404 | Not Found | This error occurs when a URL path does not resolve to an entity. | Did you enter your API URL correctly? |

| HTTP Error Code | HTTP Standard Error Name | Explanation | Recommendation |
|---|---|---|---|
| 429 | Too Many Requests | This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded. | The server or user license/quota will eventually recover. The connector will periodically retry the query.<br>If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas. |

For a full list of codes, refer to HTTP response status codes.

# Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** to **Syslog**.

   The table immediately updates to show ingested Interflow records.


© 2026 Stellar Cyber . All rights reserved.