Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Proofpoint TAP Connectors

This connector allows Stellar Cyber to ingest logs from Proofpoint Targeted Attack Protection (TAP) and add the records to the data lake. This connector integrates with the SIEM API and the Threat API to provide information from Proofpoint TAP.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Proofpoint TAP

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **Yes**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records

Events
Threats
	Syslog	msg_class:
		`proofpoint_tap_event`
		`proofpoint_tap_threat`
		
		msg_origin.source:
		`proofpoint_tap`
		
		msg_origin.vendor:
		`proofpoint`
		
		msg_origin.category:
		`email`

Domain

<Host URL>

where <Host URL> is a variable from the configuration of this connector

Response Actions

N/A

Third Party Native Alert Integration Details

This connector ingests logs from Proofpoint Targeted Attack Protection (TAP) to get the raw alerts that are stored in the Syslog Index. Select the Events content type.

Stellar Cyber maps Proofpoint TAP alerts. The alerts are read from the Syslog Index, enriched with Stellar Cyber fields, and mapped (with deduplication) to the Alerts Index.

Deduplication is by `email.from.address` and `email.sender.address`.

There are the following event types:

- Proofpoint TAP messageBlocked
- Proofpoint TAP messageDelivered
- Proofpoint TAP clickBlocked
- Proofpoint TAP clickDelivered

For details, see Integration of Native Third Party Alerts.

Required Credentials and Configurations

- Host URL, Service Principal, and Secret

Locating Records

To search the alerts in the Alerts index or to search the Original Records in the Syslog index, use the query: `msg_class: proofpoint_tap_event`

Adding a Proofpoint TAP Connector

To add a Proofpoint TAP connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

You can also Disable Users.

Obtaining Proofpoint TAP Credentials


Before you configure the connector in Stellar Cyber, you must obtain the following Proofpoint TAP credentials:

- Service Principal
- Secret


Follow guidance on Proofpoint TAP documentation.

To generate Proofpoint TAP service credentials.

1. Log in as an administrative user to https://threatinsight.proofpoint.com.
2. Navigate to **Settings | Connected Applications**.




3. Click **Create New Credential**.
4. Enter a name for the new credential set and click **Generate**.



5. Copy the **Service Principal** and the **Secret**. You need these for the Stellar Cyber connector configuration.


Make sure to copy these credentials as they will not be available after the following dialog is closed.




Adding the Connector in Stellar Cyber

To add a Proofpoint TAP connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Email** from the **Category** dropdown.
5. Choose **Proofpoint Targeted Attack Protection** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

Notes:


- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.

12. Enter the **Host URL**, for example, https://tap-api-v2.proofpoint.com.
13. Enter the **Service Principal** you noted above in Obtaining Proofpoint TAP Credentials.
14. Enter the **Secret** you noted above.
15. Choose the **Interval (min)**. This is how often the logs are collected.
16. Choose the **Content Type** you would like to collect. The logs for **Events** and **Threats** are supported.
17. Click **Next**. The final confirmation tab appears.



18. Click **Submit**.


The new connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.


   The **Interflow Search** tab appears.

2. Change the **Indices** to **Syslog**.

   The table immediately updates to show ingested Interflow records.


(Optional) Disabling Users

You can disable an associated Active Directory (AD) user account that is listed in the **Recipient Address(es)** key field in a Proofpoint TAP alert.




To configure the disabling an AD user account:

1. Configure the Proofpoint TAP connector as described in this document.
2. Configure the Active Directory connector as described in Configuring Active Directory Connectors. For **Function**, select both **Collect** and **Respond**.




3. Configure the Disable User action as described in External Actions: Disable User. In the **Disable User** field, enter `email.recipient.addresses`.




The Disable User action will be applied to data that has a value in the Email Recipient Addresses for a `msg_class` of `proofpoint_tap_event`.

You can click the JSON tab to see the `email.recipient.addresses`.



Or you can navigate to **Threat Hunting** to see the **Email Recipient Addresses**. You may have to add the column to the table.



4. On the AD Server, make sure you have a user with the same email address. In this example, it is ceo@exec.vogon.science.

The `email.recipient.addresses` can be a list. When there are multiple recipients in the list, the AD response action, Disable User, will be applied to all recipient addresses in the list.

© 2026 Stellar Cyber . All rights reserved.