Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Sophos Central Connectors

This connector allows Stellar Cyber to collect data from Sophos Central and add the records to the data lake and, optionally, to issue the contain a host response action.

Integration with Sophos enables organizations to monitor and detect security threats across their network, including endpoints, servers, and cloud infrastructure, while providing quick incident response capabilities. By combining Sophos' security solutions with Stellar Cyber's advanced security analytics and machine learning algorithms, organizations can effectively defend against cyber attacks.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Sophos Central

Capabilities

- Collect: **Yes**
- Respond: **Yes**
- Native Alerts Mapped: **Yes**
- Runs on: **DP**
- Interval: **Configurable** (applicable to Collect only)

Collected Data

Content Type	Index	Locating Records

Alerts
Events
	Syslog
	Assets (for Alerts and Events)
		msg_class:
		`sophos_alerts`
		`sophos_events`
		
		msg_origin.source:
		`sophos_alerts`

Content Type	Index	Locating Records

		`sophos_events`
		
		msg_origin.vendor
		`sophos`
		
		msg_origin.category:
		`endpoint`

If there is asset information in the logs for Events and Alerts, the detected assets are reported in the Assets Index.

Domain

<API Access URL>

where <API Access URL> is a variable from the configuration of this connector

Response Actions

Action	Required Fields
Contain (Isolate) Host	`sophos.hostid_assetid (endpoint_id)`

Third Party Native Alert Integration Details

This connector ingests logs from Sophos Central to get the raw alerts that are stored in the Syslog index. Select the Alerts and Events content types.

Stellar Cyber maps Sophos alerts and events. The alerts and events are read from the Syslog index, enriched with Stellar Cyber fields, and mapped (with deduplication) to the Alerts index.

Deduplication is by `tenantid` and `sophos.id`.

The subtype uses `sophos.type`. Only Endpoint-related alerts and events are integrated.

For details, see Integration of Third Party Native Alerts.

Required Credentials and Configurations

If the Collect function only is selected, or the Respond function only, or both the Collect and Respond functions:

- API Key / Header Auth Method: API Access URL, x-api-key header value, and Authorization header value
- Client ID / Client Secret Auth Method: Account Type of Tenant, Client ID, and Client Secret

If the Collect function only is selected:

- Account Type of Organization, Client ID, and Client Secret

Respond actions are not supported with an Account Type of Organization.

Locating Records

To search the alerts or events in the Alerts index or to search the Original Records in the Syslog index, use the queries:

- `msg_class: sophos_alerts AND event.type: Endpoint`
- `msg_class: sophos_events AND event.type: Endpoint`

Adding a Sophos Central Connector

To add a Sophos Central conne:

1. Enable access to Sophos Central
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Enabling Sophos Central Access


Before you create a Sophos Connector, you must create a Token and get the key values.

Use our example as a guideline, as you might be using a different software version.


1. Login to Sophos Central Website (https://central.sophos.com) as the user you want to associate with your Stellar Cyber connector.
2. If you are going to configure the Stellar Cyber Sophos connector to Collect only, you can use an API Access URL method for authentication. If you anticipate using the Respond (with or without the Collect function), you must use Client ID/Client Secret for authentication. Select the appropriate section below to obtain the needed credentials.

   For API Access URL...


   Legacy API Token Management is being retired.


   a. Navigate to **Global Settings > API Token Management**.

   b. Click **Add Token**.

c. In the dialog that displays, specify a **Name** for your new Stellar Cyber Sophos connector.



d. Click **Save**.

e. When the Token Summary displays, make note of the following for use in Stellar Cyber.



- **API Access URL**
- Headers for **x-api-key** and for **Authorization**

Use the diagram above to identify which parts of the header strings to use. You do not need to save the **API Access URL + Headers** string.

For Client Secret / Client ID...


Follow the guidance in the Sophos Central documentation for API Credentials Management.

a. Navigate to **Global Settings**.

b. Go to **Access Control** > **API Credentials Management**.

c. Click **Add Credential**.

d. Enter a **Name** and optional **Description** to help you identify the credential later.




e. From the **Role** menu, select **Service Principal ReadOnly**.

f. Click **Add**.

g. The **API Credential Summary** displays your **Client ID** and **Client Secret**.

The **Client Secret** is only displayed once.




h. Copy the **Client ID** and **Client Secret**.


Adding the Connector to Stellar Cyber

With the information ready, you can add a Sophos Central connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **Sophos Central** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For **Function**, enable **Collect**. If you want to be able to contain hosts, also check the box for **Respond**.
7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.


8. Choose a **Tenant Name**.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears. There is a toggle for **Auth Method**. Depending on what you selected as the **Function** in the previous screen, the authentication method: either **API Key / Header** or **Client ID / Client Secret**, will be selected.

    The configuration fields for the **API Key / Header** Auth Method are as follows:



    The asterisk (*) indicates a required field.

    The configuration fields for the **Client ID / Client Secret** Auth Method are as follows.



    The asterisk (*) indicates a required field.

12. For the **API Key/Header** Auth Method:
    a. Enter the **API Access URL** you obtained above.
    b. Using the **Headers** information you noted above, enter the **x-api-key header value** and the **Authorization header value**.

       The Authorization header value must include the string "Basic".

13. For the **Client ID / Client Secret** Auth Method:

The Sophos API is a Tenant API. This Sophos Central connector pulls data for individual Sopho nants (not for organizations or partners).

If you have a multi-tenant instance, log in with that tenant and create the API credential.

a. Choose an **Account Type**. Select either a Tenant account or an Organization account. You can check your Sophos Central portal for the account type.


6.0.0

Respond actions are not supported with an Account Type of Organization.

If you have a multi-tenant instance, do not configure the top tenant as Organization or Tenant.

b. Enter the **Client ID** and **Client Secret** you obtained above.

14. Set the **Interval (min)**. This is how often the logs are collected.
15. Choose the **Content Type**. The logs for **Alerts** and **Events** are supported.
16. Click **Next**. The final confirmation tab appears.



17. Click **Submit**.
18. The **Connector Overview** appears.


The new connector is immediately active. It does not collect any historical logs.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:
   - For **Alerts** and **Events**, change the **Indices** to **Syslog**.
   - For **Alerts** and **Events**, change the **Indices** to **Assets** to view asset data ingested from the logs for Events and Alerts.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.