Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Tenant Mapping

Root-level users

Early Access Program: If this feature doesn't appear in your version of the Stellar Cyber Platform, contact your account manager to inquire about taking part in the Early Access Program and enabling its functionality.

Tenant Mapping 6.5.0 is a feature that lets a single parser route incoming log events to different Stellar Cyber tenants based on a tenant ID embedded in each event. Without it, a parser is bound to one tenant and sends all of the logs it processes to that tenant. With Tenant Mapping, a parser can examine each log event as it arrives, extract a tenant identifier from a designated field, and direct the event to the appropriate tenant automatically.

This capability is particularly useful in two scenarios:

- Managed security service providers (MSSPs) that monitor multiple customer environments from a single platform. Customer logs from different organizations often arrive in a single stream, each event tagged with a customer identifier. Tenant Mapping allows one parser to deliver them to the correct customer tenant without manual intervention.
- Enterprises with multi-tenant deployments where logs originate from different business units, regions, or subsidiaries, each represented as its own Stellar Cyber tenant. A central parser configuration can handle the full log stream and distribute events based on the organizational identifier embedded in each log.

The practical benefit in both cases is consolidation: instead of deploying and maintaining a separate parser for each tenant, you configure one parser and one tenant map, and Stellar Cyber assigns each log to the correct tenant automatically. As the number of tenants grows, you update the tenant map rather than create new parsers.

Tenant Mapping works in conjunction with Parser Studio. When you configure a parser in Parser Studio and enable Tenant Mapping on the Raw Log step, you designate a field in the incoming log event that carries the tenant identifier. Stellar Cyber then uses that field—and, if necessary, a

tenant map to translate a vendor tenant ID to a Stellar Cyber tenant ID—to assign each event to the correct tenant.

Tenant Mapping and Parser Studio are accessible only to root-level users. For information about enabling Tenant Mapping in a custom parser configuration, see **Parser Studio – Parsers**.

Tenant maps are created and managed on the **Tenant Mapping** page, which is where you define the lookup dictionary that the parser uses at runtime. A tenant map must exist before you can select it in a parser configuration.

How Tenant Mapping Works

When a parser with Tenant Mapping enabled processes an incoming log event, it performs the following steps:

1. The parser extracts the value at the configured JSON path from the log event.

   For example, if the configured field is `metadata.tenant_id`, the parser reads the value of that field from the event.

2. Depending on which Tenant Mapping option is configured in the parser, one of the following happens:

   If the parser uses **Stellar Tenant ID**, the parser extracts the Stellar Cyber tenant ID value from the log. The parser uses it to assign the event to the matching tenant directly. No lookup table is needed.


   or

   If the parser uses **Vendor Tenant ID**, the parser extracts the vendor tenant ID from a vendor-assigned identifier in the log. The parser then looks it up in the selected tenant map. If it finds a matching entry, Stellar Cyber associates the event to the corresponding Stellar Cyber tenant. If the tenant map can't match the vendor tenant ID with a Stellar Cyber tenant, Stellar Cyber assigns the log to the same tenant as the sensor that received it.

   If events are appearing under an unexpected tenant, review your tenant map entries.

The Tenant Mapping Page

To access Tenant Mapping, navigate to **System | ORGANIZATION MANAGEMENT | Tenant Mapping**.



The page displays an **Entries** table of existing tenant maps. Each row represents one tenant map and shows the following information:

Column	Description
Name	The name defined for the tenant map when it was created
Description	An optional description describing some aspect of the tenant map such as its purpose
# Entries	The number of vendor tenant ID-to-Stellar Cyber tenant ID mappings that the tenant map contains
Last Modified Time	The date and time the tenant map was last updated
Actions	**Edit** (pencil icon) and **Delete** (trash icon*) controls for each tenant map

* Before deleting a tenant map, confirm that no parser configurations in **Parser Studio** are currently using it. Deleting a tenant map that is referenced by an active parser causes that parser to lose its tenant assignment capability. Log events that previously matched entries in the deleted tenant map will instead be assigned to the tenant associated with the sensor that receives them.

The page also provides the following controls:

- **+ Create Tenant Mapping** – Opens the **Create Tenant Map** dialog box to define a new tenant map.
- **Export CSV** – Exports the list of tenant maps shown in the table.
- **Select View** – Opens the **Saved Views** panel to create or apply a customized table view.



For information about **Export CSV** and **Select View**, see **Using Tables**.

Create a Tenant Map


Before you begin, confirm the following:

- You have the Stellar Cyber tenant IDs for every tenant you want to include in the tenant map. You can find tenant IDs on the **Tenants** page (**System | ORGANIZATION MANAGEMENT | Tenants**).
- You have the vendor tenant IDs that the third-party system uses to identify those tenants in its log events.
- (Optional) If you are uploading a CSV file, you have prepared it with the correct two-column format: Vendor Tenant ID and Stellar Cyber Tenant ID. You can download the provided template from the **+ Create Tenant Mapping** dialog box to use as a starting point.

To create a tenant map:

1. Navigate to **System | ORGANIZATION MANAGEMENT | Tenant Mapping** and then select **+ Create Tenant Mapping**.

   The Create Tenant Map dialog box appears.



2. Enter a descriptive name in the **Tenant Mapping Name** field.

   Choose a name that makes the tenant map easy to identify when selecting it in a parser configuration in Parser Studio.

3. (Optional) Enter a description in the **Description** field.

   Consider including additional context, such as the vendor system the tenant map supports or the set of tenants it covers.

4. Add entries to the tenant map using one or both of the following methods:

   Upload a CSV file: Drag your prepared CSV file into the upload area, or select the area to browse for the file. When the upload succeeds, a confirmation banner displays the number of entries loaded and the entries appear in the **Entries** table. Confirm that the count in the banner matches the number of data rows in your file.


   > Use the link to download a provided template, which is a pre-formatted CSV file with the correct column structure and a sample row that you can replace with your own data.

   Add entries manually: Select **+ Add Entry**. An inline row appears in the **Entries** table. Enter the **Vendor Tenant ID** and the **Stellar Cyber Tenant ID** in the respective fields. Repeat for each additional entry.

   You can combine both methods: **Upload a CSV file** to load a batch of entries, and then use **+ Add Entry** to append individual entries in the same session.

   Each vendor tenant ID must be unique within a tenant map. If you add an entry whose vendor tenant ID already exists in the tenant map and then select **Create** or **Update**, the duplicate entry is silently discarded and the original is retained. The pre-save count shown in the confirmation banner won't match the post-save entry count if duplicates are staged. Check the **# Entries** column after saving to confirm the final count.

5. Review the entries in the **Entries** table to confirm that the Vendor Tenant IDs and Stellar Cyber Tenant IDs are correct and that the **Stellar Cyber Tenant Name** column reflects the expected tenant names.

   The following are some notes about the file upload and processing:

- The **Stellar Cyber Tenant Name** column that appears in the **Entries** table after upload is resolved automatically from the Stellar Cyber Tenant ID. It's not a column in the CSV file and does not need to be provided.
- After uploading, confirm that the number of entries shown in the confirmation banner matches the number of data rows in your CSV file. If the counts do not match, remove the affected entries and re-upload the file.
- Uploading a CSV file to a tenant map that already contains entries replaces all existing entries with the contents of the uploaded file. The upload does not append to existing entries. Before uploading, ensure that your CSV file contains all of the entries you want the tenant map to contain, not just the new ones you are adding.

6. To remove an entry, select the **Delete** icon for that row.
7. Select **Create**.

   The new tenant map appears in the **Tenant Mapping** table on the main page and is now available for selection when configuring a parser in **Parser Studio**. (For information, see Parser Studio.)

© 2026 Stellar Cyber . All rights reserved.