Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring WatchGuard Firebox Responder Connectors 6.1.0

Use a WatchGuard Firebox Responder to configure a Webhook action that can be triggered manually or that can enhance Automated Threat Hunting (ATH) actions.

WatchGuard Firebox Responders use Webhook templates that support actions. Each action is one responder, there are two actions, and hence there are two Responders: WatchGuard Firebox Add Allowed Sites and WatchGuard Firebox Add Blocked Sites.

This document describes how to configure a WatchGuard Firebox Responder using the Universal Webhook Responder, how to manually trigger an action with a WatchGuard Firebox Responder, and how to perform ATH actions with a WatchGuard Firebox Responder.

Note the following rate limit:

Maximum API requests per second	500
Quota of API requests per day	200,000

Connector Overview: WatchGuard Firebox Responder

Capabilities

- Collect: **No**
- Respond: **Webhook actions**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **N/A**

Collected Data

N/A

Domain

<Hostname>

where <Hostname> is variable from the configuration of this connector

Response Actions

Webhook action templates:

- WatchGuard Firebox Add Allowed Sites
- WatchGuard Firebox Add Blocked Sites

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Hostname, Protocol, Access ID, Password, and WatchGuard-API-Key

Adding a WatchGuard Firebox Responder

To add a WatchGuard Firebox Responder:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Use actions

Obtaining Credentials


Before you configure the connector in Stellar Cyber, you must obtain the following WatchGuard Firebox credentials:

- Hostname—The base URL for API access. The default (for United States) is api.usa.cloud.watchguard.com. Locate the Base URL for other regions at WatchGuard API documentation.
- Protocol—The options for Protocol are HTTP and HTTPS.
- Access ID and Password—The authentication credentials. To obtain an Access ID and password, follow the guidance in the WatchGuard API documentation to Get Started with WatchGuard APIs. Specify the Read-write credential.
- WatchGuard-API-Key—The API Key associated with your WatchGuard Cloud account. Locate it on the Managed Access page in WatchGuard Cloud. Specify the API Key as the value of the WatchGuard-API-Key header parameter.


Adding the Connector in Stellar Cyber

To add a WatchGuard Firebox Responder in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Webhook** from the **Category** dropdown.
5. Choose one of the predefined templates from the **Type** dropdown: **WatchGuard Firebox Add Allowed Sites** or **WatchGuard Firebox Add Blocked Sites**.



The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Respond**, which is enabled already.
7. Enter a **Name**.

Notes:


- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. This identifies which tenant is allowed to use the connector. In addition to specific tenants, this connector supports **All Tenants**, which means that a WatchGuard Firebox Responder can be used across tenants.
9. Choose the device on which to run the connector.

- Certain connectors can be run on either a Sensor or a Data Processor. The available devices are displayed in the **Run On** menu. If you want to associate your collector with a sensor, you must have configured that sensor prior to configuring the connector or you will not be able to select it during initial configuration.


- If the device you're connecting to is on premises, we recommend you run on the local sensor. If you're connecting to a cloud service, we recommend you run on the DP.

10. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.

11. Enter the **Hostname** you noted above in Obtaining Credentials.
12. Select the **Protocol**, either **HTTP** or **HTTPS**. If you select **HTTPS**, another field is available: **Disable SSL Certificate Verification**.
13. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to, otherwise, it is not a good security practice and may expose the connection to security risks.
14. Enter the **Access ID** and **Password** you noted above.
15. Enter the **WatchGuard-API-Key** you noted above.
16. Click **Next**. The final confirmation tab, **Done**, appears.




17. Click **Submit**.

Testing the Connector

When you define a WatchGuard Firebox Responder, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication / connectivity. The **Test** button shows success with a valid credential.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector that you want to test.
3. Click **Test** at the right  of that row. The test runs immediately.

   Note that you may run only one test at a time.

   Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

   To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

   The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.

   Repeat the test as needed.

If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Using Actions

With a WatchGuard Firebox Responder, you can:

- Manually trigger an action
- View action status
- Perform an ATH action

Manually Triggering an Action

To manually trigger an action with a WatchGuard Firebox Responder:

1. Select **Threat Hunting**.


   The **Interflow Search** tab appears.

2. Change the **Indices** for the record type, for example, **Alerts**.

3. Scroll down the page and click the icon for **More Info** in the **Actions** column.


4. Click the **Actions** tab.

   Webhook actions appear under **External Actions**.



5. Click a WatchGuard Firebox Webhook action.

   The template populates the fields in the **Path and Query** and the **JSON Body**.



6. Modify the **Path and Query** by entering your WatchGuard Cloud account ID in the {{account_id}} parameter in the path. Locate your account ID on the My Account page in the WatchGuard Cloud, then enter it in place of {{account_id}} in the path, for example: /rest/firebox/management/v1/configuration/{{account_id}}/exceptions/blockedsite

7. Modify the **JSON Body** by entering string values or curly brace expressions. Fill in any empty fields.


8. To perform the action, click **Submit**.

Viewing Action Status

To view action status:

1. Click **Automation | Action History**.

2. Click **Webhook Actions**.




You can view the action status or error message in the table.

Performing an ATH Action

To perform an ATH action with a WatchGuard Firebox Responder:

1. Click **Automation | Automation**.
2. Click **Create**.
3. Scroll down to **Actions**.



4. Click the ✚ button to add an action. Another action appears below the existing action.
5. Select the **Trigger on condition**.
6. Select **Webhook Responder** for the **Type**.
7. Select a previously configured WatchGuard Firebox Responder from the dropdown menu for the **Webhook Responder**. The template populates the fields in the **Path and Query** and **JSON Body**.
8. Modify the **Path and Query** by entering your WatchGuard Cloud account ID in the {{account_id}} parameter in the path. Locate your account ID on the My Account page in the WatchGuard Cloud, then enter it in place of {{account_id}} in the path, for example: /rest/firebox/management/v1/configuration/{{account_id}}/exceptions/blockedsite
9. Modify the **JSON Body** by entering string values or curly brace expressions. Fill in any empty fields.
10. (Optional) Click **Override Default Settings** to override the playbook's mute settings and mute just this action.
11. Click **Submit**

© 2026 Stellar Cyber . All rights reserved.