Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring WithSecure Elements Connectors

6.3.0

This connector allows Stellar Cyber to ingest logs from WithSecure Elements and add the records to the data lake. This connector integrates with the WithSecure Elements API to query devices, events, incidents, and detections.

In addition, you can use WithSecure Elements responders to configure Webhook actions that can be triggered manually or that can enhance Automated Threat Hunting (ATH) actions.

WithSecure Elements responders use Webhook templates that support actions. Each action is one responder, there are four actions, and hence there are four WithSecure Elements responders: WithSecure Elements Isolate From Network, WithSecure Elements Kill Process, WithSecure Elements Kill Thread, and WithSecure Elements Release From Network Isolation.

This document describes how to configure a WithSecure Elements responder using the Universal Webhook Responder, how to add the respond function to a WithSecure Elements connector and how to manually trigger an action and perform ATH actions with a WithSecure Elements responder.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: WithSecure Elements

Capabilities

- Collect: **Yes**
- Respond: **Webhook actions**
- Native Alerts Mapped: **Yes** 6.3.0
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records

Detections
Devices
Incidents
Security Events
	Syslog
	Assets (for Devices)
		msg_class:
		`withsecure_elements_detection`
		`withsecure_elements_device`
		`withsecure_elements_incident`
		`withsecure_elements_event`
		
		msg_origin.source:
		`withsecure_elements`
		
		msg_origin.vendor:
		`withsecure`
		
		msg_origin.category:
		`endpoint`

Domain

<Base URL>

where <Base URL> is a variable from the configuration of this connector

Response Actions

Webhook action templates:

- WithSecure Elements Isolate from Network
- WithSecure Elements Kill Process (Beta feature)
- WithSecure Elements Kill Thread (Beta feature)
- WithSecure Elements Release From Network Isolation

Third Party Native Alert Integration Details 6.3.0

This connector ingests logs from WithSecure Elements to get the raw alerts that are stored in the Syslog index. Select the Detections content type.

Stellar Cyber maps WithSecure Elements detections. The detections are read from the Syslog index, enriched with Stellar Cyber fields, and mapped (with deduplication) to the Alerts index.

Deduplication is by `tenantid`, `event.threat.name`, `user.name`, `process.hash.sha1`, `withsecure_elements.detectionId`, and `withsecure_elements.description`.

For details, see Integration of Third Party Native Alerts.

Required Credentials and Configurations

- For Collect: Base URL, Client ID, Client Secret, and Organization ID
- For Respond: Hostname, Protocol, Client ID, and Client Secret

Locating Records 6.3.0

To search the alerts in the Alerts index or the Original Records in the Syslog index, use the query: `msg_class:withsecure_elements_detection AND NOT event.severity_str:info AND NOT withsecure_elements.riskLevel:info AND NOT event.threat.name:network_connection_discovery_by_detected_process`

Adding a WithSecure Elements Connector

To add a WithSecure Elements connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber (Collect)
3. Add the connector in Stellar Cyber (Respond)
4. Test the connector
5. Verify ingestion
6. Use actions

Obtaining WithSecure Elements Credentials


Before you configure the connector in Stellar Cyber, you must obtain the following WithSecure Elements credentials:

- Base URL—The base URL for API access. The default is: https://api.connect.withsecure.com.
- Hostname—Hostname for respond function. The default is: api.connect.withsecure.com.
- Client ID and Client Secret—Generated API Client ID and Client Secret.


Generating a Client ID and Client Secret

To generate a Client ID and Client Secret:

1. Log in to the Console.
2. Navigate to **Management** > **Organization Settings**.




3. Select the **API Clients** tab and click **Add new**.




4. On the **Add new API client** page, enter an **Organization** and a **Description**.

- For an API key for the Collect function, check **Read-only**.



- For an API key for the Respond function, uncheck **Read-only**.

5. Click **Add**.
6. The API client is generated. Copy the **Client ID** and **Secret**. You will need them when configuring the connector in Stellar Cyber.




Store the Client ID and Secret in a safe location. It cannot be retrieved later although you can create a new one.


Adding the Connector in Stellar Cyber (Collect)

To add the collect function for a WithSecure Elements connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.

5. Choose **WithSecure Elements** from the **Type** dropdown.




   The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



   The asterisk (*) indicates a required field.

12. Enter the **Base URL** you noted above in Obtaining WithSecure Elements Credentials.
13. Enter the **Client ID** you noted above.
14. Enter the **Client Secret** you noted above.
15. (Optional) Enter the **Organization ID**.

    If an Organization ID is not entered, the default organization of the authenticated client is used.


16. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a reason to, otherwise, it is not a good security practice.
17. Choose the **Interval (min)**. This is how often the logs are collected.

The logs for **Devices** are queried every 24 hours.

18. Choose the **Content Type** you would like to collect. The logs for **Devices**, **Detections**, **Incidents**, and **Security Events** are supported.

    The **Devices** content type is always selected and cannot be removed from the configuration as it is required for host information.

19. Click **Next**. The final confirmation tab appears.




20. Click **Submit**.

The new connector is immediately active.


Adding the Connector in Stellar Cyber (Respond)

To add the respond function for a WithSecure Elements connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



   The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Webhook** from the **Category** dropdown.
5. Choose one of the predefined templates from the **Type** dropdown: **WithSecure Elements Isolate From Network**, **WithSecure Elements Kill Process**, **WithSecure Elements Kill Thread**, or **WithSecure Elements Release From Network Isolation**.




The asterisk (*) indicates a required field.

WithSecure Elements Kill Process and **WithSecure Elements Kill Thread** are Beta features.

6. For this connector, the supported **Function** is **Respond**, which is enabled already.
7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.
8. Choose a **Tenant Name**. This identifies which tenant is allowed to use the connector. In addition to specific tenants, this connector supports **All Tenants**, which means that a WithSecure Elements responder can be used across tenants.
9. Choose the device on which to run the connector.


   - Certain connectors can be run on either a Sensor or a Data Processor. The available devices are displayed in the **Run On** menu. If you want to associate your collector with a sensor, you must have configured that sensor prior to configuring the connector or you will not be able to select it during initial configuration.
   - If the device you're connecting to is on premises, we recommend you run on the local sensor. If you're connecting to a cloud service, we recommend you run on the DP.
10. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.

11. Enter the **Hostname** you noted above in Obtaining WithSecure Elements Credentials.
12. Select the **Protocol**, either **HTTP** or **HTTPS**. If you select **HTTPS**, another field is available: **Disable SSL Certificate Verification**.

13. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to, otherwise, it is not a good security practice and may expose the connection to security risks.
14. Enter the **Client ID** and **Client Secret** you noted above.
15. Click **Next**. The final confirmation tab, **Done**, appears.




16. Click **Submit**.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:

- For **Devices**, **Detections**, **Incidents**, and **Security Events**, change the **Indices** to **Syslog**.
- For **Devices** only, change the **Indices** to **Assets**.

The table immediately updates to show ingested Interflow records.

Using Actions

With a WithSecure Elements responder, you can:


- Manually trigger an action
- View action status
- Perform an ATH action

Manually Triggering an Action

To manually trigger an action with a WithSecure Elements responder:


1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.
2. Change the **Indices** for the record type, for example, **Syslog**.
3. Scroll down the page and click the icon for **More Info** in the **Actions** column.
4. Click the **Actions** tab. Webhook actions appear under **External Actions**.



5. Click a WithSecure Elements Webhook action.

   The template populates the fields in the **Path and Query** and the **JSON Body**.




6. You can modify the **JSON Body** by entering string values or curly brace expressions. Fill in any empty fields, such as **organizationId**, **threadId**, or **targets**.
7. To perform the action, click **Submit**.

Viewing Action Status

To view action status:

1. Click **Automation | Action History**.

2. Click **Webhook Actions**.




You can view the action status or error message in the table.

Performing an ATH Action

To perform an ATH action with a WithSecure Elements responder:

1. Click **Automation | Automation**.
2. Click **Create**.
3. Scroll down to **Actions**.



4. Click the **+** button to add an action. Another action appears below the existing action.
5. Select the **Trigger on condition**.
6. Select **Webhook Responder** for the **Type**.
7. Select a previously configured WithSecure Elements responder from the dropdown menu for the **Webhook Responder**.

   The template populates the fields in the **Path and Query** and **JSON Body**.
8. You can modify the **JSON Body** by entering string values or curly brace expressions.
9. (Optional) Click **Override Default Settings** to override the playbook's mute settings and mute just this action.
10. Click **Submit**.

© 2026 Stellar Cyber . All rights reserved.