Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Wiz Connectors 6.3.0 6.4.0

This connector allows Stellar Cyber to ingest logs from Wiz and add the records to the data lake. It integrates with the Wiz API to ingest Issues and Vulnerabilities data types.

Wiz is a cloud security platform that helps organizations make their cloud environments secure and more streamlined. They create a normalizing layer across different cloud environments, so companies can spot and remove high-priority risks faster.

The Wiz API has a rate limit that is based per service account on tenant level. The rate limit is 10 calls per second for a service account query. Depending on the amount of data, the connector may fail to pull data and receive a 429 response.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Wiz

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **Yes** 6.4.0
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records
Issues	Syslog (for Issues)	msg_class: `wiz_issues`
Vulnerabilities	Scans (for Vulnerabilities)	`wiz_vulnerabilities`

Content Type	Index	Locating Records

		msg_origin.source:
		`wiz`
		
		msg_origin.vendor:
		`wiz`
		
		msg_origin.category:
		`cloudsec`

Domain

<Auth URL> and <Base URL>

where <Auth URL> and <Base URL> are variables from the configuration of this connector

Response Actions

N/A

Third Party Native Alert Integration Details 6.4.0

This connector ingests logs from Wiz to get the raw alerts that are stored in the Syslog index. Select the Issues content type.

Stellar Cyber maps Wiz events. The events are read from the Syslog index, enriched with Stellar Cyber fields, and mapped (with deduplication) to the Alerts index.

Deduplication is by `tenantid` and `wiz.id`.

For details, see Integration of Third Party Native Alerts.

Required Credentials and Configurations

- Auth URL, Base URL, Client ID, and Client Secret
  or
- Auth URL (Custom URL), Custom Auth URL, Credential Audience, Base URL (Custom URL), Custom Base URL, Client ID, and Client Secret

Locating Records 6.4.0

To search the alerts in the Alerts index or the Original Records in the Syslog index, use the query: `msg_class:\"wiz_issues\"`

Adding a Wiz Connector

To add a Wiz connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Obtaining Wiz Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following Wiz credentials:

- Auth URL—The authentication URL. There are three URLs, based on tenant. The values are:
    - https://auth.app.wiz.io for Wiz Commercial (default)
    - https://auth.app.wiz.us for Wiz for Gov
    - https://auth.gov.wiz.io for Wiz Commercial on GovCloud
    - Custom URL
- Base URL—The base URL for API access. The base URL depends on the region. There are four regions (us1, us2, eu1, and eu2). The values are:
    - https://api.us1.app.wiz.io (default)
    - https://api.us2.app.wiz.us
    - https://api.eu1.app.wiz.io
    - https://api.eu2.app.wiz.io
    - Custom URL
- Client ID and Client Secret—The authentication credentials.

or


- Auth URL—The same values as above. Select Custom URL to display Custom Auth URL and Credential Audience fields.
- Custom Auth URL—The default is: https://auth.app.wiz.io
- Credential Audience—The credential audience may have a different value based on the tenant URL used in authentication. When Auth URL is custom, then the Credential Audience value is unknown, so it needs to be input by the user. The default is: wiz-api
- Base URL—The same values as above. Select Custom URL to display Custom Base URL field.
- Custom Base URL—The default is https://api.us1.app.wiz.io
- Client ID and Client Secret—The authentication credentials.

Adding a Service Account


Add a service account for authenticating with the Wiz API. You will need to specify the permissions (API scopes).

Follow the guidance in your Wiz API documentation.


1. Log in as a Wiz administrative user with Write permission for Service Accounts.
2. Select **Settings** > **Access Management** > **Service Accounts**.



3. Click **Add Service Account**.




4. Enter a **Name**, an optional **Description**, and select a **Type**. For **Type**, choose Custom Integration (GraphQL API).




5. Select the API Scopes to grant to this new service account.


   For example, under Resources, select Read graph resource.



   For example, under Issues, select Read an issue, list issues.



   For example, under Vulnerabilities, select Read vulnerabilities.




6. Click **Add Service Account**.
7. The Client ID and Client Secret are displayed for the new service account. They will be needed when configuring the connector in Stellar Cyber.

   Copy the Client ID and Client Secret and store them in a safe location.


Adding the Connector in Stellar Cyber

To add a Wiz connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



   The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Cloud Security** from the **Category** dropdown.
5. Choose **Wiz** from the **Type** dropdown.




   The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.

7. Enter a **Name**.


   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.




   The asterisk (*) indicates a required field.

12. If you select an **Auth URL** from the dropdown menu:
    a. Select the **Auth URL** you noted above in Obtaining Wiz Credentials.
    b. Select the **Base URL** you noted above, then skip the next step.
13. If you select **Custom URL** from the dropdown menu in the **Auth URL** field:



    a. Enter the **Custom Auth URL** or keep the default.
    b. Enter the **Credential Audience** or keep the default.
    c. For **Base URL**, select **Custom URL**.
    d. Enter the **Custom Base URL** or keep the default.
14. Enter the **Client ID** you noted above.
15. Enter the **Client Secret** you noted above.
16. Choose the **Content Type** you would like to collect. The logs for **Issues** and **Vulnerabilities** are supported.
17. Choose the **Interval (min)**. This is how often the logs are collected.

18. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to, otherwise, it is not a good security practice and may expose the connection to security risks.
19. Click **Next**. The final confirmation tab appears.



20. Click **Submit**.

The new connector is immediately active.


Testing the Connector

In addition to testing for connectivity, the **Test** button for the Wiz connector tests that the Auth URL, Base URL, Client ID, and Client Secret are correct and data requests for the requested content type returns successful responses.

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search**  appears.

2. Change the **Indices** for the type of content you collected:
   - For **Issues**, change the **Indices** to **Syslog**.
   - For **Vulnerabilities**, change the **Indices** to **Scans**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.