

CPE/EE 695: Applied Machine Learning

Lecture 3 – 2: Evaluating Classifiers

Dr. Shucheng Yu, Associate Professor

Department of Electrical and Computer Engineering

Stevens Institute of Technology

1870

Classification measures

Accuracy is only one measure (error = 1-accuracy).

Accuracy is not always suitable

- In text mining, we may only be interested in the documents of a particular topic, which are only a small portion of a big document collection.
- In classification involving skewed or highly imbalanced data, e.g., network intrusion and financial fraud detections, we are interested only in the minority class.
 - High accuracy does not mean any intrusion is detected.
 - E.g., 1% intrusion. Achieve 99% accuracy by doing nothing.
- The class of interest is commonly called the positive class, and the rest negative classes.

Performance Measures of Classifiers



Confusion Matrix

Sometimes we need both a high accuracy rate and a low error rate. *Confusion matrix* is an important tool to measure both accuracy rates and error rates.

	Classified Positive	Classified Negative
Actual Positive	ТР	FN
Actual Negative	FP	TN

True Positive (TP): the number of true positive examples

True Negative (TN): the number of true negative examples

False Positive (FP): the number of false positive examples (type I error)

False Negative (FN): the number of false negative examples (type II error)

Performance Measures of Classifiers



Precision, Recall and F_1 -Score

We are often interested in two measures on relevance:

- **precision** $p = \frac{TP}{TP + FP}$, is the number of true positive divided by all classified as positive.
- recall (a.k.a., sensitivity) $r = \frac{TP}{TP + FN}$, is the number of true positive divided by all positive.
- $F_1 = \frac{2pr}{n+r}$, is a measure of both p and r. F_1 -score is large only if both p and r are large.

	Classified Positive	Classified Negative
Actual Positive	1	99
Actual Negative	0	200

"Precision can be seen as a measure of quality and recall as a measure of quantity.


- Higher precision means that an algorithm returns <u>more relevant results</u> than irrelevant ones,
- high recall means that an algorithm returns <u>most of the relevant results</u>." (Wikipedia)

Performance Measures of Classifiers



Receiver Operating Characteristic (ROC) Curve

Another common measure is the *Receiver Operating Characteristic* (ROC) curve, which shows the tradeoff between **True Positive Rate** (i.e., *sensitivity*) and **False Positive Rate** (i.e., *1 - specificity*).



- The closer to the top-left corner of the ROC space, the better the classifier is.
- The closer to the 45-degree diagonal of the ROC space, the worse the classifier is.
- The area under the curve (AUC) is usually used to measure above properties.
- ROC/AUC are usually used to measure how well a binary classifier distinguish the two classes.



stevens.edu