# **Number Bases and Binary Operations**

#### **Author: Shekh Mostofa Abedin**

### **Understanding Number Bases**

- 1. Decimal (Base 10)
  - **Digits**: 0-9.
  - **Usage**: The standard system for counting and arithmetic.
  - **Example**: The number 345 in decimal is written as 345.
- 2. Binary (Base 2)
  - Digits: 0, 1.
  - Usage: The fundamental language of computers.
  - Example: The binary number 10112 equals 11 in decimal.
- 3. Hexadecimal (Base 16)
  - **Digits**: 0-9, A-F (where A=10, B=11, ..., F=15).
  - Usage: Compact representation of binary numbers, commonly used in computing.
  - Example: The hexadecimal number 2F3<sub>16</sub> equals 755 in decimal.

#### Use of Letters in Number Bases

- Base 2 to Base 10: Only digits 0-9 are used. There are no letters, and after 9, the next number is 10.
- Base 11 and Above: Letters are introduced to represent values greater than 9. The use of letters continues until the base limit is reached. After the highest letter (which corresponds to the base minus 1), the numbering transitions to 10, 11, and so on.
  - Examples:
    - Base 11: Uses digits 0-9 and the letter A (where A=10). After A, the next number is 10.
    - Base 12: Uses digits 0-9 and the letters A (10) and B (11). After B, the next number is 10.
    - Base 16 (Hexadecimal): Uses digits 0-9 and the letters A (10), B (11), C (12), D (13), E (14), and F (15). After F, the next number is 10.
    - Base 17: Uses digits 0-9 and the letters A (10), B (11), C (12), D (13), E (14), F (15), and G (16). After G, the next number is 10.
- **General Rule**: In bases greater than 10, after the digits 0-9 are exhausted, letters are used starting with A=10. The sequence continues with these letters until reaching the base limit. After the highest letter, the numbering restarts from 10 (which represents the base value), followed by 11, 12, etc.
- Base 8 (Octal): Uses only digits 0-7. No letters are used, and after 7, the next number is 10.

# Converting Between Number Bases

- 1. Binary to Decimal
  - Steps:
    - 1. Multiply each binary digit by 2 raised to the power of its position (starting from 0 on the right).
    - 2. Sum all the results.
  - Example: Convert 1101<sub>2</sub> to decimal.
    - Calculation:  $1 \times 2^3 + 1 \times 2^2 + 0 \times 2^1 + 1 \times 2^0 = 8 + 4 + 0 + 1 = 13_{10}$
- 2. Decimal to Binary
  - Steps:
    - 1. Divide the decimal number by 2.
    - 2. Record the remainder.
    - 3. Update the quotient and repeat until the quotient is 0.
    - 4. The binary number is the remainders read in reverse order.
  - **Example**: Convert 23<sub>10</sub> to binary.

- o Division steps:
  - 23 ÷ 2 = 11, remainder = 1
  - 11 ÷ 2 = 5, remainder = 1
  - $5 \div 2 = 2$ , remainder = 1
  - $2 \div 2 = 1$ , remainder = 0
  - $1 \div 2 = 0$ , remainder = 1
- o Result: 101112

#### 3. Hexadecimal to Decimal

#### • Steps:

- 1. Multiply each hex digit by 16 raised to the power of its position (starting from 0 on the right).
- 2. Sum all the results.
- **Example**: Convert 2F3<sub>16</sub> to decimal.
  - Calculation:  $2 \times 16^2 + F \times 16^1 + 3 \times 16^0 = 512 + 240 + 3 = 755_{10}$

#### 4. Decimal to Hexadecimal

#### • Steps:

- 1. Divide the decimal number by 16.
- 2. Record the remainder.
- 3. Update the quotient and repeat until the quotient is 0.
- 4. The hexadecimal number is the remainders read in reverse order.
- **Example**: Convert 438<sub>10</sub> to hexadecimal.
  - Division steps:
    - 438 ÷ 16 = 27, remainder = 6
    - 27 ÷ 16 = 1, remainder = 11 (B)
    - 1 ÷ 16 = 0, remainder = 1
  - o Result: 1B6<sub>16</sub>

#### 5. Binary to Hexadecimal

#### • Steps:

- 1. Group binary digits into sets of four (starting from the right).
- 2. Convert each group to its hexadecimal equivalent.

#### • Conversion Table:

Hex	0	1	2	3	4	5	6	7	8	9	Α	В	C	D	E	F
Binary	0000	0001	0010	0011	0100	0101	0110	0111	1000	1001	1010	1011	1100	1101	1110	1111

- Example: Convert 1011101111012 to hexadecimal.
  - o Grouping: 1011 1011 1101
  - O Conversion: BBD<sub>16</sub>

#### 6. Hexadecimal to Binary

- Steps:
  - 1. Convert each hexadecimal digit to its 4-bit binary equivalent.
- **Example**: Convert A4F<sub>16</sub> to binary.
  - o Conversion: A=1010, 4=0100, F=1111
  - o Result: 101001001111<sub>2</sub>

#### 7. Decimal to Other Bases

#### • Steps:

- 1. Divide the decimal number by the target base.
- 2. Record the remainder.
- 3. Update the quotient and repeat until the quotient is 0.
- 4. The number in the target base is the remainders read in reverse order.
- **Example**: Convert 345<sub>10</sub> to base 5.

- o Division steps:
  - 345 ÷ 5 = 69, remainder = 0
  - $69 \div 5 = 13$ , remainder = 4
  - $13 \div 5 = 2$ , remainder = 3
  - $2 \div 5 = 0$ , remainder = 2
- o Result: 23405

#### 8. Any Base to Decimal

- Steps:
  - 1. Multiply each digit by its base power (starting from 0 on the right).
  - 2. Sum the results.
- **Example**: Convert 2340<sub>5</sub> to decimal.
  - Calculation:  $2 \times 5^3 + 3 \times 5^2 + 4 \times 5^1 + 0 \times 5^0 = 250 + 75 + 20 + 0 = 345_{10}$

# Bit Shifting

- 1. Left Shift (<<)
  - Operation: Shifts bits left, multiplying by 2 for each shift.
  - Example: 1011 << 2 shifts 1011 to 101100.
    - 1011 in decimal = 11
    - 101100 in decimal = 44
- 2. Right Shift (>>)
  - Operation: Shifts bits right, dividing by 2 for each shift.
  - Example: 1011 >> 2 shifts 1011 to 10.
    - 1011 in decimal = 11
    - 10 in decimal = 2

# **Binary Arithmetic**

### 1. Binary Addition

#### **Basic Rules:**

- 0 + 0 = 0
- 0 + 1 = 1
- 1 + 0 = 1
- 1 + 1 = 10 (0 with a carry of 1)

#### **Adding Binary Numbers of Different Sizes:**

- Align the numbers by their rightmost digits.
- If the numbers are of different lengths, prepend zeros to the smaller number to make both numbers the same size.
- **Example**: Add 1011 and 110:
  - o Align:

```
1011
+ 0110
-----
10001
```

- o Result: 100012
- 2. Binary Subtraction

#### **Basic Rules:**

- 0 0 = 0
- 1 0 = 1
- 1 1 = 0
- 0 1 = 1 (borrow 1 from the next higher bit)

#### **Subtracting Binary Numbers of Different Sizes:**

- Align the numbers by their rightmost digits.
- If the numbers are of different lengths, prepend zeros to the smaller number to make both numbers the same size.
- **Example**: Subtract 110 from 1011:
  - o Align:

```
1011
- 0110
-----
0101
```

o Result: 01012 or simply 1012

### **Prefixes for Number Bases**

```
• Hexadecimal: 0x or 0X (e.g., 0x1A3F)
```

- **Binary**: 0b or 0B (e.g., 0b1101)
- Octal: 0 (leading zero) (e.g., 0754)
- Decimal: No prefix needed (e.g., 1234)

# **Summary of Conversion Steps**

- **To Decimal**: Multiply each digit by its base power, sum the results.
- From Decimal: Divide by the target base, record remainders, read them in reverse order.
- **Binary** ↔ **Hex/Oct**: Group binary digits (3 for octal, 4 for hex), convert each group.
- Any Base ↔ Any Base: Convert to decimal first, then to the target base.