Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

Principles of congestion control

congestion:


- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control (which is about applications and read buffers)
- manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- a top-10 problem!


two senders, two receivers

one router, infinite buffers


output link capacity: R

no retransmission






maximum per-connection throughput: R/2




• large delays as arrival rate, λ_{in} , approaches capacity


- one router, finite buffers
- sender retransmission of timed-out packet
 - application-layer input = application-layer output: λ_{in} = λ_{out}
 - transport-layer input includes retransmissions : $\lambda_{in} \ge \lambda_{in}$



idealization: perfect knowledge

 sender sends only when router buffers available






Idealization: known loss


packets can be lost, dropped at router due to full buffers


 sender only resends if packet known to be lost



Idealization: known loss packets can be lost, dropped at router due to full buffers


sender only resends if packet known to be lost






Realistic: duplicates


- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered





Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered




"costs" of congestion:


- more work (retrans overhead) for a desired "goodput"
- unneeded retransmissions: link carries multiple copies of packet
 - decreasing goodput

- four senders
- multihop paths
- timeout/retransmit

Q: what happens as λ_{in} and λ_{in} increase?

A: as red λ_{in} increases, all arriving blue pkts at upper queue are dropped, blue throughput $\rightarrow 0$





another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!

Approaches towards congestion control

two broad approaches towards congestion control:

end-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

network-assisted congestion control:

- routers provide feedback to end systems
 - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
 - explicit rate for sender to send at

Case study: ATM ABR congestion control


ABR: available bit rate:

- "elastic service"
- if sender's path "underloaded":
 - sender should use available bandwidth
- if sender's path congested:
 - sender throttled to minimum guaranteed rate

RM (resource management) cells:

- sent by sender, interspersed with data cells
- bits in RM cell set by switches ("network-assisted")
 - NI bit: no increase in rate (mild congestion)
 - Cl bit: congestion indication
- RM cells returned to sender by receiver

Case study: ATM ABR congestion control



- two-byte ER (explicit rate) field in RM cell
 - congested switch may lower ER value in cell
 - senders' send rate thus max supportable rate on path
- EFCI bit in data cells: set to I in congested switch
 - if data cell preceding RM cell has EFCI (explicit forward congestion indication) set, receiver sets CI bit in next returned RM cell

Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control


Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

TCP Slow Start

- when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = I MSS
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received
- summary: initial rate is slow but ramps up exponentially fast



TCP congestion control: additive increase multiplicative decrease

* approach: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs


additive increase: increase cwnd by I maximum segment size (MSS) every RTT until loss detected

• multiplicative decrease: cut cwnd in half after loss


(TCP RENO)

cwnd: TCP sender

AIMD saw tooth behavior: probing for bandwidth



TCP Congestion Control: details



sender limits transmission:

$$\begin{array}{ccc} \text{LastByteSent} & - & \leq & \text{cwnd} \\ \text{LastByteAcked} & & & \end{array}$$

 cwnd is dynamic, function of perceived network congestion

TCP sending rate:

roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

rate
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

TCP: detecting, reacting to loss

loss indicated by timeout:


Lots of ways to do this, some with odd names

- cwnd set to 1 MSS;
- window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
 - dup ACKs indicate network capable of delivering some segments
 - **cwnd** is cut in half, window then grows linearly (congestion avoidance)
- TCP Tahoe always sets cwnd to I (timeout or 3 duplicate acks)

TCP: switching from slow start to CA

Q: when should the exponential increase switch to linear?


A: when **cwnd** gets to 1/2 of its value before timeout.



Implementation:


- * variable ssthresh
- on loss event, ssthresh is set to 1/2 of what cwnd was just before loss event (12 -> 6)

Summary: TCP Congestion Control



TCP throughput

- Can we calculate avg. TCP throughput as function of window size and RTT?
 - ignore slow start, assume always data to send
- W: window size (measured in bytes) where loss occurs
 - avg. window size (# in-flight bytes) is ³/₄ W
 - avg. thruput is $\frac{3}{4}W$ per $\frac{RT_3T}{4}W$ bytes/sec



TCP Futures: TCP over "long, fat pipes"


- example: I500 byte segments, I00ms RTT, want
 I0 Gbps throughput
- requires W = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:

TCP throughput =
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- → to achieve 10 Gbps throughput, need a loss rate of L = $2 \cdot 10^{-10}$ a very small loss rate!
- new versions of TCP for high-speed

TCP Fairness


fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



Why is TCP fair?

two competing sessions:

- additive increase gives slope of I, as throughput increases (creeps up slowly)
- multiplicative decrease decreases throughput proportionally



Fairness (more)

Fairness and UDP

- multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- instead use UDP:
 - send audio/video at constant rate, tolerate packet loss

Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- web browsers do this
- e.g., link of rate R with 9 existing connections:
 - new app asks for I TCP, gets rate R/10
 - new app asks for 11 TCPs, gets R/2

Chapter 3: summary

- principles behind transport layer services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control
- Instantiation and implementation in the Internet via:
 - UDP
 - TCP

<u>next:</u>

- leaving the network "edge" (application, transport layers)
- into the network "core"