# Lab 9 - Integer Arithmetic

In this Lab we will practice the fundamental binary shift and rotation techniques. Bit manipulation is an intrinsic part of computer graphics, data encryption, and hardware manipulation.

# 9.1 Shift and Rotate Instructions

Along with bitwise instructions we studied in Lab 6, shift instructions are among the most characteristic of assembly language. *Bit shifting* means to move bits right and left inside an operand. x86 processors provide a particularly rich set of instructions in this area.


#### **Shift instructions:**

SHL	Shift left
SHR	Shift right
SAL	Shift arithmetic left
SAR	Shift arithmetic right
ROL	Rotate left
ROR	Rotate right
RCL	Rotate carry left
RCR	Rotate carry right
SHLD	Double-precision shift left
SHRD	Double-precision shift right

Flags: All shift instructions affect the Overflow and Carry flags.


### 9.1.1 Logical Shift SHL and SHR Instructions

logical shift fills the newly created bit position with zero.



A byte is logically shifted one position to the right. In other words, each bit is moved to the next lowest bit position. Note that bit 7 is assigned 0.

The following illustration shows a single logical right shift on the binary value 11001111, producing 01100111. The lowest bit is shifted into the Carry flag:



Instructor: Syed Tehseen ul Hasan Shah

### 9.1.2 SHL and SHR Instructions

```
SHL destination, count SHR destination, count
```

The following lists the types of operands permitted by this instruction:

```
SHL reg,imm8
SHL mem,imm8
SHL reg,CL
SHL mem,CL
```

Note: Formats shown above also apply to the SHR, SAL, SAR, ROL, ROR, RCL, and RCR instructions.

### **Example:**

```
Include Irvine32.inc
.data
      testData BYTE 10110001b
      message BYTE "Input binary: 1011 0001",0
      message_SHL1 BYTE "SHL 1 bit: ",0
      message_SHL2 BYTE "SHL 2 bit: ",0
      message_SHR1 BYTE "SHR 1 bit: ",0
      message_SHR2 BYTE "SHR 2 bit: ",0
.code
main proc
      mov EDX, OFFSET message
      call WriteString
      call Crlf
      ; Left shift 1 bit
      mov AL,testData
                                ; AL=10110001
      mov CL,1
      SHL AL, CL
                                ; AL=01100010
                                                   CF=1
      mov EDX, OFFSET message_SHL1
      call printResult
      ; Left shift 2 bits
      mov AL, testData
                               ; AL=10110001
      mov CL,2
      SHL AL, CL
                                ; AL=11000100
                                                   CF=0
      mov EDX, OFFSET message_SHL2
      call printResult
      ; Right shift 1 bit
      mov AL,testData
                               ; AL=10110001
      mov CL,1
                                                   CF=1
      SHR AL, CL
                                ; AL=01011000
      mov EDX, OFFSET message_SHR1
      call printResult
      ; Right shift 2 bits
      mov AL, testData
                                ; AL=10110001
      mov CL,2
                                ; AL=00101100
                                                   CF=0
      SHR AL, CL
      mov EDX, OFFSET message_SHR2
      call printResult
```

## **Example - Bitwise Multiplication using SHL:**

Bitwise multiplication is performed when you shift a number's bits in a leftward direction. For example, SHL can perform multiplication by powers of 2. Shifting any operand left by  $\mathbf{n}$  bits multiplies the operand by  $\mathbf{2}^{\mathbf{n}}$ . So, the formula is:

```
multiplication = operand \times 2^n where n = number\ of\ bit\ shifts\ towards\ Left
```

For example, shifting the integer 5 left by 1 bit yields the product of  $5x2^1 = 10$ :

```
mov dl,5 Before: 0 0 0 0 1 0 1 = 5
shl dl,1 After: 0 0 0 0 1 0 1 0 = 10
```

If binary 00001010 (decimal 10) is shifted left by two bits, the result is the same as multiplying 10 b 22:

```
mov AL,10 ; before: 00001010
SHL AL,2 ; after: 00101000
```

### **Example - Bitwise Division using SHR:**

Bitwise division is accomplished when you shift a number's bits in a rightward direction. Shifting an unsigned integer right by  $\mathbf{n}$  bits divides the operand by  $\mathbf{2}^{\mathbf{n}}$ . So, the formula is:

```
division = operand \div 2^n where n = number\ of\ bit\ shifts\ towards\ Right
```

In the following statements, we divide 32 by 2<sup>1</sup>, producing 16:


```
mov dl,32 Before: 0010000 = 32
shr dl,1 After: 00010000 = 16
```

In the following example, 64 is divided by 2<sup>3</sup>:

```
mov AL,01000000b ; AL = 64
SHR AL,3 ; divide by 8, AL = 00001000b
```

### 9.1.3 Arithmetic Shift SAL and SAR Instructions

The **SAL** (shift arithmetic left) instruction works exactly the same as the **SHL** instruction. For each shift count, SAL shifts each bit in the destination operand to the next highest bit position. The lowest bit is assigned 0. The highest bit is moved to the Carry flag, and the bit that was in the Carry flag is discarded:




The **SAR** (shift arithmetic right) instruction performs a right arithmetic shift on its destination operand. The difference here is that the SAR instruction duplicates the sign bit in the most significant bit while shifting the bits towards right:



The following example shows how SAR duplicates the sign bit. AL is negative before and after it is shifted to the right:

```
mov AL,0F0h ; AL = 11110000b (-16)
SAR AL,1 ; AL = 11111000b (-8), CF = 0
```

Binary 11001111, for example, has a 1 in the sign bit. When shifted arithmetically 1 bit to the right, it becomes 11100111:



### **Example:**

```
Include Irvine32.inc
.data
      testData BYTE 10110001b
      message BYTE "Input binary: 1011 0001",0
      message_SAL1 BYTE "SAL 1 bit: ",0
      message_SAL2 BYTE "SAL 2 bit: ",0
      message_SAR1 BYTE "SAR 1 bit: ",0
      message_SAR2 BYTE "SAR 2 bit: ",0
. code
main proc
      mov EDX, OFFSET message
      call WriteString
      call Crlf
      ; Left arithmetic shift 1 bit
      mov AL, testData ; AL=10110001
      mov CL,1
```

```
; AL=01100010
                                                CF=1
      SAL AL, CL
      mov EDX, OFFSET message_SAL1
      call printResult
      ; Left arithmetic shift 2 bits
      mov AL,testData
                             ; AL=10110001
      mov CL,2
      mov CL,2
SAL AL,CL ; AL=11000100
                                                CF=0
      mov EDX, OFFSET message_SAL2
      call printResult
      ; Right arithmetic shift 1 bit
      mov AL, testData ; AL=10110001
      mov CL,1
                 ; AL=11011000
      SAR AL, CL
                                                CF=1
      mov EDX, OFFSET message_SAR1
      call printResult
      ; Right arithmetic shift 2 bits
      mov AL, testData ; AL=10110001
      mov CL,2
      SAR AL,CL
                             ; AL=11101100
                                                CF=0
      mov EDX, OFFSET message_SAR2
      call printResult
exit
main endp
printResult proc
      call WriteString
      ;mov EAX,0
      mov EBX, TYPE BYTE
      call WriteBinB
      call Crlf
      ret
printResult endp
end main
```

### **Example - Signed Division using SAR:**

You can divide a signed operand by a power of 2, using the SAR instruction. In the following example, -128 is divided by  $2^3$ . The quotient is -16:

```
mov AL,-128 ; AL = 10000000b (-128)
SAR AL,3 ; AL = 11110000b (-16)
```

### Example - Sign-Extend AX into EAX using SAR:

Suppose **AX** contains a signed integer and you want to extend its sign into EAX. First shift EAX 16 bits to the left, then shift it arithmetically 16 bits to the right:

```
mov AX,-128 ; EAX = ????FF80h
SHL EAX,16 ; EAX = FF800000h
SAR EAX,16 ; EAX = FFFFF80h
```

This code works same as we studied earlier using **MOVSX** instruction:


```
mov AX,-128 ; EAX = ????FF80h
```

```
movsx EAX,AX ; EAX = FFFFFF80h
```

### 9.1.4 ROL Instruction

Bitwise rotation occurs when you move the bits in a circular fashion. In some versions, the bit leaving one end of the number is immediately copied into the other end. Another type of rotation uses the Carry flag as an intermediate point for shifted bits.

The **ROL** (rotate left) instruction shifts each bit to the left. The highest bit is copied into the Carry flag and the lowest bit position. The instruction format is the same as for **SHL**:



**Note:** Bit rotation does not lose bits. A bit rotated off one end of a number appears again at the other end.

When using a rotation count greater than 1, the Carry flag contains the last bit rotated out of the MSB position:

```
MOV AL,00100000b
ROL AL,3 ; AL = 00000001b, CF = 1
```

### **Example - Exchanging Groups of Bits:**

We can use ROL to exchange the upper (bits 4–7) and lower (bits 0–3) halves of a byte. For example, 26h rotated four bits in either direction becomes 62h:

```
Include Irvine32.inc
.code
main proc
          MOV AL,26h
          ROL AL,4 ; AL = 62h
exit
main endp
end main
```

When rotating a multibyte integer by **four** bits, the effect is to rotate each hexadecimal digit one position to the right or left. Here, for example, we repeatedly rotate 6A4Bh left four bits, eventually ending up with the original value:

```
MOV AX,6A4Bh

ROL AX,4 ; AX = A4B6h


ROL AX,4 ; AX = 4B6Ah

ROL AX,4 ; AX = B6A4h

ROL AX,4 ; AX = 6A4Bh
```

### 9.1.5 ROR Instruction

The **ROR** (rotate right) instruction shifts each bit to the right and copies the lowest bit into the Carry flag and the highest bit position. The instruction format is the same as for **SHL**:



# 9.1.6 RCL (Rotate Cary Left) Instruction

The **RCL** (rotate carry left) instruction shifts each bit to the left, first copies the Carry flag to the LSB, then copies the MSB into the Carry flag:



If we imagine the Carry flag as an extra bit added to the high end of the operand, RCL looks like a rotate left operation.

### **Example - Recover a Bit from the Carry Flag:**

RCL can recover a bit that was previously shifted into the Carry flag (e.g., due to binary addition).

# 9.1.7 RCR (Rotate Cary Right) Instruction

The **RCR** (rotate carry right) instruction shifts each bit to the right, first copies the Carry flag into the MSB, then copies the LSB into the Carry flag:



As in the case of RCL, it helps to visualize the integer in this figure as a 9-bit value, with the Carry flag to the right of the LSB.

# 9.1.8 Signed Overflow

The Overflow flag is set if the act of shifting or rotating a signed integer by one bit position generates a value outside the signed integer range of the destination operand. To put it another way, the number's sign is reversed.

In the following example, a positive integer (+127) stored in an 8-bit register becomes negative (-2) when rotated left:

```
MOV AL,+127 ; AL = 01111111b
ROL AL,1 ; OF = 1, AL = 11111110b
```

Similarly, when -128 is shifted one position to the right, the Overflow flag is set. The result in AL (+64) has the opposite sign:

```
MOV AL,-128 ; AL = 10000000b
SHR AL,1 ; OF = 1, AL = 01000000b
```


Note: The value of the Overflow flag is undefined when the shift or rotation count is greater than 1.

### 9.1.9 SHLD and SHRD Instructions


The SHLD (shift left double) instruction shifts a destination operand a given number of bits to the left.

The bit positions opened up by the shift are filled by the most significant bits of the source operand. The source operand is not affected, but the Sign, Zero, Auxiliary, Parity, and Carry flags are affected:

SHLD dest, source, count



The SHRD (shift right double) instruction shifts a destination operand a given number of bits to the right. The bit positions opened up by the shift are filled by the least significant bits of the source operand:



The following instruction formats apply to both SHLD and SHRD:

```
SHLD reg16,reg16,CL/imm8
SHLD mem16,reg16,CL/imm8
SHLD reg32,reg32,CL/imm8
SHLD mem32,reg32,CL/imm8
```

### Example 1:

```
Include Irvine32.inc
.data
          testVal WORD 9BA6h
.code
main proc
          MOV AX,0AC36h
          SHLD testVal,AX,4 ; wval = BA6Ah
exit
main endp
end main
```

### Example 2:

```
Include Irvine32.inc
.code
main proc
MOV AX,234Bh
MOV DX,7654h
SHRD AX,DX,4
exit
main endp
end main
```

# Example 3 - Shifting an array of doublewords to the right by 4 bits:

```
Include Irvine32.inc
.data
       array DWORD 648B2165h,8C943A29h,6DFA4B86h,91F76C04h,8BAF9857h
. code
main proc
                                         ; shift count
       mov BL,4
      mov BL,4 ; shift count
mov ESI,OFFSET array ; offset of the array
mov ECX,(LENGTHOF array) - 1 ; number of array elements
L1:
       push ECX
                                         ; save loop counter
       mov EAX, [ESI + TYPE DWORD]
       mov CL, BL
                                         ; shift count
                                        ; shift EAX into high bits of [ESI]
       SHRD [ESI], EAX, CL
       add ESI, TYPE DWORD
                                        ; point to next doubleword pair
       pop ECX
                                          ; restore loop counter
       LOOP L1
       SHR DWORD PTR [ESI],4 ; shift the last doubleword
exit
main endp
end main
```

- SHLD and SHRD can be used to manipulate bit-mapped images, when groups of bits must be shifted left and right to reposition images on the screen.
- Another potential application is data encryption, in which the encryption algorithm involves the shifting
  of bits.
- These two instructions can be used when performing fast multiplication and division with very long integers.

# 9.2 Shift and Rotate Applications


When a program needs to move bits from one part of an integer to another, assembly language is a great tool for the job. Sometimes, we move a subset of a number's bits to position 0 to make it easier to isolate the value of the bits. In this section, we show a few common bit shift and rotate applications that are easy to implement. More applications will be found in the chapter 7 exercises.

# 9.2.1 Shifting Multiple Doublewords


We can shift an integer that has been divided into an array of bytes, words, or doublewords.

The following steps show how to shift an array of bytes 1 bit to the right:


Step 1: Shift the highest byte at [ESI+2] to the right, automatically copying its lowest bit into the Carry flag.




**Step 2:** Rotate the value at [ESI+1] to the right, filling the highest bit with the value of the Carry flag, and shifting the lowest bit into the Carry flag:



**Step 3:** Rotate the value at [ESI] to the right, filling the highest bit with the value of the Carry flag, and shifting the lowest bit into the Carry flag:



After Step 3 is complete, all bits have been shifted 1 position to the right:



Instructor: Syed Tehseen ul Hasan Shah

```
Include Irvine32.inc
.data
      ArraySize = 3
      array BYTE ArraySize DUP(99h) ; 1001 pattern in each nybble
. code
main PROC
      call DisplayArray
                                      ; display the array
      mov esi,0
      shr array[esi+2],1
rcr array[esi+1],1
                                  ; high byte
                                     ; middle byte, include Carry flag
                                    ; low byte, include Carry flag
      rcr array[esi],1
      call DisplayArray
                                      ; display the array
      exit
main ENDP
DisplayArray PROC
; Display the bytes from highest to lowest
      pushad
      mov ecx, ArraySize
      mov esi,ArraySize-1
L1:
      mov al,array[esi]
                                     ; size = byte
      mov ebx,1
      call WriteBinB
                                      ; display binary bits
      mov al,''
      call WriteChar
      sub esi,1
      Loop L1
      call Crlf
      popad
      ret
DisplayArray ENDP
END main
```

### 9.2.2 Binary Multiplication

We can get performance advantage of Assembly language in integer multiplication by using bit shifting rather than the MUL instruction. The **SHL** instruction performs unsigned multiplication when the multiplier is a power of 2. Shifting an unsigned integer n bits to the left multiplies it by  $2^n$ .

Any other multiplier can be expressed as the sum of powers of 2. For example, to multiply unsigned EAX by 36, we can write 36 as  $2^5 + 2^2$  and use the distributive property of multiplication:

```
EAX * 36 = EAX * (32 + 4)
= EAX * (2^5 + 2^2)
= (EAX * 2^5) + (EAX * 2^2)
```

Code will be:

# 9.2.3 Displaying Binary Bits


A common programming task is converting a binary integer to an ASCII binary string, allowing the latter to be displayed. The **SHL** instruction is useful in this regard because it copies the highest bit of an operand into the Carry flag each time the operand is shifted left. The following *BinToAsc* procedure is a simple implementation:

```
Include Irvine32.inc
.data
      binVal DWORD 1234ABCDh
                                        ; sample binary value
      buffer BYTE 32 dup(0),0
.code
main PROC
      mov eax,binVal ; EAX = binary integer
mov esi,OFFSET buffer ; point to the buffer
call BinToAsc ; do the conversion
                                      ; EAX = binary integer
             edx,OFFSET buffer ; display the buffer
      call WriteString
                                      ; output: 00010010001101001010101111001101
      call Crlf
      exit
main ENDP
; BinToAsc PROC
; Converts 32-bit binary integer to ASCII binary.
; Receives: EAX = binary integer, ESI points to buffer
; Returns: buffer filled with ASCII binary digits
BinToAsc PROC
      push ecx
      push esi
                                      ; number of bits in EAX
      mov
             ecx,32
L1:
      shl
                                      ; shift high bit into Carry flag
            eax,1
             BYTE PTR [esi],'0'; choose 0 as default digit
      mov
                                       ; if no Carry, jump to L2
      jnc
             BYTE PTR [esi], '1' ; else move 1 to buffer
      mov
L2:
                                      ; next buffer position
      inc
             esi
      loop L1
                                       ; shift another bit to left
```

```
pop esi
pop ecx
ret
BinToAsc ENDP
```

### 9.2.4 Extracting File Date Fields

When storage space is at a premium, system-level software often packs multiple data fields into a single integer. To uncover this data, applications often need to extract sequences of bits called bit strings. For example, in real-address mode, MS-DOS function 57h returns the date stamp of a file in DX. (The date stamp shows the date on which the file was last modified.) Bits 0 through 4 represent a day number between 1 and 31, bits 5 through 8 are the month number, and bits 9 through 15 hold the year number. If a file was last modified on March 10, 1999, the file's date stamp would appear as follows in the DX register (the year number is relative to 1980):



To extract a single bit string, shift its bits into the lowest part of a register and clear the irrelevant bit positions. The following code example extracts the day number field of a date stamp integer by making a copy of DL and masking off bits not belonging to the field:

```
mov al,dl ; make a copy of DL and al,00011111b ; clear bits 5-7 mov day,al ; save in day
```

To extract the month number field, we shift bits 5 through 8 into the low part of AL before masking off all other bits. AL is then copied into a variable:

```
mov ax,dx ; make a copy of DX shr ax,5 ; shift right 5 bits and al,00001111b ; clear bits 4-7 mov month,al ; save in month
```

The year number (bits 9 through 15) field is completely within the DH register. We copy it to AL and shift right by 1 bit:

```
mov al,dh ; make a copy of DH shr al,1 ; shift right one position mov ah,0 ; clear AH to zeros add ax,1980 ; year is relative to 1980 mov year,ax ; save in year
```