

Fix: Destination Host Unreachable (Persistent Solution using nmcli)

Goal: Route Internet through eth1 (172.16.x network) and keep eth0 for local LAN only.

Step 1: Check Current Network Connections

Run the following command to list all network connections:

Command:

```
nmcli connection show
```

Step 2: Configure eth1 (Internet Connection)

Assign static IP, gateway, and DNS to eth1 to route all Internet traffic through it.

Command:

```
sudo nmcli connection modify global-net ipv4.addresses 172.16.90.2/16 ipv4.gateway 172.16.0.3 ipv4.dns '8.8.8.8 1.1.1.1' ipv4.method manual
```

Step 3: Configure eth0 (Local Connection)

Assign static IP but no gateway to eth0 so it does not interfere with Internet routing.

Command:

```
sudo nmcli connection modify local-net ipv4.addresses 192.168.50.10/24 ipv4.gateway '' ipv4.method manual
```

Step 4: Apply Network Configuration

Restart both connections to apply changes.

Commands:

```
sudo nmcli connection down local-net
sudo nmcli connection down global-net
sudo nmcli connection up local-net
sudo nmcli connection up global-net
```

Step 5: Verify Routing Table

Check that the default route points to eth1 (172.16.0.3).

Command:

```
ip route show
```

Expected Output:

```
default via 172.16.0.3 dev eth1
172.16.0.0/16 dev eth1 proto kernel scope link src 172.16.90.2
192.168.50.0/24 dev eth0 proto kernel scope link src 192.168.50.10
```

Step 6: Test Connectivity

Run these commands to confirm successful Internet access.

Commands:

```
ping -I eth1 8.8.8.8
ping 8.8.8.8
ping google.com
```

Step 7: Confirm Persistence

Reboot and verify that the default route is still via eth1.

Command:

```
sudo reboot
ip route
```

Summary:

Interface	Connection Name	IP Address	Gateway	Purpose
eth0	local-net	192.168.50.10/24	(none)	Local LAN only
eth1	global-net	172.16.90.2/16	172.16.0.3	Internet access