
## 4: IPC





#### 4: IPC

- Interprocess Communication(IPC)
- □ IPC in Shared-Memory Systems
- IPC in Message-Passing Systems
- Examples of IPC Systems





### **Objectives**

- Describe and contrast interprocess communication using shared memory and message passing.
- Design programs that uses pipes and POSIX shared memory to perform interprocess communication.






### **Motivations for Program Reuse**

□ What would you do if you need to go through a file containing 10,000 names to count the number of names containing the "sam"?






### **Interprocess Communication**


- Processes within a system may be independent or cooperating
- Independent process cannot affect or be affected by the execution of another process
- Cooperating process can affect or be affected by other processes, including sharing data
- Advantages/Reasons of process cooperation
  - Information sharing: to share the already processed data
  - Computation speed-up: to focus on its own task
  - Modularity: e.g., database in one process which can be reused
  - Convenience
- □ But:
  - Added complexity
  - Deadlocks possible
  - Starvation possible






#### **Communications Models**


- Cooperating processes need interprocess communication (IPC)
- ☐ Interprocess communication:
  - Two (or more) different processes
  - Send and receive control information or data
  - Communicating through the kernel or other shared resources
  - Two sides of the interaction:
    - sender/receiver, client/server, caller/callee
  - □ The content: "message"
    - ▶ The message size is either fixed or variable





#### **Communications Models**


- Two models of IPC
  - Shared memory
  - Message passing



(a) Shared memory.

(b) Message passing.





#### **Interprocess Communication – Shared Memory**

- The system kernel maps an area of memory shared among the processes that wish to communicate
- The communication is under the control of the users processes not the operating system.
- Major issues is to provide mechanism that will allow the user processes to synchronize their actions when they access shared memory.
  - Sender doesn't delete unread data
  - Receiver doesn't read other data
- □ Synchronization is discussed in great details later






#### **Producer-Consumer Problem**

- Paradigm for cooperating processes, producer process produces information that is consumed by a consumer process
  - unbounded-buffer places no practical limit on the size of the buffer
    - Producer never has to wait because there is always extra space available for new information; only consumer might have to wait if no information is available to read
  - bounded-buffer assumes that there is a fixed buffer size
    - Producer might have to wait if there is no space available to store new information; consumer might have to wait if no information is available to read






### **Bounded-Buffer – Shared-Memory Solution**

#### Shared data


```
#define BUFFER_SIZE 8
typedef struct {
    . . .
} item;

item buffer[BUFFER_SIZE]; // shared data
int in = 0; // sharing status: produced
int out = 0; //sharing status: consumed
```





### **Producer Process – Shared Memory**





# Consumer Process – Shared Memory


```
item next consumed;
while (true) {
       while (in == out)
              ; /* do nothing, new item to consume */
       next consumed = buffer[out];
       out = (out + 1) % BUFFER SIZE;
       /* consume the item from the buffer */
          Out
                             In
                3
                             5
                                   6
```

0



- □ Solution is correct, but can **only use BUFFER\_SIZE-1 elements**
- Problems
  - Polling can be wasteful
  - □ Fixed checking time (ready or not), longer delay time






#### **Message Passing**

- Mechanism for processes to communicate and to synchronize their actions
- ☐ If processes *P* and *Q* wish to communicate, they need to:
  - Establish a communication link between them
  - Exchange messages via send()/receive()
- Implementation issues:
  - How are links established?
  - Can a link be associated with more than two processes?
  - How many links can there be between every pair of communicating processes?
  - What is the capacity of a link?
  - Is the size of a message that the link can accommodate fixed or variable?
  - Is a link unidirectional or bi-directional?






#### **Message Passing**

- Implementation of communication link
  - Physical:
    - Shared memory
    - Hardware bus
    - Network
  - Logical:
    - Direct (process to process) or indirect (mail box)
    - Synchronous (blocking) or asynchronous (non-blocking)
    - Automatic or explicit buffering






#### **Direct Communication**

- Processes must name each other explicitly:
  - send (P, message) send a message to process P
  - □ receive(Q, message) receive a message from process Q
- Properties of communication link
  - Links are established automatically
  - A link is associated with exactly one pair of communicating processes
  - Between each pair there exists exactly one link
  - The link may be unidirectional, but is usually bi-directional





#### **Indirect Communication**

- Messages are directed and received from mailboxes (also referred to as ports)
  - Each mailbox has a unique id
  - Processes can communicate only if they share a mailbox
- Properties of communication link
  - Link established only if processes share a common mailbox
  - A link may be associated with many processes
  - Each pair of processes may share several communication links
  - Link may be unidirectional or bi-directional
- Operations
  - create a new mailbox (port)
  - send and receive messages through mailbox
  - destroy a mailbox
- Primitives are defined as:

send(A, message) - send a message to mailbox A


**receive**(A, message) – receive a message from mailbox A



#### **Indirect Communication**

- Mailbox sharing
  - $P_1$ ,  $P_2$ , and  $P_3$  share mailbox A
  - $P_1$ , sends;  $P_2$  and  $P_3$  receive
  - Who gets the message?
- Possible Solutions
  - Allow a link to be associated with at most two processes
  - Allow only one process at a time to execute a receive operation
  - Allow the system to select arbitrarily the receiver. Sender is notified who the receiver was.







## **Synchronization**

- Message passing may be either blocking or non-blocking
- Blocking is considered synchronous
  - Blocking send -- the sender is blocked until the message is received
  - Blocking receive -- the receiver is blocked until a message is available
- Non-blocking is considered asynchronous
  - Non-blocking send -- the sender sends the message and continues without waiting for the message to be received
  - Non-blocking receive -- the receiver receives:
    - A valid message, or
    - Null message
- Different combinations possible
  - If both send and receive are blocking, we have a rendezvous








## **Buffering**

- Queue of messages attached to the link, in kernel memory
- Implemented in one of three ways
  - Zero capacity no messages are queued on a link.
     Sender must wait for receiver (rendezvous)
  - 2. Bounded capacity finite length of *n* messages Sender must wait if link full
  - 3. Unbounded capacity infinite length Sender never waits





### **Examples of IPC Systems - POSIX**

- POSIX Shared Memory -- Producer
  - Producer process first creates shared memory segment
    shm\_fd = shm\_open(name, O\_CREAT | O\_RDWR, 0666);
  - Also used to open an existing segment to share it
  - Set the size of the file object


```
ftruncate(shm_fd, 4096); int ftruncate(int fd, off_t length)
```

map the shared memory segment in the address space of the process

Now the process could write to the shared memory

```
sprintf(ptr, "%s", "Writing to shared memory");
```

void\* mmap(void \*addr, size\_t length, int prot, int flags, int fd, off\_t offset);



### **Examples of IPC Systems - POSIX**


- POSIX Shared Memory Consumer
  - consumer process opens shared memory object name shm\_fd = shm\_open (name, O\_RDONLY, 0666);
    - Returns file descriptor (int) which identifies the file
  - map the shared memory object in the address space of the process
    - ptr = mmap(0,SIZE, PROT\_READ, MAP\_SHARED, shm\_fd, 0);
  - Now the process can read from the shared memory object printf("%s", (char \*)ptr);
  - remove the shared memory object once finished shm\_unlink(name);

```
int shm open( const char *name, int oflag, mode t mode);
void* mmap(void* start,size_t length,int prot,int flags,int fd,off_t offset);
int shm_unlink( const char *name);
```



#### **IPC POSIX Producer**


```
#include <stdio.h>
#include <stdlib.h>
                                                 shm producer.c
#include <string.h>
                                                 compiling command:
#include <fcntl.h>
#include <sys/shm.h>
                                                 gcc -o producer shm_producer.c -lrt
#include <sys/stat.h>
#include <sys/mman.h>
#include <unistd.h>
int main() {
      const int SIZE = 4096;
                                    //the size of shared memory object
      const char *name = "OS";
                                    //name of the shared memory object
      const char *message0= "Studying Operating Systems ";//string written to shared memory
      const char *message1= "Is Fun!\n";
      int shm fd;
                        //shared memory file descriptor
      void *ptr;
                        //pointer to shared memory object
      /* create the shared memory segment/object */
      shm_fd = Shm Open(name, O_CREAT | O_RDWR, 0666);
      ftruncate(shm_fd, SIZE); /* configure the size of the shared memory segment */
      /* now map the shared memory segment in the address space of the process */
      ptr = MMap(0,SIZE, PROT READ | PROT WRITE, MAP SHARED, shm fd, 0);
      if (ptr == MAP FAILED) {
            printf("Map failed\n");
            return -1;
      /* Now write to the shared memory region.
       * Note we must increment the value of ptr after each write. */
      sprintf(ptr, "%s", message0);
      ptr += strlen(message0);
      sprintf(ptr, "%s", message1);
      ptr += strlen(message1);
      return 0;
```



#### **IPC POSIX Consumer**

```
#include <stdio.h>
                                           shm consumer.c
#include <stdlib.h>
#include <string.h>
                                           compiling command:
#include <fcntl.h>
#include <sys/shm.h>
                                            gcc –o consumer shm_consumer.c -lrt
#include <sys/stat.h>
#include <sys/mman.h>
int main() {
                                     //name of the shared memory object
      const char *name = "OS";
      const int SIZE = 4096;
                                     //size of shared memory object
      int shm fd;
                                     //shared memory file descriptor
      void *ptr;
                                     //pointer to shared memory object
      /* open the shared memory segment */
      shm fd = shm open(name, O RDONLY, 0666);
      if (shm fd == -1) {
            printf("shared memory failed\n");
            exit(-1);
      /* now map the shared memory segment in the address space of the process */
      ptr = mmap(0,SIZE, PROT READ, MAP SHARED, shm fd, 0);
      if (ptr == MAP FAILED) {
            printf("Map failed\n");
            exit(-1);
      /* now read from the shared memory region */
      printf("%s", (char*)ptr);
      /* remove the shared memory segment */
      if (shm_unlink(name) == -1) {
            printf("Error removing %s\n", name);
            exit(-1);
      return 0;
```







### **Examples of IPC Systems – Windows**

- Message-passing centric via advanced local procedure call (ALPC) facility
  - Only works between processes on the same system
  - Uses ports (like mailboxes) to establish and maintain communication channels
  - Communication works as follows:
    - The client opens a handle to the subsystem's connection port object.
    - The client sends a connection request.
    - The server creates two private **communication ports** and returns the handle to one of them to the client.
    - The client and server use the corresponding port handle to send messages or callbacks and to listen for replies.






### **ALPC in Windows**



- 1. For small messages (up to 256 bytes), the port's message queue is used as intermediate storage, and the messages are copied from one process to the other.
- 2. Larger messages must be passed through a **section object**, which is a region of shared memory associated with the channel.
- 3. When the amount of data is too large to fit into a section object, an API is available that allows server processes to read and write directly into the address space of a client.


The ALPC facility in Windows is not part of the Windows API and hence is not visible to the application programmer.



### **Pipes**

- Acts as a conduit allowing two processes to communicate on the same computer
- Issues:
  - 1. Is communication unidirectional or bidirectional?
  - 2. In two-way communication, is it half or full-duplex(data can travel in both directions at the same time)?
  - 3. Must there exist a relationship (i.e., parent-child) between the communicating processes?
  - 4. Can the pipes be used over a network?
- □ **Ordinary pipes** cannot be accessed from outside the process that created it. Typically, a parent process creates a pipe and uses it to communicate with a child process that it created.
- □ Named pipes can be accessed without a parent-child relationship.





### **Pipes**


- A stream of communication between two processes
- You can think of it as a virtual file stream shared between two processes
  - A process can read and/or write to a pipe
  - The pipe function gets two descriptors (integer labels)
  - Read descriptor read from the pipe
  - Write descriptor write to the pipe
  - Both processes must know the descriptors
  - read and write are used with the pipe





### **Ordinary Pipes**

- Ordinary Pipes allow communication in standard producer-consumer style
- Producer writes to one end (the write-end of the pipe)
- Consumer reads from the other end (the read-end of the pipe)
- Ordinary pipes are therefore unidirectional
  - create two separate pipes if bidirectional communication is necessary
- □ Require **parent-child relationship** between communicating processes




Windows calls these anonymous pipes





Every process has at least 3


Files...









If the process creates a pipe, it would have 2 more files opened.








Spawn a child process, it would have the same files opened.






#### File redirection




- File Descriptors
  - Just a Number
- ▶ In Linux/Unix,
  - 0 for stdin
  - 1 for stdout
  - 2 for stderr
- Any number for the PipeIn or PipeOut





### File redirection



- Aim: get 1 to be the same object as pipeout.
- Use dup system call.






### **Unix File Descriptors**


- Unix/Linux files are numbered
  - □ 0, 1, 2 ... etc
  - 0 is stdin, 1 is stdout, 2 is stderr
  - By default,
    - scanf and std::cin gets input from stdin.
    - printf and std::cout will print to stdout.
    - The default "file" opened for stdin, stdout and stderr will be the console. (where you can observe the printing)
  - However, using redirection, we can actually get 0, 1 or 2 to be "files" other than the console.







### **Using dup**

- close() system call closes a file. (Renders the file descriptor invalid)
- ☐ The **dup()** system call duplicates the given file descriptor using the lowest available file descriptor number.






#### What does dup do?







## "grep abc | wc"





Ordinary pipe in UNIX

pipe.c

gcc -o pipe pipe.c

```
#include <sys/types.h>
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <unistd.h>
#include <sys/wait.h>
#define BUFFER SIZE 80
#define READ END 0
#define WRITE END 1
int main(void)
      char write msg[BUFFER SIZE] = "Greetings
      from parent process";
      char read_msg[BUFFER_SIZE];
      int fd[2];
      pid_t pid;
      int status;
      /* create the pipe */
      if (pipe(fd) == -1) {
            fprintf(stderr,"Pipe failed");
            return 1;
      /* fork a child process */
      pid = fork();
      if (pid < 0) { /* error occurred */
            fprintf(stderr, "Fork Failed");
            return 1;
      }
```

```
Parent Child

fd [0] closed fd [0] fd [1]

x ______ x ____ closed
```

```
if (pid > 0) { /* parent process */
            /* close the unused end of the pipe */
            close(fd[READ_END]); //optional
            /* write to the pipe */
            write(fd[WRITE END], write msg,
            strlen(write msq)+1);
            /* close the write end of the pipe */
            close(fd[WRITE END]);
            pid = wait(&status);
            printf("Parent: child(%d) exit(%d)\n",pid,
                        status);
      else { /* child process */
            /* close the unused end of the pipe */
            close(fd[WRITE_END]); //optional
            /* read from the pipe */
            read(fd[READ_END], read_msg, BUFFER_SIZE);
            printf("Child Read: %s",read msq);
            /* close the read end of the pipe */
            close(fd[READ_END]);
   return 0;
}
```




#### Ordinary pipe in Windows

win\_pipe\_parent.c

```
//Windows anonymous pipe -- parent process
#include <stdio.h>
#include <stdlib.h>
#include <windows.h>
#define BUFFER_SIZE 25
int main(VOID) {
            HANDLE ReadHandle, WriteHandle;
            STARTUPINFO si:
            PROCESS INFORMATION pi;
            char message[BUFFER SIZE] = "Greetings";
            DWORD written;
            /* set up security attributes allowing pipes to be inherited */
            SECURITY ATTRIBUTES sa = {sizeof(SECURITY ATTRIBUTES), NULL, TRUE};
            /* allocate memory */
            ZeroMemory(&pi, sizeof(pi));
            /* create the pipe */
            if (!CreatePipe(&ReadHandle, &WriteHandle, &sa, 0)) {
                         fprintf(stderr, "Create Pipe Failed");
                         return 1;
            /* establish the START INFO structure for the child process */
            GetStartupInfo(&si);
            si.hStdOutput = GetStdHandle(STD_OUTPUT_HANDLE);
            /* redirect standard input to the read end of the pipe */
            si.hStdInput = ReadHandle;
            si.dwFlags = STARTF USESTDHANDLES;
```





Ordinary pipe in Windows cont.

win\_pipe\_parent.c


```
/* don't allow the child to inherit the write end of pipe */
SetHandleInformation(WriteHandle, HANDLE_FLAG INHERIT, 0);
/* create the child process */
CreateProcess(NULL, "child.exe", NULL, NULL,
TRUE, /* inherit handles */
0, NULL, NULL, &si, &pi);
/* close the unused end of the pipe */
CloseHandle(ReadHandle);
/* the parent writes to the pipe */
if (!WriteFile(WriteHandle, message,BUFFER_SIZE,&written,NULL))
            fprintf(stderr, "Error writing to pipe.");
/* close the write end of the pipe */
CloseHandle(WriteHandle);
/* wait for the child to exit */
WaitForSingleObject(pi.hProcess, INFINITE);
CloseHandle(pi.hProcess);
CloseHandle(pi.hThread);
//Sleep(10000);
return 0;
```



Ordinary pipe in Windows cont.

win\_pipe\_child.c


```
//Windows anonymous pipe -- child process
//executable filename: child.exe
#include <stdio.h>
#include <windows.h>
#define BUFFER SIZE 25
int main(VOID) {
         HANDLE ReadHandle;
         CHAR buffer[BUFFER SIZE];
         DWORD read;
         /* get the read handle of the pipe */
         ReadHandle = GetStdHandle(STD INPUT HANDLE);
         /* the child reads from the pipe */
         if (ReadFile(ReadHandle, buffer, BUFFER_SIZE, &read, NULL))
                   printf("child read message[%s]",buffer);
         else
                   fprintf(stderr, "Error reading from pipe");
         return 0;
```



#### **Named Pipes**

- Named Pipes are more powerful than ordinary pipes
- Communication can be bidirectional
- No parent-child relationship is necessary between the communicating processes
- Several (>=2) processes can use the named pipe for communication
- Provided on both UNIX and Windows systems





### **Named Pipes Example1**

writer.c

gcc -o writer writer.c ./writer &


```
#include <fcntl.h>
#include <sys/stat.h>
#include <sys/types.h>
#include <unistd.h>
int main() {
  int fd;
  char *myfifo = "/tmp/myfifo";
  char msg[]= "Hi,this is named pipe";
  /* create the FIFO (named pipe) */
  mkfifo(myfifo, 0666);
  /* write msg to the FIFO */
  fd = open(myfifo, O_WRONLY);
  write(fd, msg, sizeof(msg));
  close(fd);
  /* remove the FIFO */
  unlink(myfifo);
  return 0;
```

reader.c

gcc –o reader reader.c ./reader

```
#include <fcntl.h>
#include <stdio.h>
#include <sys/stat.h>
#include <unistd.h>
#define MAX BUF 1024
int main() {
  int fd;
  char *myfifo = "/tmp/myfifo";
  char buf[MAX BUF];
  // open, read, & display the msg from the FIFO
  fd = open(myfifo, O_RDONLY);
  read(fd, buf, MAX BUF);
  printf("Received: %s\n", buf);
  close(fd);
  return 0;
```





#### Named Pipes Example2

#### fifo\_server.c

```
#include <stdio.h>
#include <stdlib.h>
#include <sys/stat.h>
#include <unistd.h>
#include <string.h>
#define FIFO FILE
                       "MYFIFO2"
int main(void) {
     FILE *fp;
     char readbuf[80];
     /* Create the FIFO if it does not exist */
     umask(0); // set file mode creation mask
      mknod(FIFO_FILE, S_IFIFO | 0666, 0);
                  //create a FIFO-special file
     while (1) {
           fp = fopen(FIFO FILE, "r");
           fgets(readbuf, 80, fp);
           printf("Received string: %s\n", readbuf);
           fclose(fp);
           if (strncmp(readbuf, "exit", 4) == 0)
              break;
      }
     return(0);
```

#### fifo\_client.c

```
#include <stdio.h>
#include <stdlib.h>
#define FIFO FILE
                       "MYFIFO2"
int main(int argc, char *argv[]) {
      FILE *fp;
      if (argc != 2) {
            printf("USAGE: fifo client [string]\n");
            exit(1);
      }
      if ((fp = fopen(FIFO_FILE, "w")) == NULL) {
            perror("fopen");
            exit(1);
      }
      fputs(argv[1], fp);
     fclose(fp);
      return(0);
}
```

int mknod(const char \*pathname, mode\_t mode, dev\_t dev);


The system call **mknod**() creates a filesystem node (file, device special file or named pipe) named *pathname*, with attributes specified by *mode* and *dev*.



#### **Named Pipes**

# mode\_t umask(mode\_t mask); umask is used to set permission of the file or directory

Octal digit in umask command	Permissions the mask will prohibit from being set during file creation	Octal digit in umask command	Binary in the mask	Negation of mask	Logical AND with "rwx" request <sup>[5]</sup>
0	any permission may be set (read, write, execute)	0	000	111	rwx
1	setting of execute permission is prohibited (read and write)	1	001	110	rw-
2	setting of write permission is prohibited (read and execute)	2	010	101	r-x
3	setting of write and execute permission is prohibited (read only)	3	011	100	r
4	setting of read permission is prohibited (write and execute)	4	100	011	-WX
5	setting of read and execute permission is prohibited (write only)	5	101	010	-W-
6	setting of read and write permission is prohibited (execute only)	6	110	001	X
7	all permissions are prohibited from being set (no permissions)	7	111	000	





Named Pipes	Anonymous Pipes	
Sharable btw any processes (subject to permissions)	Sharable btw processes of the same ancestry	
Full Duplex in Windows Half Duplex in Linux	Unidirectional	
CreateNamedPipes (Windows) mkfifo (Unix/Linux)	CreatePipes (Windows) pipe (Linux)	
Obtain the pipe by the name of the pipe	Obtain the pipe from parent	





#### Message Queue


- "Typed" Message Passing
- Message Queue: organizes messages in a linked list
  - Supports asynchronous communication (non-blocking)
- □ Format of the message: type + data
  - Type: represented by an integer, the specific meaning is determined by the user
- Message queues are indirect messaging
  - Establish connections by sharing a queue

#### System V example

```
key = ftok("./msgque", 11);
msgid = msgget(key, 0666
| IPC_CREAT);
message.mesg_type = 1;
msgsnd(msgid, &message,
sizeof(message), 0);
```

```
key = ftok("./msgque", 11);
msgid = msgget(key, 0666 |
IPC_CREAT);
msgrcv(msgid, &message,
sizeof(message), 1, 0);
msgctl(msgid, IPC_RMID,
NULL);
```






#### Message Queue

- Organization of message queues
  - Basically, follow the FIFO (First-In-First-Out) principle
  - Write to message queue: append to the end of the queue
  - Read from the message queue: popped from the head of the queue
- Allow query by type: Recv(A, type, message)
  - type is 0: returns the first message (FIFO)
  - oterwise, query based on the type number
    - If type > 0, return the first message of that type






## **Signal**

- A signal is a small message that notifies a process that an event of some type has occurred in the system.
  - linux> /bin/kill -9 -15213
  - kill(15213, SIGKILL);
- Whenever there is a transition from kernel-mode to user-mode execution
  - e.g., on return from a syscall c
  - scheduling onto the CPU
- The kernel checks whether there is a pending unblocked signal for which the process has established a signal handler.
- If there is, start signal handling steps

#include <signal.h>
typedef void (\*sighandler\_t)(int);
sighandler t signal(int signum, sighandler t handler);








### **Signal**

Number	Name	Default action	Corresponding event		
1	SIGHUP	Terminate	Terminal line hangup		
2	SIGINT	Terminate	Interrupt from keyboard		
3	SIGQUIT	Terminate	Quit from keyboard		
4	SIGILL	Terminate	Illegal instruction		
5	SIGTRAP	Terminate and dump core a	Trace trap		
6	SIGABRT	Terminate and dump core a	Abort signal from abort function		
7	SIGBUS	Terminate	Bus error		
8	SIGFPE	Terminate and dump core a	Floating-point exception		
9	SIGKILL	Terminate b	Kill program		
10	SIGUSR1	Terminate	User-defined signal 1		
11	SIGSEGV	Terminate and dump core a	Invalid memory reference (seg fault)		
12	SIGUSR2	Terminate	User-defined signal 2		
13	SIGPIPE	Terminate	Wrote to a pipe with no reader		
14	SIGALRM	Terminate	Timer signal from alarm function		
15	SIGTERM	Terminate	Software termination signal		
16	SIGSTKFLT	Terminate	Stack fault on coprocessor		
17	SIGCHLD	Ignore	A child process has stopped or terminated		
18	SIGCONT	Ignore	Continue process if stopped		
19	SIGSTOP	Stop until next SIGCONT <sup>b</sup>	Stop signal not from terminal		
20	SIGTSTP	Stop until next SIGCONT	Stop signal from terminal		
21	SIGTTIN	Stop until next SIGCONT	Background process read from terminal		
22	SIGTTOU	Stop until next SIGCONT	Background process wrote to terminal		
23	SIGURG	Ignore	Urgent condition on socket		
24	SIGXCPU	Terminate	CPU time limit exceeded		
25	SIGXFSZ	Terminate	File size limit exceeded		
26	SIGVTALRM	Terminate	Virtual timer expired		
27	SIGPROF	Terminate	Profiling timer expired		
28	SIGWINCH	Ignore	Window size changed		
29	SIGIO	Terminate	I/O now possible on a descriptor		
30	SIGPWR	Terminate	Power failure		


Figure 8.26 Linux signals. Notes: (a) Years ago, main memory was implemented with a technology known as core memory. "Dumping core" is a historical term that means writing an image of the code and data memory segments to disk. (b) This signal can be neither caught nor ignored. (Source: man 7 signal. Data from the Linux Foundation.)






#### **Communications in Client-Server Systems**

- Sockets
- Remote Procedure Calls (RPC)







### **Summary**

What is a process?

**Process states** 

new/ready/running/waiting/terminated

How does OS represent a process? PCB

task-struct

Scheduling queues

ready queue, wait queue

Interprocess communication methods:

shared memory/message passing

Process creation and termination

fork(), exit(), abort(), wait(), execlp(), execvp()

zombie and orphans

Understand process tree

Communication methods:

pipes/shared memory/massage queue/sockets/rpc/

Two kinds of pipes:

Ordinary / Named pipes



## **End of Chapter 4**

