



**Ariemmas**

POINT OF SALE

# Staff Training Guide

Everything cashiers and administrators need to run the till, sell by weight, take payment, and track every transaction — with pictures of every screen.

For Cashiers

For Administrators

Hardware Setup

Troubleshooting

---

Ariemmas Shop · Mongu, Zambia

Version 1.0 · Application v1.0.10

---

Ariemmas POS — Staff Training Guide

Part 1: For Cashiers

## CONTENTS

# What's in this guide

## 1 Welcome & the basics — what the system is, who uses it

## 2 Cashier Guide — sign in, shift, sell, weigh, take payment, close

2.1 Signing in · 2.2 Opening your shift · 2.3 The sale screen

2.4 Adding products · 2.5 Selling by weight · 2.6 Taking payment

2.7 Receipt & cash drawer · 2.8 Closing your shift · 2.9 The rules

## 3 Administrator Guide — products, barcodes, reports, exports

3.1 Products · 3.2 Barcodes · 3.3 Butchery items · 3.4 Reports · 3.5 Settings

## 4 Hardware: printer & cash drawer — wiring and first-time setup

## 5 Troubleshooting & FAQ — common problems and fixes

## 6 Quick reference card — logins and keyboard shortcuts (print & pin up)

### How to read this guide

Steps you perform are **numbered**. Buttons and screen labels look like **"Open Shift"**. Keys on the keyboard look like **F12**. Every important screen has a picture so you can match what you see.

## Welcome & the basics

Ariemmas POS is the till software the shop runs on its touchscreen terminals. It records every sale, prints receipts, opens the cash drawer, tracks stock, and shows the owner exactly how much was sold and by whom.

### 1.1 Who uses it

#### CASHIER

##### Runs the till

Signs in with a cashier login, opens a shift with their name, scans or searches products, weighs butchery items, takes cash or mobile money, and closes the shift at the end of the day.

#### ADMINISTRATOR

##### Runs the shop

Adds and prices products, prints barcodes, marks items as sold-by-weight, reads the daily reports (who sold what), exports to Excel, and configures the printer and drawer.

### 1.2 The three things every cashier does, every day

- 1 **Open a shift** when you start — type your name and the cash in the drawer.
- 2 **Ring up sales** all day — scan/search items, take payment, hand over the receipt.
- 3 **Close the shift** when you finish — count the drawer so the totals balance.

#### Works without internet

The till keeps working even if the internet goes down. Sales are saved on the terminal and sent to the owner's dashboard automatically when the connection returns.

### 1.3 A note on prices and VAT


All prices are entered **VAT-inclusive** (the price on the shelf is the price the customer pays). The system works out the 16% VAT portion automatically and shows it on the receipt and in reports. You never calculate VAT by hand.

## Cashier Guide

This is everything you do on the till, from signing in to closing your shift. Follow it in order the first few times and it will quickly become second nature.


### 2.1 Signing in

When the terminal is ready you'll see the sign-in screen. Each cashier has their own login and 4-digit PIN.



**The sign-in screen.** Your cashier logins are listed on the right under **"Cashier Logins"**.

- 1 Find your name in the **Cashier Logins** list (Cashier 1 to Cashier 5).
- 2 **Tap your row** — this fills in your username and PIN automatically.
- 3 Tap **"Sign In"**.



Tapping a cashier row fills the username and PIN ready to sign in.

### Use your own login

Always sign in as yourself. Every sale is tagged with your login, so the owner can see who served each customer. Signing in as someone else makes the reports wrong.

## 2.2 Opening your shift

Before you can sell anything you must open a shift. This records who is on the till and how much cash you started with.

The screenshot shows the Ariemmas POS interface. At the top, there's a header with 'Ariemmas', 'Sale', a clock showing '14:02:00 Sat 6 Jun', and a 'No Shift' badge. Below the header is a search bar and a table with columns '#', 'ITEM', 'QTY', 'PRICE', and 'TOTAL'. A modal window titled 'Open Shift' is centered on the screen. It contains instructions: 'Open a new shift to start recording sales. Count the cash in the drawer before you begin.' It has two input fields: 'CASHIER'S NAME' with 'Mary Banda' entered, and 'OPENING CASH (K)' with '1000' entered. A note below the second field says 'Opening cash should be K 1,000.00 or less.' At the bottom of the modal is a green 'Open Shift' button. To the right of the modal is a 'Receipt' section with columns 'ITEM', 'QTY', and 'TOTAL'. It shows 'Subtotal K 0.00', 'VAT (16%) K 0.00', and 'Total K 0.00'. At the bottom of the receipt is a 'Pay K 0.00' button. The bottom of the screen has a row of function keys: F1 New Sale, F2 Search, F3 Discount, F5 Drawer, F6 Remove, and F12 Pay.


**The Open Shift window.** It asks for your real name and the opening cash.

- 1 If you see **"No Shift"** at the top right, tap it to open this window.
- 2 In **"Cashier's Name"**, type the name of the real person on the till today — for example *Mary Banda*. (The login may be "Cashier 1", but the owner wants the real name.)
- 3 In **"Opening Cash (K)"**, type the amount of cash counted in the drawer.
- 4 Tap **"Open Shift"**. The badge at the top changes to **"Shift Open"**.

### Why the name matters

Five cashiers share three terminals and swap during the day. The name you type here is how the owner's report tells *who* actually rang each sale. Always type your own name.

## 2.3 The sale screen



**The sale screen.** Search bar at the top, the cart in the middle, and the running **Receipt** with the total on the right.


- **Search bar (top):** scan a barcode or type a product name here.
- **Cart (middle):** the items in the current sale, with quantity and price.
- **Receipt panel (right):** the running subtotal, VAT, and the big **Total**.
- **Pay button (bottom right):** shows the amount due — tap it to take payment.

## 2.4 Adding products to the sale


There are two ways to add an item — whichever is faster for you.

**A. Scan the barcode.** Point the barcode scanner at the product. It's added to the cart instantly.

**B. Search by name.** Tap the search bar (or press **F2**) and start typing. A list appears — tap the item you want.



Typing in the search bar shows matching products with their price and stock.



**Items in the cart.** Use the **–** and **+** buttons to change quantity, or the **×** to remove a line. The total updates on the right.


### Handy keys

**F2** jump to search · **F8** remove the selected line · **F1** clear the whole sale · **F12** take payment.

## 2.5 Selling by weight — the butchery


Meat and other items sold by weight work a little differently. The price you see is the **price per kilogram**, and you tell the till how much the item weighs.

- 1 **Weigh the item on the shop scale.** The scale shows the weight, for example **0.450 kg**. (The scale is separate — the till does not read it automatically.)
- 2 Scan or search the item as normal — for example *T-Bone Steak*.
- 3 Because it's a weighed item, a **"Weigh item"** window pops up.




**The Weigh item window.** It shows the item name and the price per kg at the top.

- 1 Type the weight from the scale into **"Weight (kg)"** — for example **0.450**. Use a dot for the decimal.
- 2 The **Line total** updates as you type, so you can check it before adding.
- 3 Tap **"Add to cart"** (or press Enter).



0.450 kg of T-Bone at K 289.99/kg = **K 130.50**, shown live before you add it.



The weighed item in the cart. It reads **"T-Bone Steak (0.450 kg)"** so it's clear how much was sold.

### Careful: kilograms, not grams


The scale shows kilograms. If it reads **0.450**, type **0.450** — not **450**. Typing **450** would charge the customer for 450 kilograms. If the line total looks far too big, you typed grams by mistake — tap **X** and re-do it.

### Each weighing is its own line

If a customer buys two separate cuts of the same meat, weigh and add them one at a time. Each becomes its own line, so you can sell different weights of the same product in one sale.

## 2.6 Taking payment


When the cart is complete, tap the green **"Pay"** button (or press **F12**).



**The payment window.** Choose **Cash** or **Mobile Money**. The amount due is shown big at the top.

### For a cash payment:

- 1 Type the cash the customer handed you into **"Cash Received"**, or tap one of the quick amounts (**K 50, K 100, K 500...**).
- 2 The **Change** to give back is worked out for you.
- 3 Tap **"Pay"** to finish.




Customer paid **K 500** on a **K 170.50** sale → the till shows **K 329.50** change.

**For mobile money:** tap **Mobile Money**, enter the reference number from the customer's payment confirmation, and tap **Pay**.

## 2.7 Receipt & cash drawer

As soon as the sale is finished:

- The **receipt prints** automatically — hand it to the customer.
- On a **cash** sale, the **cash drawer opens** automatically so you can put the money in and take out change.
- A **"Thank You"** screen confirms the sale, showing the total, amount paid, and change.



**Sale complete.** The screen confirms total, paid, and change, then returns to a fresh sale.

## 2.8 Closing your shift

At the end of your time on the till, close your shift so the day's cash can be checked.

- 1 Tap the **"Shift Open"** badge at the top right.
- 2 Count the cash in the drawer and type it into **"Closing Cash"**.
- 3 Add a note if anything unusual happened (optional).
- 4 Tap **"Close Shift"**. The system compares your count to what it expected and records any difference.

### Swapping cashiers on one terminal

When you hand the till to the next person: **close your shift**, then **sign out** (the arrow icon, top right). The next cashier signs in with their own login and opens their own shift.


## 2.9 The rules — read this once

| RULE                                      | WHY                                                                                                     |
|-------------------------------------------|---------------------------------------------------------------------------------------------------------|
| Sign in as yourself                       | Every sale is tagged to your login for the owner's report.                                              |
| Type your real name at shift open         | So the report shows the person, not just "Cashier 1".                                                   |
| One cashier login, one terminal at a time | If you're already signed in on another till, the system will stop a second sign-in with the same login. |
| Check the weight before adding meat       | Kilograms, not grams. A wrong weight overcharges the customer.                                          |
| Close your shift before handing over      | So the drawer balances against your sales.                                                              |

## Administrator Guide

Admins sign in with the **admin** login (the PIN is in the credentials file saved to the Downloads folder when the app is first installed). Admins see extra tabs: **Products**, **Reports**, and **Settings**.

### 3.1 Managing products



| PRODUCT                                                | BARCODE | CATEGORY    | PRICE    | COST    | STOCK | STATUS   | ACTIONS |
|--------------------------------------------------------|---------|-------------|----------|---------|-------|----------|---------|
| AA Batteries (4pk)<br><small>each - VAT 16%</small>    | 5490678 | Electronics | K 35.00  | K 18.00 | 39    | In Stock |         |
| Apples (1kg)<br><small>each - VAT 16%</small>          | 2324345 | Groceries   | K 55.89  | K 40.00 | 120   | In Stock |         |
| Bar Soap (3-pack)<br><small>each - VAT 16%</small>     | 9945123 | Household   | K 35.00  | K 22.00 | 80    | In Stock |         |
| Bread (White)<br><small>each - VAT 16%</small>         | 7834562 | Groceries   | K 25.00  | K 18.00 | 28    | In Stock |         |
| Bream Fish (Medium)<br><small>each - VAT 16%</small>   | 4490678 | Meat & Fish | K 120.00 | K 80.00 | 15    | In Stock |         |
| Candles (Pack of 6)<br><small>each - VAT 16%</small>   | 7712890 | Household   | K 18.00  | K 10.00 | 75    | In Stock |         |
| Castle Lager 340ml<br><small>each - VAT 16%</small>    | 1167345 | Beverages   | K 22.00  | K 15.00 | 100   | In Stock |         |
| Chicken Pieces (1kg)<br><small>each - VAT 16%</small>  | 3389567 | Meat & Fish | K 85.00  | K 60.00 | 40    | In Stock |         |
| Chitenge Fabric (6yd)<br><small>each - VAT 16%</small> | 3278456 | Clothing    | K 150.00 | K 90.00 | 20    | In Stock |         |
| Coca-Cola 500ml<br><small>each - VAT 16%</small>       | 8945123 | Beverages   | K 15.00  | K 10.00 | 197   | In Stock |         |

**The Products screen.** Every item with its barcode, price, stock and status. Tap **"Add Product"** to create one, or the pencil to edit.

- 1 Go to the **Products** tab.
- 2 Tap **"Add Product"** (top right) to add a new item, or the **pencil** icon to edit an existing one.
- 3 Fill in the name, price, category, stock and VAT rate, then tap **"Add Product"** / **"Update Product"**.

## 3.2 Generating & printing barcodes

For items you prepare in-store (like home-made food) that have no barcode, the system can **make one for you** and you can print it as a label.

The screenshot shows the 'Add New Product' interface in the Ariemmas POS system. The left sidebar lists existing products. The main form is for adding a new product named 'Beef Sausages'. The barcode field has been populated with '247341707829', and a barcode image is generated and displayed. Below the barcode, there are fields for category (Groceries), selling price (0.00), cost price (0.00), stock quantity (0), minimum stock alert (5), VAT rate (Standard 16%), and unit (Each). A 'Generate' button is next to the barcode field, and a 'PNG' button is below the barcode preview. The right sidebar shows a table of products with columns for category, stock, status, and actions.

**Add/Edit Product.** Tap **“Generate”** to create a barcode, see it previewed, then tap **“PNG”** to download a printable label.

- 1 In the product window, tap **“Generate”** next to the barcode field — a unique barcode is created.
- 2 The barcode preview appears below.
- 3 Tap **“PNG”** to download the barcode image, then print it and stick it on the product.

### Works offline

The barcode generator needs no internet — it works on the terminal at any time.


### 3.3 Setting up a butchery (weighed) item

Tick **"Sold by weight (butchery)"**. The unit switches to **kg** and the price becomes **price per kg**.

- 1 Add or edit the product (for example, *T-Bone Steak*).
- 2 Set the **Selling Price** to the **price per kilogram**.
- 3 Tick **"Sold by weight (butchery)"** near the bottom.
- 4 Save. Now, whenever a cashier adds this item, the **Weigh item** window appears automatically (see section 2.5).


### 3.4 Reports — who sold what

The **Reports** tab is where the owner sees the day's trading. Pick a date at the top right; everything updates for that day.



**Daily overview.** Total revenue, number of sales, items sold, average sale, the cash/mobile split, and the VAT summary.

Scroll down for the part that matters most for staff accountability — **By cashier** and the full **Transactions** list.



**By cashier.** Each login, the **real person on shift**, how many sales they made and their total — for example *Joyce Mwanza: 3 sales, K 245.00*.

The screenshot shows the Ariemmas POS interface. At the top, there's a navigation bar with 'Sale', 'Products', 'Reports', and 'Settings'. The 'Reports' tab is active. Below the navigation bar, there's a 'Sales Reports' section with a date filter set to '06/06/2026' and an 'Export Excel' button. The main content area displays two tables. The first table, 'By cashier', shows sales and revenue for three cashiers. The second table, 'Transactions', shows a list of transactions with columns for time, receipt number, cashier, person, terminal, payment method, and total.

| LOGIN     | PERSON ON SHIFT | SALES | REVENUE  |
|-----------|-----------------|-------|----------|
| Cashier 2 | Joyce Mwanza    | 3     | K 245.00 |
| Cashier 3 | Grace Phiri     | 2     | K 225.00 |
| Cashier 1 | Mary Banda      | 2     | K 205.50 |

| TIME     | RECEIPT       | CASHIER   | PERSON       | TERMINAL | PAY    | TOTAL    |
|----------|---------------|-----------|--------------|----------|--------|----------|
| 14:02:13 | 20260606-0007 | Cashier 1 | Mary Banda   | -        | Cash   | K 170.50 |
| 14:00:36 | 20260606-0006 | Cashier 3 | Grace Phiri  | -        | Cash   | K 130.00 |
| 14:00:36 | 20260606-0005 | Cashier 3 | Grace Phiri  | -        | Cash   | K 95.00  |
| 14:00:34 | 20260606-0004 | Cashier 2 | Joyce Mwanza | -        | Mobile | K 135.00 |
| 14:00:33 | 20260606-0003 | Cashier 2 | Joyce Mwanza | -        | Cash   | K 55.00  |
| 14:00:11 | 20260606-0002 | Cashier 2 | Joyce Mwanza | -        | Cash   | K 55.00  |
| 10:58:15 | 20260606-0001 | Cashier 1 | Mary Banda   | -        | Cash   | K 35.00  |

**Every transaction.** Time, receipt number, cashier login, the person on shift, terminal, payment method and total — newest first.

This is exactly how the owner answers “who served this customer and on which till?” — the cashier login and the typed name are recorded on every single sale, even across the different terminals.

### 3.5 Exporting to Excel

- 1 Pick the date you want.
- 2 Tap “**Export Excel**” (top right of Reports).
- 3 A spreadsheet is saved with two sheets: a **Sales Summary** (every receipt with cashier, person on shift, terminal, payment and totals) and a **Line Items** sheet (every product sold).

#### Good for record-keeping

Export at the end of each day or week and keep the files as the shop’s sales record and for ZRA bookkeeping.

## 3.6 Settings & hardware

The **Settings** tab holds the shop details on the receipt, cash-drawer alerts, and the hardware controls.

The screenshot shows the 'Settings' tab in the Ariemmas POS application. The top navigation bar includes 'Sale', 'Products', 'Reports', and 'Settings' (which is active). The top right shows the time '14:03:41' and date 'Sat 6 Jun', along with a 'Shift Open' button and an 'Administrator' profile icon. The main content area is titled 'Settings' with the subtitle 'Manage your POS configuration' and a 'Save Changes' button. There are two main sections: 'Shop Information' and 'Receipt Settings'. 'Shop Information' includes fields for 'SHOP NAME' (Ariemmas), 'ADDRESS' (Independence Ave Mongu), 'PHONE' (097 4542233), and 'TPIN' (ZRA Tax Payer ID). 'Receipt Settings' includes fields for 'RECEIPT HEADER MESSAGE' (Welcome to Ariemmas!), 'RECEIPT FOOTER MESSAGE' (Thank you for shopping at Ariemmas!), and 'VAT RATE (%)' (0.16).

**Settings.** Shop name, address and details printed on receipts, plus cash-alert options.

This is a duplicate of the screenshot above, showing the 'Settings' tab in the Ariemmas POS application. It displays the 'Shop Information' and 'Receipt Settings' sections with their respective fields and values.

**Hardware section.** Choose the receipt printer, then use **Test Print** and **Open Drawer** to confirm the hardware works.

- 1 Under **Hardware** → **Active Printer**, pick your receipt printer from the list.
- 2 Tap **"Test Print"** — a test slip should print.
- 3 Tap **"Open Drawer"** — the cash drawer should pop open.

## Hardware: printer & cash drawer

This is a one-time setup, usually done by the administrator when a terminal is installed.

### 4.1 How the pieces connect

The important thing to understand: **the cash drawer is opened by the printer, not the terminal**. The drawer's cable plugs into the *printer*, and the printer sends the pulse that pops it open when a receipt prints.

| CABLE              | PLUGS INTO                                                                                                    |
|--------------------|---------------------------------------------------------------------------------------------------------------|
| Printer power      | Wall socket → round power port on the printer                                                                 |
| Printer → PC (USB) | The square <b>USB-B</b> port on the printer → the terminal                                                    |
| Cash drawer cable  | The <b>white "DK / Cash Drawer" port</b> on the printer — <i>not</i> the LAN port, <i>not</i> the touchscreen |

#### The drawer cable looks like a network cable but isn't

It's a telephone-style (RJ11/RJ12) plug — slightly narrower than a network (LAN) cable. It must go into the printer's white drawer port. Plugged into the terminal or the LAN port, the drawer will never open.

### 4.2 First-time setup checklist

- 1 Plug the **drawer cable into the printer's white DK port**.
- 2 Connect the printer to the terminal by **USB** and switch it on.
- 3 On Windows, make sure the printer appears under **Printers & scanners** and prints a Windows test page. (Install the printer's driver if it doesn't show up.)
- 4 In the app, go to **Settings → Hardware**, choose the printer, and run **Test Print** and **Open Drawer**.

#### Once it's set up

Every cash sale prints the receipt and opens the drawer automatically — cashiers don't need to do anything extra.

## Troubleshooting & FAQ

| PROBLEM                                                        | WHAT TO DO                                                                                                                              |
|----------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------|
| "Invalid username or PIN"                                      | Check you tapped the right cashier row. PINs are 4 digits. If it still fails, ask the admin to confirm your login is active.            |
| It won't let me sign in — says I'm already signed in elsewhere | Your login is open on another terminal. Close the shift and sign out there first, or wait a few minutes for it to release.              |
| The cash drawer didn't open                                    | Check the drawer cable is in the <b>printer's white DK port</b> . The drawer only opens on cash sales and only when the receipt prints. |
| The receipt didn't print                                       | Check the printer is on, has paper, and is selected in <b>Settings → Hardware</b> . Run <b>Test Print</b> .                             |
| A meat sale total looks far too high                           | You likely typed grams instead of kilograms. Remove the line (X) and re-add it — type kilograms, e.g. <b>0.450</b> .                    |
| The "Pay" button is greyed out                                 | Either the cart is empty or no shift is open. Add an item and make sure the badge says <b>"Shift Open"</b> .                            |
| I can't see Products / Reports / Settings                      | Those are admin-only. Sign in with the admin login.                                                                                     |
| The internet is down                                           | Keep selling — the till works offline and syncs automatically when the connection returns.                                              |

### Frequently asked

**Do I need internet to sell?** No. The till works fully offline and catches up later.

**Can two cashiers use the same login?** No — one login works on one terminal at a time, on purpose, so sales are tracked to the right person.

**What if I make a mistake on a line?** Tap the **X** on that line to remove it, or **F1** to clear the whole sale and start again.

## Quick reference card

Print this page and pin it next to each till.

### Keyboard shortcuts

|            |                      |
|------------|----------------------|
| <b>F1</b>  | Clear / new sale     |
| <b>F2</b>  | Jump to search       |
| <b>F8</b>  | Remove selected line |
| <b>F12</b> | Take payment         |

### Everyday checklist

- ☐ Sign in as yourself
- ☐ Open shift — type your name
- ☐ Enter opening cash
- ☐ Sell all day
- ☐ Close shift & count drawer
- ☐ Sign out when handing over

## Selling by weight, in three steps

- 1 Weigh on the scale (e.g. **0.450 kg**).
- 2 Scan/search the item → the **Weigh item** window opens.
- 3 Type the kilograms (0.450), check the total, **Add to cart**.

## Golden rules

- Always sign in as **yourself** and type your **real name** at shift open.
- Weighed items are in **kilograms** — never grams.
- **Close your shift** before you hand the till to the next person.

### Need help?

Show this guide to the administrator, or contact the system supplier. Keep the admin credentials file (saved in the Downloads folder) somewhere safe and private.