#### **CHAPTER FOUR**

# 3. Chemical Equilibrium And Phase Equilibrium

# 4.1. Chemical Equilibrium

#### 4.1.1. Introduction

It is well established fact that reversible reactions do not go to completion even if favorable conditions are maintained. The reactions proceed to some extent and supposed to stop often leaving considerable amounts of unreacted reactants. When such a stage is reached in the course of a reaction that no further reaction occur, it is said to have attained a state of equilibrium at that temperature and observable properties of the system do not change with time.


Equilibrium is a state in which there are no observable changes as time goes.

Chemical equilibrium is defined as a chemical system where the concentrations of reactants and products remain constant over time. On the molecular level, the system is dynamic: The rate of change is the same in either the forward or reverse directions. At this equilibrium condition the reaction proceeds in both directions at equal rates so that the rate of formation of products is exactly equal to the rate of disappearance of the reactants. There are two types of equilibrium: Physical and Chemical equilibrium.

**Physical equilibrium** occurs between two phases of the same substance. Changes that occur are physical which mean has the same chemical composition.

*Chemical equilibrium* occurs in between the chemical species of the reactionchemists are more interested in this because the progress of the reaction can be easily monitored.

**The Equilibrium Constant (K)** - A number equal to the ratio of the equilibrium concentrations of the products to the equilibrium concentrations of the reactants each raised to the power of its stoichiometric coefficient. For a general reaction:



#### Characteristics of chemical equilibrium

- 1. Equilibrium can be attained from either side
- 2. Equilibrium is dynamic in nature i.e. at equilibrium reaction does not stop.
- 3. At equilibrium, there is no change in the concentration of various species
- 4. The equilibrium state remains unaffected by the presence of catalyst. Catalyst helps to attain the equilibrium state rapidly.
- 5. The observable physical properties of the process become constant.

#### Law of Mass Action

*Guldberg and Waage* state that the rate of a chemical reaction is directly proportional to the product of the active masses of the reacting substances. For general reaction

$$aA + bB \rightleftharpoons cC + dD$$

Rate of forward reaction  $\propto [A]^a [B]^b = k_f [A]^a [B]^b$ Rate of backward reaction  $\propto [C]^c [D]^d = k_b [C]^c [D]^d$ 

At equilibrium Rate of forward reaction is equal with Rate of backward reaction

$$k_f[A]^a[B]^b = k_b[C]^c[D]^d$$

For a reversible reaction at equilibrium and constant temperature, the ratio of the rate of forward to backward reaction is known as **equilibrium constant** 

*Equilibrium constants* can be expressed using  $K_c$  or  $K_p$ .  $K_c$  uses the concentration of reactants and products to calculate the equilibrium constant.  $K_p$  uses the pressure of the gaseous reactants and products to calculate the equilibrium constant.

### The relationships between chemical reaction and expression of its equilibrium constant

- ▶ If a reaction is re-written where the reactants become products and products-reactants, the new Equilibrium Expression is the reciprocal of the old. i.e.  $K_{new} = 1/K_{original}$
- ▶ When the entire equation for a reaction is multiplied by n,  $K_{new} = (K_{original})^n$
- ► For a reaction which is the **sum** of two or more reactions, the overall *K* is the **product** of the expressions for *K* for the individual steps:

#### 4.1.2. Standard Gibbs free energy of reaction and equilibrium

Let us consider the reaction

$$aA + bB \rightleftharpoons cC + dD$$

If all moles of the reactants as expressed by the balanced chemical equation have combined to form the products as expressed by the equation, then we can say that the progress of the reaction is 100%. But, when all the reactants are not consumed the progress of the reaction is less than 100%. Therefore, it is convenient to define a new variable to show the progress of the reaction called *extent of reaction* ( $\xi$ ).

The value of the Gibbs free energy  $\Delta G$  decreases until the extent of reaction  $\xi$  reaches its equilibrium  $\xi(\text{eq})$ . At  $\xi(\text{eq})$ , the reaction has no longer energy i.e.  $\Delta G = 0$ , at  $\xi = 0$  there is no reaction and  $\xi = 1$  mol represents complete reaction.

Let the reaction advances with an infinitesimal amount  $d\xi$ , then the reactants and products are changed as follows

Change in amount of A =  $dn_A = -ad\xi$ , Change in amount of B =  $dn_B = -bd\xi$ , Change in amount of C =  $dn_C = cd\xi$  and Change in amount of D =  $dn_d = dd\xi$ 

➤ The negative indicates the decrease in the reactants because they are consumed in the reaction. Hence, we can express the differential extent of reaction as

As the reaction takes place the free energy also changes. The change in Gibb's free energy can be expressed in terms of the chemical potential of the species as

$$dG = -SdT + VdP + \sum \mu_i dn_i$$
 
$$dG = -SdT + VdP + \mu_A dn_A + \mu_B dn_B + \mu_C dn_C + \mu_D dn_D$$
 
$$dG = -SdT + VdP - \mu_A ad\xi - \mu_B bd\xi + \mu_C cd\xi + \mu_D dd\xi$$

Since the reaction is carried out at constant temperature and pressure (volume is also constant) can be written as

$$dG = \sum \mu_i dn_i$$

Substituting the values of  $dn_i$  s, we have

$$(dG)_{P,T} = \left[d\mu_D + c\mu_C - (b\mu_B + a\mu_A)\right]d\xi$$

$$\Rightarrow \left[\frac{\partial G}{\partial \xi}\right]_{P,T} = \left[d\mu_D + c\mu_C - (b\mu_B + a\mu_A)\right] = \Delta G$$

Then,  $\left[d\mu_D + c\mu_C - (b\mu_B + a\mu_A)\right] = \Delta G$  from the definition of chemical potential

*Chemical potential* is the change of Gibbs energy with the change of amount of one component of the system by keeping the T, P and the other amounts of components constant.

The sign of  $\Delta G$  and  $\left[\frac{\partial G}{\partial \xi}\right]_{P,T}$  are a measure of the nature of the chemical reaction. The decrease in the

free energy of the reaction is defined as the *chemical affinity*  $(A_f)$ :

$$\Rightarrow A_f = -\left[\frac{\partial G}{\partial \xi}\right]_{P,T} = -\Delta G$$

The affinity  $A_f$  and the reaction free energy  $\Delta G$  are numerically exactly equal and opposite in sign but represent different ways of viewing at the same situation. When  $\Delta G$  is used the system is thought of as large enough to allow a moles of A and b moles of B to react: When  $A_f$  is used it implies that only  $ad\xi$  moles of A and  $bd\xi$  moles of B react.

- When the derivative  $\left[\frac{\partial G}{\partial \xi}\right]_{P,T} = -ve \Rightarrow A_f = +ve$ , the free energy of the system decreases as the reaction proceeds in the forward direction i.e  $d\xi$  is positive but  $\Delta G$  is negative and the reaction is spontaneous.
- ▶ When the derivative  $\left[\frac{\partial G}{\partial \xi}\right]_{P,T} = +ve \Rightarrow A_f = -ve$ , the reaction is spontaneous in the reverse direction
- When the derivative  $\left[\frac{\partial G}{\partial \xi}\right]_{P,T} = 0 \Rightarrow A_f = 0$ , the free energy has the minimum value and reaction is at equilibrium. This equilibrium condition is applicable for all reactions.

# Relationships between K and $\Delta G^{o}$

The standard Gibbs free energy change for reaction is  $\Delta G^0$  and represents the energy available for reaction of one mole of reactants reacts until it reaches its equilibrium. Figure 4.1 relates  $\Delta G$  and  $\xi$ , and clearly shows how the amount of energy available for reaction  $\Delta G$  decreases during reaction (i.e. in going from left to right as  $\xi$  increases). Stated another way, the gradient of the curve is always negative before the position of equilibrium, so any increases in  $\xi$  cause the value of  $\Delta G$  to become more negative.




Figure 4.1. The value of Gibbs free energy as a function of an extent of reaction

The amount of energy liberated per incremental increase in reaction extent is quite larger at the beginning of reaction but decreases until the equilibrium; a tiny increase in the extent of reaction would not change the total  $\Delta G$ . The minimum value on the G versus  $\xi$  graph is the reaction's position of equilibrium  $\xi$ (eq) at which maximum amount of energy has already been expended at equilibrium, so  $\Delta G$  is zero.

The relationship between the energy available for reaction  $\Delta G$  and the extent of reaction (expressed in terms of the reaction quotient Q) is given by

$$\Delta G = \Delta G^o + RT lnQ$$

Where  $\Delta G$  is the energy available for reaction during chemical changes, Q is reaction quotient and  $\Delta G^o$  is the standard change in Gibbs function.

Before we look at this Equation in any quantitative sense, we note that if  $RT \ln Q$  is smaller than  $\Delta G_0$ , then  $\Delta G$  is positive. The value of  $\Delta G$  only reaches zero when  $\Delta G_0$  is exactly the same as  $RT \ln Q$ . In other words, there is no energy available for reaction when  $\Delta G = 0$ : we say the system has 'reached equilibrium'. In fact,  $\Delta G = 0$  is one of the best definitions of equilibrium.

Justification

Consider again the simple reaction of Equation

$$aA + bB \rightleftharpoons cC + dD$$

We ascertain the Gibbs energy change for this reaction. We start by saying

$$\Delta G = \sum vG_{products} - \sum vG_{reactants}$$

Where v is the respective stoichiometric number; so

$$G = cG_C + dG_D - aG_A - bG_B 2.7$$

And  $G = G^0 + RT \ln \frac{P}{P^0}$ , so each G term in Equation (2.7) may be converted to a *standard* Gibbs function.

$$\Delta G = cG_C^{\ 0} + RT ln \left(\frac{P_C}{P^0}\right)^C + dG_D^{\ 0} + RT ln \left(\frac{P_D}{P^0}\right)^d - aG_A^{\ 0} + RT ln \left(\frac{P_A}{P^0}\right)^a - bG_B^{\ 0} + RT ln \left(\frac{P_B}{P^0}\right)^b$$

We can combine the Go terms as  $\Delta G^{0}$  by saying

$$\Delta G^{0} = cG_{C}^{0} + dG_{D}^{0} - aG_{A}^{0} - bG_{B}^{0}$$

So the  $\Delta G$  equation simplifies to become:

$$\Delta G = \Delta G^{0} + RT ln \left(\frac{P_{C}}{P^{0}}\right)^{C} + RT ln \left(\frac{P_{D}}{P^{0}}\right)^{d} - RT ln \left(\frac{P_{A}}{P^{0}}\right)^{a} - RT ln \left(\frac{P_{B}}{P^{0}}\right)^{b}$$

Then, using the laws of logarithms, we can simplify further:

$$\Delta G = \Delta G^{0} + RT \left[ ln \frac{\left(\frac{P_{C}}{P^{0}}\right)^{c} \left(\frac{P_{D}}{P^{0}}\right)^{d}}{\left(\frac{P_{A}}{P^{0}}\right)^{a} \left(\frac{P_{B}}{P^{0}}\right)^{b}} \right]$$

The bracketed term is the reaction quotient, expressed in terms of pressure; a similar proof may be used to derive an expression relating to  $\Delta G_0$  and  $K_c$ . In the case of equilibrium, Q = Kp and  $\Delta G = 0$ 

$$0 = \Delta G^{0} + RT \left[ ln \frac{\left(\frac{P_{C}}{P^{0}}\right)^{C} \left(\frac{P_{D}}{P^{0}}\right)^{d}}{\left(\frac{P_{A}}{P^{0}}\right)^{a} \left(\frac{P_{B}}{P^{0}}\right)^{b}} \right]$$
 Then, 
$$\Delta G^{0} = -RT \left[ ln \frac{\left(\frac{P_{C}}{P^{0}}\right)^{C} \left(\frac{P_{D}}{P^{0}}\right)^{d}}{\left(\frac{P_{A}}{P^{0}}\right)^{a} \left(\frac{P_{B}}{P^{0}}\right)^{b}} \right]$$

Since, Q = Kp = 
$$\frac{\left(\frac{P_C}{P^0}\right)^C \left(\frac{P_D}{P^0}\right)^d}{\left(\frac{P_A}{P^0}\right)^a \left(\frac{P_B}{P^0}\right)^b}$$

$$\Delta G^0 = -RTlnQ = -RTlnKp$$

The derivation of this equation is a thermodynamic proof the existence of equilibrium constant Since  $\Delta G^o$  is a function of temperature alone, it cannot depend on the partial pressure

As known *Kp* at certain temperature is constant.

 $\Delta G^0 = -RT ln Kp$  not only proves the existence of an equilibrium constant, Kp, but also give us an explicit formula for calculating Kp from  $\Delta G^0$  data.

This allows us to develop a set of criteria to determine in which direction a reaction will proceed under non-standard conditions. This is because Q/K will determine the sign of  $\Delta G$ :

- 1. If  $Q/K \le I$ , then  $\Delta G$  is negative, and the reaction is spontaneous as written
- 2. If Q/K = 1, then  $\Delta G = 0$  and the system is at equilibrium,
- 3. If Q/K > 1, then  $\Delta G$  is positive, and the reaction is spontaneous in the opposite direction as written

**Example.** Consider the dissolution of CaCO3 (calcite) in aqueous solution:

$$CaCO_3 \rightarrow Ca^{2+} + CO_3^{2-}$$

Does the reaction proceed spontaneously as written?

Calculate the free energy of reaction at standard state and equilibrium constant (products and reactants at activity = 1, P = 1 atm,  $T = 25^{\circ}C$ ): free energy of  $CaCO_3$ ,  $Ca^{2+}$  and  $CO_3^{2-}$  are -270,-132, and -126 kcalmol<sup>-1</sup> respectively.

$$\Delta G^{0} = \sum vG_{products} - \sum vG_{reactants}$$

$$\Delta G^{\circ} = (1(-132) + 1(-126) - (1(-270)) \text{ kcal/mole}$$

$$= (-258 + 270) \text{ kcal/mole}$$

$$= +12 \text{ kcal/mole}$$

Therefore, at standard state, the reaction spontaneously proceeds in the opposite direction to what is written (i.e., calcite precipitates).

From Sample Calculation of above, we know:  $\Delta G^{\circ} = +12 \text{ kcal/mole}$ 

Thus:

$$12\frac{kcal}{mol} = -\left(\frac{1.9987cal}{mol}\right)\left(\frac{1kcal}{1000ca}\right)(298K)lnK \qquad \text{All units cancel out}$$

$$lnK = -20.27$$

$$K = 1.58 \times 10^{-9} \quad equilibrium \quad constant$$

**Example.** The equilibrium constant for the reaction A  $\rightarrow$  M is 0.1 at 300K. Calculate  $\Delta G$  and  $\Delta G^0$  for the production of 1 mol of M at a pressure of 1 atm from A at a pressure of 20 atm and predict the nature of the reaction under this condition.

Solution

$$\Delta G^{0} = -RT \ln K_{P}$$

$$\Delta G^{0} = -2.303 \times 8.314 J K^{-1} mol^{-1} \times 300 K \log 0.1$$

$$\Delta G^{0} = 5744 J mol^{-1}$$

$$Q_{P} = \frac{1.0 \ atm}{20.0 \ atm} = \frac{1}{20}$$

$$\Delta G = \Delta G^{0} + RT \ \ln Q_{P} = -RT \ln K_{P} + RT \ \ln Q_{P}$$

$$\Delta G = 2.303 \times 8.314 J K^{-1} mol^{-1} \times 300 K [-\log 0.1 + \log \frac{1}{20}]$$

$$\Delta G = -1729 J mol^{-1}$$

 $\bullet$  Since the free energy change  $\Delta G$  is negative for the given reaction it should precede forward spontaneously.

# 1.1. Relationship between K<sub>P</sub> and K<sub>C</sub>

Kp and Kc for a given reaction are not the same numerically. Since for ideal gases the pressure is given by

$$P = \left(\frac{n}{v}\right)RT$$
 Where V is the volume occupied by **n** moles of a gas at a temperature T

But from the expression in the above equation  $\frac{n}{V}$  is equal to the molar concentration C therefore

$$P = \left(\frac{n}{V}\right)RT \Rightarrow P = CRT$$

Substitute the value of P in the Kp equation give

$$K_{P} = \frac{C_{C}^{c} (RT)^{c} . C_{D}^{d} (RT)^{d}}{C_{A}^{a} (RT)^{a} . C_{B}^{b} (RT)^{b}}$$

$$K_{P} = \frac{C_{C}^{c} . C_{D}^{d}}{C_{A}^{a} C_{B}^{b}} . \frac{(RT)^{c} . (RT)^{d}}{(RT)^{a} . (RT)^{b}} = \frac{C_{C}^{c} C_{D}^{d}}{C_{A}^{a} C_{B}^{b}} . \frac{(RT)^{c+d}}{(RT)^{a+b}}$$

$$K_P = K_C \cdot (RT)^{(c+d-a+b)}$$
 But  $(c+d) - (a+b) = \Delta n$ 

$$K_P = K_C (RT)^{\Delta n}$$

If  $\Delta n > O \Rightarrow$  number moles reactants < number moles of prod  $\Rightarrow K_P > K_C$ 

If  $\Delta n > O \Rightarrow$  number moles reactants < number moles of prod  $\Rightarrow$   $K_P < K_C$ 

If  $\Delta n > O =>$  number moles reactants < number moles of prod =>  $K_P = K_C$ 

**Problem**. At 2 atmosphere and 673 k the equilibrium constant K<sub>P</sub> for the given reaction.

$$N_2(g) + H_2(g) \leftrightarrow 2NH_3(g)$$
 is  $1.623x10^{-4}$ . Calculate  $K_C$ , (answer:  $Kc = 0.495$ )

# Properties of equilibrium constants (Kc and K<sub>P</sub>)

- i. The expressions for  $K_P$  and  $K_C$  are valid only at equilibrium
- ii. The equilibrium varies only with T of the reaction and is constant at a constant temperature

- iii. The values of  $K_P$  and  $K_C$  can determine the extent to which a particular reaction which take place under the given conditions. Large value of  $K_P$  and  $K_C$  imply that the formation of more products & the reaction is more on the right side. Small value of  $K_P$  and  $K_C$  shows little product and the reaction is more on the left side.
- iv. It is possible to predict quantitatively the effect of changing concentrations of reactants and products on the extent of reaction.

# 1.2. Heterogeneous Equilibria

*Homogeneous equilibrium* is an equilibrium at which all reactants and products of the reaction system are in the same phase. On the other hand, *Heterogeneous* equilibrium is an condition in which more than one phase exists in a reaction mixture. (One or more of the components is a liquid or solid.)

A pure solid always has the same concentration at a given temperature, and its volume does not change much. Since, we're only concerned with quantities that are changing, we eliminate the terms for pure liquids and solids from the reaction quotient:

**Problem**: Write equilibrium laws for the following heterogeneous reactions.

4.1.3. 
$$2CO(g) \rightleftharpoons CO_2(g) + C(g)$$

4.1.4. 
$$2Hg(1) + Cl_2(g) \rightleftharpoons Hg_2Cl_2(s)$$

4.1.5. 
$$NH_3(g) + HCl(g) \rightleftharpoons NH_4Cl(s)$$

#### 1.3. Factors which influence the equilibrium: Lechateliers principle

Lechatelier's principle states "If a dynamic equilibrium is disturbed by changing the conditions, the position of equilibrium moves to counteract the change". When a chemical system in a state of equilibrium is disturbed, it retains the equilibrium by undergoing a net reaction that reduces the effect of the disturbance Such common disturbances are the change in the factors that affect the equilibrium are concentration, pressure and temperature

- If the concentration of a solute reactant is increased, the equilibrium position shifts to use up the added reactants by producing more products.
- If the pressure on an equilibrium system is increased, then the equilibrium position shifts to reduce the pressure.
- If the volume of a gaseous equilibrium system is reduced (equivalent to an increase in pressure) then the equilibrium position shifts to increase the volume (equivalent to a decrease in pressure).

- If the temperature of an endothermic equilibrium system is increased, the equilibrium position shifts to use up the heat by producing more products.
- If the temperature of an exothermic equilibrium system is increased, the equilibrium position shifts to use up the heat by producing more reactants.

# **Quantitative Effects in Temperature and Pressure**

The equilibrium constant of a chemical reaction is constant at a given temperature, but its magnitude varies considerably with changes in temperature. The Lech atelier's principle gives only a qualitative idea of the shift of equilibrium when temperature changes. However, Quantitative expression for the variation of equilibrium constant with temperature can be derived thermodynamically as follows:

From the relation of equilibrium constant and Gibbs function, we have

$$\Delta G^{\circ} = -RT lnKp$$
 then  $lnKp = -\frac{\Delta G^{\circ}}{RT}$ 

The differentiation of this equation with respect to T at constant pressure gives,

$$\frac{dlnKp}{dT} = -\frac{1}{R} \left[ \frac{d(\Delta G^{\circ})/T}{dT} \right]$$

Where  $\Delta G^{\circ} = \Delta H^{o} - T\Delta S$  then  $\left[\frac{d(\Delta G^{\circ})/T}{dT}\right]_{P} = -\frac{\Delta H^{o}}{T^{2}}$  and the above differention becomes

$$\frac{dlnKp}{dT} = -\frac{1}{R} \left[ -\frac{\Delta H^o}{T^2} \right]$$

Then 
$$\frac{dlnKp}{dT} = \frac{\Delta H^o}{RT^2}$$

This result, which is fundamentally important in chemistry, it represents the variation of equilibrium constant with temperature. In order to integrate this equation; it must be known as function of temperature. Assuming to be constant over a small range of temperature, integration of the above equation yields

$$log \frac{Kp_2}{Kp_1} = \frac{\Delta H^o}{2.303R} \left[ \frac{T_2 - T_1}{T_1 T_2} \right]$$
 This equation is known as *Van't Hoff's equation*.

# 4.2. Phase Equilibrium

### 4.2.1. Introduction

The main idea of this chapter is to establish the thermodynamic relations obeyed by two or more phases that are at equilibrium with each other. A phase is a portion of a system (or an entire system) inside which intensive properties do not change abruptly as a function of position. The principal kinds of phases are solids, liquids, and gases, also plasmas (ionized gases), liquid crystals, and glasses are sometimes considered to be separate types of phases. Solid and liquid phases are called condensed phases and a gas phase is often called a vapor phase. Several elements such as carbon exhibit solidphase allotropy because there is more than one kind of solid phase of the element. For example, diamond and graphite are both solid carbon but have different crystal structures and physical properties. This phenomenon is called **polymorphism** 

**Phase equilibrium** describes the condition at which phases (such as solid, liquid and/or gas) co-exist at some temperatures and pressure, but interchange at others.

### 4.2.2. Definitions

# 1. *Phase* (P)

A phase is defined as part of the system which is homogenous throughout and separated from other homogenous part of the system by a means of definite boundary.

#### **Example 4.2.1.**

- i. A gaseous mixture constitute one phases
- ii. In case of liquids depending up on their mutual solubility one or more phases can arise.
- a) Water  $CCl_4 \rightarrow two phases$
- d) Water ethanol  $\rightarrow$  one phase
- b) Liquid its vapour  $\rightarrow$  two phases e) Aqueous solutions, NaCl in H<sub>2</sub>O  $\rightarrow$  one phase
- c)  $CaCO_3(s) \rightarrow CaO(s) + CO_2(g) \rightarrow three phases$  f)  $S_{rho} \rightarrow S_{mono} \rightarrow two phases$

### 2. Number of components (C)

The minimum number of independent chemical species necessary to describe the composition of each and every phase of the system in equilibrium is called the number of components.

#### **Example 4.2.2.**

- a. Equilibria between phases of water. C is one because each phase is represented by H<sub>2</sub>O
- b. Aqueous sugar solution (sugar  $+ H_2O(1)$ ) number of components is 2.

For chemically reactive systems the number of components can be calculated as C = S - RWhere S is number of chemical species and R is number of independent chemical reactions If ions are also present in the system then for the condition of neutrality (No, positive ions = n negative ions) one is added to the value of R and the equation modified as

$$C = S - (R+1)$$

# **Example 4.2.3**

- a. For Aqueous NaCl solution, C = S (1 + 1) = 4-2 = 2
- b. For  $PCl_5(s) \rightarrow PCl_3(s) + Cl_2(g)$ , C = S (1 + 0) = 3 1 = 2
- c.  $CaCO_3(s) \rightarrow CaO(s) + CO_2(g)$ ,  $C = S (1 + 0) = 3-1 = \underline{\underline{2}}$
- d. KCl NaCl-H<sub>2</sub>O system, C= 6- (2 + 1) = 3
- e.  $KCl NaBr H_2O$  system,  $C = 9 (4 + 1) = \underline{4}$  (Condition of neutrality = 1) (NaBr, NaCl, KBr, KCl, K<sup>+</sup>, Cl<sup>-</sup>, Na<sup>+</sup>, Br<sup>-</sup>, H<sub>2</sub>O),  $\Rightarrow$  S=9  $KCl \rightarrow K^+ + Cl$ , NaBr  $\rightarrow Na^+ + Br^-$ , K<sup>+</sup> + Br<sup>-</sup>  $\rightarrow$  KBr, Na<sup>+</sup> + Cl<sup>-</sup>  $\rightarrow$  NaC,  $\Rightarrow$  R = 4

# 3. Number of degrees of freedom (F)

**Number of degrees of freedom** is defined as the minimum number of independent intensive variables such as pressure, temperature and concentration that must be specified in order to know all the remaining intensive variables and describe the state of a system completely. If we consider a one phase, one component system, it will have a number of intensive properties like density, refractive index, surface tension, viscosity etc. If the temperature and pressure are given, then the substance will have a fixed value of other intensive properties at this given temperature and pressure. Degree of freedom is sometimes known as variance of the system.

#### **Example 4.2.4.**

- a) For a gaseous system, to describe completely only two of the three variables (T and P) are essential because the third can be obtained from the two using the equation of state.
  - $\Rightarrow$  Number degrees of freedom = 2 for pure gaseous systems.
- b) For one component system F + P = 3
- c) If there is a single phase F = 3 1 = 2 for pure gas specify P & T
- d) If there are two phase F = 3 2 = 1 specifying T or P
- e) If there are three phases F = 3 3 = O no need of fixing because any variable will not be altered without losing one of the phases. For example the three phases of water coexist at 0.0099  $^{0}$ C and

4.579 mmHg. This point is called the triple point. If change one of the variable we will lose the triple point. this if

F = 0, invariant system, F = 1, univeriant system and F = 2, bi-variant system

#### 4.2.3. Phase rule

The *phase rule* is an important and versatile tool in the study of heterogeneous equilibria. It relates the conditions which must be specified to describe the state of a system at equilibrium. If the p phases in a multiphase simple system and c components are separated from each other so that they cannot equilibrate with c+1 independent intensive variables for each phase, a total of p(c+1) variables. Now place the phases in contact with each other, open them to each other, and allow them to equilibrate. There are three aspects of equilibrium. Thermal equilibrium implies that all phases have the same temperature; mechanical equilibrium implies that all phases have the same pressure, and phase equilibrium implies that the chemical potential of every substance has the same value in every phase.

The phase rule states that "for systems in complete internal equilibrium in which the phases can exchange material, heat and P-V work".

# 4.2.4. **Derivation of the phase rule**

Consider a system of C components containing P phases.

- The composition of each phase can be specified if the amount of each component is known. All we need here is to describe the mole fraction of each component.
- If C is the number of components required to describe the composition of a phase, then the total number of composition variables for P phases are PC.
- Besides these there are two variables temperature and pressure which have to be considered. Then the total number of independent variables is PC + 2.
- For each phase there is one equation and for phases there are P equation similar to the above equation and the total numbers of independent variables are to be specified are

$$CP + 2 - P$$
 or  $P(C-1) + 2$ 

When a heterogeneous system is in equilibrium at a constant temperature and pressure, the chemical potential of a particular component must be the same in all the phases in which it appears. For one component system having two phases  $\alpha$  and  $\beta$ , the equality of chemical potential implies  $\mu(\alpha) = \mu(\beta)$ . Similarly for one component system having three  $\alpha$ ,  $\beta$  &  $\delta$ 

$$\mu(\alpha) = \mu(\beta) = \mu(\delta) = \mu(\alpha)$$

• For each component in P phases, (P-1) relations are possible. Since there are C components, the total number of relations restricting the variations will be

$$C(P-1)$$

• Therefore, the degree of freedom or the number of independent variables F is given by

F = Total number of variables - Total number of relations restricting the variation among the variables

$$F = PC + 2 - P - C(P - 1)$$
$$F + P = C + 2$$

This equation is given by Willard Gibbs and it is called the *Gibbs phase rule*, the fundamental relation controlling the equilibria in heterogeneous systems.

• For condensed systems pressure is not a significant variable and the phase rule takes the form F + P = C + 1.

**Example 4.2.5.** Write down the number of components, number of phases and evaluate the degrees of freedom for the following equilibria.

i)  $N_2O_4(g) \rightarrow 2NO_2(g)$ 

$$C = S - (R) = 2-1 = 1$$
 and  $P = 1$ ,  $F = C + 2 - P = 1 + 2 - 1 = 2$ 

- ii) NH<sub>4</sub>Cl (g)  $\rightarrow$  NH<sub>3</sub> (g) + HCl (g), a/ when pNH<sub>3</sub>  $\neq$  pHCl b/ when pNH<sub>3</sub> = pHCl a/ C = S (R) = 3 1 = 2, P = 1 and F = C + 2 P = 2 + 2 1 = 3 b/ C = S (R + 1) = 3 2 = 1, P = 1 and F = C + 2 P = 1 + 2 1 = 2
- iii) Pure partly frozen acetic acid CH<sub>3</sub>COOH (l) → CH<sub>3</sub>COOH (s)

$$C = S - R = 1 - 0 = 1$$
,  $P = 2$  and  $F = C + 2 - P = 1 + 2 - 2 = 1$ 

iv) Solid carbon in equilibrium with gaseous CO, CO<sub>2</sub>, and O<sub>2</sub>, at 100<sup>o</sup>C.

$$C(s) + O_2(g) \rightarrow CO_2(g)$$
  $C = S - R = 4 - 3 = 2$   
 $C(s) + \frac{1}{2}O_2 \rightarrow CO(g)$   $P = 2$  and  $F = C + 2 - P = 2 + 2 - 2 = 2$ 

v) A dilute solution of sulphuric acid in water

$$H_2SO_4 \rightarrow H^+ + HSO_4^- \quad C = S - (2+1) = 2$$
  
 $HSO_4^- \rightarrow H^+ + SO_4^- \quad P = 1 \text{ and } F = C + 2 - P = 2 + 2 - 1 = 3$ 

Exercise 4.2.1. Write down the number of components, number of phases and evaluate the degrees of freedom for the following equilibria.

- a) An aqueous solution saturated with respect to both NaCl and KBr and in equilibrium with the vapour phase
- b) Reduction of Fe<sub>2</sub>O<sub>3</sub> in the presence of I) air and II) oxygen and c)  $N_2(g) + 3H_2(g) \rightarrow 2NH_3(g)$

#### 4.2.5. Phase diagrams

A *phase* of a substance is a form of matter that is uniform throughout in chemical composition and physical state. Thus, we speak of solid, liquid, and gas phases of a substance, and of its various solid phases, such as the white and black allotropes of phosphorus. A *phase transition* is the spontaneous conversion of one phase into another phase which occurs at a characteristic temperature for a given pressure. *A phase diagram* is a map that shows which phase is the most stable at different pressures and temperatures. The lines separating the regions in a phase diagram are called *phase boundaries*. At this curve the values of *p* and *T* at which two phases coexist in equilibrium and their chemical potentials are equal. A **triple point** is a point where three phase boundaries meet on a phase diagram.

# **Characteristic points**

As we have seen, as the temperature of a liquid is raised, its vapour pressure increases. First, consider what we would observe when we heat a liquid in an open vessel. At a certain temperature, the vapour pressure becomes equal to the external pressure. At this temperature, the vapour can drive back the surrounding atmosphere and expand indefinitely. Moreover, there is no constraint on expansion; bubbles of vapour can form throughout the body of the liquid, a condition known as boiling.




Figure 4.2. A typical phase diagram showing the regions of pressure and temperature at which each phase is the most stable.

The temperature at which the vapour pressure of a liquid is equal to the external pressure is called the boiling temperature. When the external pressure is 1 atm, the boiling temperature is called the normal boiling point, Tb.

Now consider what happens when we heat the liquid in a closed vessel. Because the vapour cannot escape, its density increases as the vapour pressure rises and in due course the density of the vapour becomes equal to that of the remaining liquid. At this stage the surface between the two phases disappears, as was depicted in Fig. 4.1. The temperature at which the surface disappears is the critical temperature, Tc. The vapour pressure at the critical temperature is called the critical pressure, pc, and the critical temperature and critical pressure together identify the critical point of the substance.

**Table 4.1.** Summary of terms used to describe phase changes

Phase transition	Name of transition	Everyday examples
Solid → gas	sublimation	Smoke forming from dry ice
Solid →liquid	Melting	Melting of snow or ice
Liquid → gas	Boiling or vaporization	Steam formed by a kettle
Liquid → solid	Freezing, solidification or fusion	Ice cubes formed in a fridge; hail
Gas → liquid	Condensation or liquefaction	Formation of dew or rain
Gas → solid	Deposition or condensation	Formation of frost

The temperature at which the liquid and solid phases of a substance coexist in equilibrium at a specified pressure is called the melting temperature of the substance. Because a substance melts at the same temperature as it freezes, 'melting temperature' is similar with freezing temperature. The solid–liquid boundary therefore shows how the melting temperature of a solid varies with pressure. The melting temperature when the pressure on the sample is 1 atm is called the normal melting point or normal freezing point, Tf

There is a set of conditions under which three different phases (typically solid, liquid, and vapour) all simultaneously coexist in equilibrium. It is represented by the triple point, where the three phase boundaries meet. The triple point of a pure substance is a characteristic, unchangeable physical property of the substance. For water the triple point lies at ice, liquid water, and water vapour coexist in equilibrium at no other combination of pressure and temperature. At the triple point, the rates of each forward and reverse process are equal (but the three individual rates are not necessarily the same).

# 4.2.6. Phase Diagrams for Simple Systems

# 1. One component system

The composition of a one-component system is fixed so that the state of the system may therefore be defined by specifying the value of any two of the pressure, volume and temperature. The state of the system may therefore be represented as a surface on a three dimensional pressure, volume and temperature plot. *Areas* on the surface represent regions where only one phase is stable. The *lines* drawn between the regions represent the values of these variables at which *two phases* coexist in equilibrium. *Triple Points* at the intersection between two lines represent the values at which *three phases* coexist in equilibrium.




Figure 4.3. Pressure-volume-temperature phase diagram for a typical single component system


In practice it is usually easier to represent the phase diagram as two-dimensional projections of the three-dimensional surface. Phase diagrams of one-component systems are therefore usually drawn as pressure-temperature, pressure-volume and, occasionally, volume-temperature plots.

#### Pressure-Temperature Phase Diagrams

If pressure and temperature are taken as the independent variables that define the state of the system, then the volume must be a dependent variable and its value may therefore be determined for any point on the diagram.

#### Pressure-Volume Phase Diagrams

Less commonly seen are pressure-volume phase diagrams in which the pressure and volume are taken as the independent variable and temperature as the dependent variable.



**Figure 4.4.** Projection of the pressure-volume-temperature surface to form a pressure- temperature (a) and pressure-volume (b) phase diagram

# The Critical Point and Supercritical Behaviour

A critical point marks the conditions at which two phases become identical. Single component systems exhibit a critical point at which liquid and vapour phases become indistinguishable. Consider the behaviour of a one-component system in which liquid and vapour are in equilibrium. As the temperature increases, the pressure also increases, as the system follows the liquid-vapour equilibrium line on the phase diagram. This causes an increase in the density of the vapour phase and a slight decrease in the density of the liquid phase. Eventually, at the critical point, the densities of the two phases become equal and the two phases cannot be distinguished.

#### **Invariant, Univariant and Bivariant Systems**

Invariant states are represented by points on phase diagrams. Systems with one degree of freedom, F = 1, are univariant and are represented by lines and those with two degrees of freedom, F = 2, are bivariant and correspond to areas on phase diagrams.

For a one-component system, the coexistence of three phases in equilibrium corresponds to an invariant state since variant

$$F = C - P + 2 = 1 - 3 + 2 = 0$$

This state is usually called *a triple point*. The three phases may only exist at a particular temperature and particular pressure. A single-component phase diagram may have several triple points. The most obvious triple point corresponds to the coexistence of solid, liquid and vapour phases. For water, this triple point occurs at a temperature of 273.16 K and a pressure of 608 Pa, at a temperature close to the normal freezing point, but at a much lower pressure. In contrast, for carbon dioxide, the triple point occurs at a much higher temperature and pressure than ambient conditions.

# 2. The phase diagram of the water system

Water exists in three forms as solid (ice), liquid (*l*) and vapour. The application of phase rule reveals that we can have the following types of equilibria. As the maximum number of degrees of freedom is two, water system can be represented by a two dimensional phase diagram using temperature and pressure as a variable, as shown in figure 3.4




Figure 4.5 Phase diagram of water

Point A - is triple point where solid, liuid and vapour phases are at equilibrium

Point C – is critical point where the vapour & liquid are indistinguishable above that point.

- ➤ Within the single phase (areas) the system is bivariant, so the pressure and temperature can be varied independently.
- > Separating the areas are lines connecting the point at which two phases coexist at equilibrium. The system is univariant (having one degree of freedom) i.e for each value of temperature there is only one value of the pressure within the lines at which both phases coexist.
- At the triple point the system is invariant (invariant) i.e if we change he values of the variables one of the phases will disappear.

# 3. The Clapeyron Equation

The slopes of the lines on a one-component pressure-temperature phase diagram may be derived from the Clapeyron equation. For any two phases we can write

$$dG\alpha = V\alpha dP - S\alpha dT$$
 and  $dG\beta = V\beta dP - S\beta dT$ 

Where  $V\alpha$  is the molar volume of phase  $\alpha$  and  $S\beta$  is the molar entropy of phase  $\beta$  we need not label the pressure and temperature since at equilibrium these properties are the same for all phase within the system.

At equilibrium,  $dG\alpha = dG\beta$  so, that

$$V\alpha dP - S\alpha dT = V\beta dP - S\beta dT$$

$$(V\alpha - V\beta)dP = (S\alpha - S\beta)dT$$

We can write the differences as  $V\alpha - V\beta = \Delta V$  and  $S\alpha - S\beta = \Delta S$ . then

$$\Delta V dP = \Delta S dT$$
 this implies  $\frac{dP}{dT} = \frac{\Delta S}{\Delta V}$ 

But

$$\Delta G = \Delta H - T \Delta S = 0$$

since at equilibrium

$$\Delta G = G_{\infty} - G_{\beta} = 0$$

and therefore

$$\Delta S = \frac{\Delta H}{T}$$

which is the basis of Trouton's Rule.

# Substituting gives

$$\frac{dp}{dT} = \frac{\Delta S}{\Delta V} = \frac{\Delta H}{T\Delta V}$$

For one mole of ideal gas  $\Delta V = RT/P$ 

$$\frac{dp}{dT} = \frac{\Delta H}{T\Delta V} = \frac{P\Delta H}{RT^2}$$

which is the differential form of the Clausius-Clapeyron equation. Rearranging gives

$$\frac{dp}{P} = \frac{\Delta H}{R} \frac{dT}{T^2}$$

The integrated form of this equation is

$$lnP_2 - lnP_1 = \frac{\Delta H}{R} \left( \frac{1}{T_1} - \frac{1}{T_2} \right)$$
 Clausius-Clapeyron equation

# 4. Two component systems

For a two component system, C = 2, the phase rule can be written as

$$F = C - P + 2$$
 or  $F + P = C + 2$   $\Rightarrow F = 4 - P$ 

- ⇒ For a system having one phase the number degrees of freedom would be three
- ⇒ Three variables temperature, pressure & composition must be specified in order to describe a two component system completely.

To represent such a system graphically we must have the coordinates temperature, pressure and composition at right angles. This is a three dimensional figure which is rather difficult to construct. It is therefore customary to represent such a system by any two of the three variables keeping the third constant in this way one can represent the various relations in two component systems. In a two component system, the possible phase equilibria are;

Among the above listed equilibria those without the vapour phase are relatively unaffected by changes in pressure and such systems are often called condensed systems and are studied at constant pressure, usually (1 atmosphere).

 $\Rightarrow$  When pressure is constant the phase rule become F + P = C + 1

The equation is known as the reduced phase rule. F + P = 3 for a two component system

- ⇒ The equilibria taken is the liquid → solid equilibria the variables are temperature, and composition.
- ⇒ The phase diagram is represented on a temperature composition diagram

### **Experimental techniques to determine the equilibrium conditions**


To determine the equilibrium conditions for solid-liquid systems, it is necessary to determine the composition of the mixture at different temperatures. This can be done in two general ways

- a. Thermal analysis method
- **b.** The solubility (saturation) method

#### a. Thermal analysis method

In this technique a mixture of two components of known composition is heated until a homogenous melt or liquid phase is obtained (inert atmosphere is used to avoid oxidation). The melt is then cooled at a slow rate during which the melt is thoroughly stirred to avoid super cooling. The temperature of the melt is recorded at regular intervals until it completely solidifies. The process is repeated for other mixtures covering the entire range of composition (0-100%).

The temperature time plots (cooling curves) for each composition are then constructed. From such a diagram (figure 4.6.) it is possible to detect the various transformations and phase transitions that occur during cooling.




**Figure 4.6.** Cooling curves for a binary system with eutectic point **I**) for a pure component **II**) for a mixture of two components

When a melt containing only the pure component (a) is cooled slowly the cooling curve reveals that the slop of the curve is constant up to (b) which represents cooling of the melt at (b) the temperature is constant with time up to (c) which is called the <u>Halt</u>, is due to the heat evolved when the liquid solidifies. When solidification is complete the curve cd is obtained which represents the progressive cooling of the pure solid. But when a melt of two components is cooled slowly, a typical cooling curve of type shown in figure 4.6 (II) is obtained. The system becomes univariant (F = 3-2 = 1). On further cooling more and more of the pure components separate out. At point g, the  $2^{nd}$  component also begins

to crystallize from the melt and three phases are in equilibrium and the system becomes invariant (F = 3 - 3 = 0). The temperature remains constant. Finally when solidification is completed the system regains a degree of freedom (F = 1), and the temperature drops (hi) of the curve with a uniform cooling of the solid mass.

The experiments is repeated for different compositions of the substances (a and b), the temperature of the breaks and the halts for each cooling curve are recorded and plotted as functions of composition and a diagram of type figure 4.7 is obtained.



**Figure 4.7.** Phase diagram for a binary system with eutectic point.

At the eutectic point three phases coexist (melt, solid A solid B) the composition corresponding to this point has the lowest melting point. The temperature at this point is called the Eutectic temperature and the composition (e) is called the eutectic composition.

#### b. Solubility or saturation method

In this method solubility of one component is determined in the presence of the other at various temperatures. These measurements of solubility at different temperatures lead to the construction of phase diagram. To determine the solubility of A in B, excess of A is added to B (molten B, if B is a solid), kept at a desired constant temperature, stirred well until equilibrium is reached. The undissolved solid A is filtered off and the saturated solution of A in B is analyzed for both constituents. Similarly possible saturated solutions of B in A are analyzed at different temperatures. This is the principal method of analysis of systems containing water and similar solvents as one of the constituents. This method is very difficult to carry out at temperatures below -50 °C and also above 200 °C. Then the thermal analysis method is preferred.