Chapter 9: Virtual-Memory Management



Silberschatz, Galvin and Gagne ©2009

Chapter 9: Virtual-Memory Management

- Background
- Demand Paging
- Copy-on-Write
- Page Replacement
- Allocation of Frames
- Thrashing
- Memory-Mapped Files
- Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

Silberschatz, Galvin and Gagne ©2009

Objectives

- To describe the benefits of a virtual memory system
- To explain the concepts of demand paging, page-replacement algorithms, and allocation of page frames
- To discuss the principle of the working-set model

Background

- **Virtual memory** – separation of user logical memory from physical memory.
  - Only part of the program needs to be in memory for execution
  - Logical address space can therefore be much larger than physical address space
  - Allows address spaces to be shared by several processes
  - Allows for more efficient process creation
- Virtual memory can be implemented via:
  - Demand paging
  - Demand segmentation

Virtual Memory That is Larger Than Physical Memory



Virtual-address Space



Shared Library Using Virtual Memory



Demand Paging

- Bring a page into memory only when it is needed
  - Less I/O needed
  - Less memory needed
  - Faster response
  - More users
- Page is needed ⇒ reference to it
  - invalid reference ⇒ abort
  - not-in-memory ⇒ bring to memory
- **Lazy swapper** – never swaps a page into memory unless page will be needed
  - Swapper that deals with pages is a **pager**

Transfer of a Paged Memory to Contiguous Disk Space



Valid-Invalid Bit

- With each page table entry a valid–invalid bit is associated
  (**v** ⇒ in-memory, **i** ⇒ not-in-memory)
- Initially valid–invalid bit is set to **i** on all entries
- Example of a page table snapshot:

Frame #	valid-invalid bit
	v
	v
	v
	v
	i
….	
	i
	i

page table

- During address translation, if valid–invalid bit in page table entry is **I** ⇒ page fault

Page Table When Some Pages Are Not in Main Memory



Page Fault

- If there is a reference to a page, first reference to that page will trap to operating system:

  page fault

1. Operating system looks at another table to decide:
   - Invalid reference ⇒ abort
   - Just not in memory
2. Get empty frame
3. Swap page into frame
4. Reset tables
5. Set validation bit = **v**
6. Restart the instruction that caused the page fault

Page Fault (Cont.)

- Restart instruction
  - block move



  - auto increment/decrement location

Steps in Handling a Page Fault



Performance of Demand Paging

- Page Fault Rate $0 \le p \le 1.0$
  - if $p = 0$ no page faults
  - if $p = 1$, every reference is a fault
- Effective Access Time (EAT)

$$
\begin{aligned}
\text{EAT} = (1 - p) \text{ x memory access} \\
+\, p\ (\text{page fault overhead} \\
+ \text{ swap page out} \\
+ \text{ swap page in} \\
+ \text{ restart overhead} \\
)
\end{aligned}
$$

Demand Paging Example

- Memory access time = 200 nanoseconds
- Average page-fault service time = 8 milliseconds
- EAT = (1 – p) x 200 + p (8 milliseconds)
  = (1 – p x 200 + p x 8,000,000
  = 200 + p x 7,999,800
- If one access out of 1,000 causes a page fault, then
  EAT = 8.2 microseconds.
  This is a slowdown by a factor of 40!!

Process Creation

- Virtual memory allows other benefits during process creation:

  - Copy-on-Write

  - Memory-Mapped Files (later)

Copy-on-Write

- Copy-on-Write (COW) allows both parent and child processes to initially *share* the same pages in memory

  If either process modifies a shared page, only then is the page copied

- COW allows more efficient process creation as only modified pages are copied

- Free pages are allocated from a **pool** of zeroed-out pages

Before Process 1 Modifies Page C



After Process 1 Modifies Page C



What happens if there is no free frame?

- Page replacement – find some page in memory, but not really in use, swap it out
  - algorithm
  - performance – want an algorithm which will result in minimum number of page faults
- Same page may be brought into memory several times

Page Replacement

- Prevent over-allocation of memory by modifying page-fault service routine to include page replacement
- Use **modify (dirty) bit** to reduce overhead of page transfers – only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory – large virtual memory can be provided on a smaller physical memory

Need For Page Replacement



Basic Page Replacement

1. Find the location of the desired page on disk

2. Find a free frame:
   - If there is a free frame, use it
   - If there is no free frame, use a page replacement algorithm to select a **victim** frame

3. Bring the desired page into the (newly) free frame; update the page and frame tables

4. Restart the process

Page Replacement



Page Replacement Algorithms

- Want lowest page-fault rate
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
- In all our examples, the reference string is

1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5

Graph of Page Faults Versus The Number of Frames



First-In-First-Out (FIFO) Algorithm

- Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
- 3 frames (3 pages can be in memory at a time per process)

1	1	4	5
2	2	1	3
3	3	2	4

9 page faults

- 4 frames

1	1	5	4
2	2	1	5
3	3	2	
4	4	3	

10 page faults

- Belady's Anomaly: more frames $\Rightarrow$ more page faults

FIFO Page Replacement



FIFO Illustrating Belady's Anomaly



Optimal Algorithm

- Replace page that will not be used for longest period of time
- 4 frames example

1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5

1	4
2	
3	
4	5

6 page faults

- How do you know this?
- Used for measuring how well your algorithm performs

Optimal Page Replacement



Least Recently Used (LRU) Algorithm

- Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5

1	1	1	1	5
2	2	2	2	2
3	5	5	4	4
4	4	3	3	3

- Counter implementation
  - Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
  - When a page needs to be changed, look at the counters to determine which are to change

LRU Page Replacement

reference string

7	0	1	2	0	3	0	4	2	3	0	3	2	1	2	0	1	7	0	1
7	7	7	2		2		4	4	4	0			1		1		1		
	0	0	0		0		0	0	3	3			3		0		0		
		1	1		3		3	2	2	2			2		2		7		

page frames

LRU Algorithm (Cont.)

- Stack implementation – keep a stack of page numbers in a double link form:
  - Page referenced:
    - move it to the top
    - requires 6 pointers to be changed
  - No search for replacement

Use Of A Stack to Record The Most Recent Page References



Page sequence: 0 4 1 4 2 4 3 4 2 4 0 4 1 4 2 4 3 4



LRU Approximation Algorithms

- Reference bit
  - With each page associate a bit, initially = 0
  - When page is referenced bit set to 1
  - Replace the one which is 0 (if one exists)
    - We do not know the order, however
- Second chance
  - Need reference bit
  - Clock replacement
  - If page to be replaced (in clock order) has reference bit = 1 then:
    - set reference bit 0
    - leave page in memory
    - replace next page (in clock order), subject to same rules

Second-Chance (clock) Page-Replacement Algorithm



Global vs. Local Allocation

- **Global replacement** – process selects a replacement frame from the set of all frames; one process can take a frame from another
- **Local replacement** – each process selects from only its own set of allocated frames

Thrashing

- If a process does not have "enough" pages, the page-fault rate is very high. This leads to:
  - low CPU utilization
  - operating system thinks that it needs to increase the degree of multiprogramming
  - another process added to the system
- **Thrashing** ≡ a process is busy swapping pages in and out

Thrashing (Cont.)



Demand Paging and Thrashing

- Why does demand paging work?
  Locality model
  - Process migrates from one locality to another
  - Localities may overlap
- Why does thrashing occur?
  Σ size of locality > total memory size

Virtualization
Vs
Containerization

5.1 Virtual Machines

Running One application on one server is wastage of money i.e. DB server, email, Web server
A **virtual machine** takes the layered approach to its logical next step. It treats hardware and the operating system kernel as though they were all hardware
A virtual machine provides an interface identical to the underlying bare hardware
The operating system **host** creates the illusion that a process has its own processor (and virtual memory)
Each **guest** provided with a (virtual) copy of underlying computer

Virtual Machines (Cont.)



(a) (b)

(a) Non-virtual machine (b) virtual machine

Hypervisor / VMM



(b)

Types of Hypervisors



(a) A type 1 hypervisor

(b) A type 2 hypervisor

Types of Hypervisors



(a) A type 1 hypervisor (b) A type 2 hypervisor

5.2 Containers

VMs consume a lot of disk space, RAM and CPU due to its own OS, slow to startup

Containers only contains applications

A **Container** is an application that's been packaged with all the files, configurations, dependencies necessary for its run

The leading software that is used to create, manage and run containers is **dockers**

Containers are considered as light-weight (small app size), fast bootup, less recourses consumption, portable files

Drawback: Containers applications are totally depending upon the underlying OS, less secure

Virtual Machines vs. Containers



Hybrid Use


Container 5
Container 6
VM 1
VM 2
VM 3
Container 3
Container 4
Container 1
Container 2
Application 1
Application 2
Binaries, Libraries
CONTAINER ENGINE
GUEST OPERATING SYSTEM
Hypervisor
HOST OPERATING SYSTEM
Infrastructure

End of Chapter 9



Silberschatz, Galvin and Gagne ©2009