





Guía Detallada para Configurar Prometheus y Grafana en Windows

Esta guía proporciona instrucciones claras y detalladas paso a paso para configurar Prometheus y Grafana en un PC con Windows. Está especialmente diseñada para aquellos que se enfrentan a esta tarea por primera vez.

Paso 1: Descargar e Instalar Prometheus

1. Descarga:

- Visita la página de descargas de Prometheus en <u>Prometheus Downloads</u>.
- Elige y descarga la versión más reciente para Windows bajo la sección 'prometheus'.

2. Instalación:

- Extrae los archivos en una carpeta de tu elección, como **C:\Prometheus**.
- Abre una línea de comandos (cmd), navega a la carpeta donde extrajiste Prometheus, y ejecuta **prometheus.exe**.
- Prometheus debería ahora estar ejecutándose y ser accesible a través de http://localhost:9090.

Paso 2: Descargar e Instalar Windows Exporter

1. Descarga:

- Visita la página de descargas de Windows Exporter en Windows Exporter on GitHub.
- Descarga el archivo .msi para una instalación más sencilla en Windows.

2. Instalación:

- Ejecuta el archivo .msi descargado y sigue las instrucciones de instalación.
- Una vez instalado, abre una línea de comandos y ejecuta windows_exporter.exe.

```
ts=2024-05-11T10:27:28.980Z caller=main.go:1039 level=info msg="Stopping scrape manager..."

ts=2024-05-11T10:27:28.981Z caller=main.go:1031 level=info msg="Scrape manager stopped"

ts=2024-05-11T10:27:28.998Z caller=motifier.go:623 level=info component=notifier msg="Stopping notification manager..."

ts=2024-05-11T10:27:28.998Z caller=main.go:1261 level=info msg="Notifier manager stopped"

ts=2024-05-11T10:27:28.998Z caller=main.go:1273 level=info msg="Notifier manager stopped"

ts=2024-05-11T10:27:36.940Z caller=main.go:773 level=info msg="No time or size retention was set so using the default tit ts=2024-05-11T10:27:36.940Z caller=main.go:673 level=info msg="No time or size retention was set so using the default tit ts=2024-05-11T10:27:36.940Z caller=main.go:673 level=info msg="Starting Prometheus Server" mode=server version="(version 7df502e7315f408cebloa966d)"

ts=2024-05-11T10:27:36.940Z caller=main.go:622 level=info build_context="(go=go1.22.3, platform=windows/amd64, user=root iltinassets, stringlabels)"

ts=2024-05-11T10:27:36.940Z caller=main.go:623 level=info host_details=(windows)

ts=2024-05-11T10:27:36.940Z caller=main.go:623 level=info folimits=N/A

ts=2024-05-11T10:27:36.940Z caller=main.go:625 level=info msg="Start listening for connections" address=0.0 ts=2024-05-11T10:27:36.940Z caller=main.go:625 level=info msg="Starting TSDB ..."

ts=2024-05-11T10:27:36.940Z caller=main.go:621 level=info component=web msg="Start listening on" address=[::]:9090 ts=2024-05-11T10:27:36.969Z caller=ts_config.go:313 level=info component=web msg="TLS is disabled." http2=false address ts=2024-05-11T10:27:36.969Z caller=ts_config.go:318 level=info component=tweb msg="TLS is disabled." http2=false address ts=2024-05-11T10:27:36.997Z caller=head.go:781 level=info component=tsdb msg="Not is disabled." http2=false address ts=2024-05-11T10:27:36.997Z caller=head.go:781 level=info component=tsdb msg="Not is disabled." http2=false address ts=2024-05-11T10:27:36.997Z caller=head.go:781 level=info component=tsdb msg="Not is
```


 El Windows Exporter debería ahora estar disponible en http://localhost:9182/metrics.

```
# HELP go_gc_duration_seconds A summary of the pause duration of garbage collection cycles.
# TYPE go_gc_duration_seconds summary
go_gc_duration_seconds{quantile="0"} 0
go_gc_duration_seconds{quantile="0.25"} 0
go_gc_duration_seconds{quantile="0.5"} 0
go_gc_duration_seconds{quantile="0.75"
go_gc_duration_seconds{quantile="1"} 0
go_gc_duration_seconds_sum 0
go_gc_duration_seconds_count 3
# HELP go_goroutines Number of goroutines that currently exist.
# TYPE go_goroutines gauge
go goroutines 13
# HELP go info Information about the Go environment.
# TYPE go_info gauge
go_info{version="go1.21.9"} 1
# HELP go_memstats_alloc_bytes Number of bytes allocated and still in use.
# TYPE go_memstats_alloc_bytes gauge
go_memstats_alloc_bytes 2.636064e+06
# HELP go_memstats_alloc_bytes_total Total number of bytes allocated, even if freed.
# TYPE go_memstats_alloc_bytes_total counter
go_memstats_alloc_bytes_total 5.567568e+06
# HELP go_memstats_buck_hash_sys_bytes Number of bytes used by the profiling bucket hash table.
# TYPE go_memstats_buck_hash_sys_bytes gauge
go_memstats_buck_hash_sys_bytes 1.449989e+06
# HELP go_memstats_frees_total Total number of frees.
# TYPE go_memstats_frees_total counter
go_memstats_frees_total 21569
# HELP go_memstats_gc_sys_bytes Number of bytes used for garbage collection system metadata.
# TYPE go_memstats_gc_sys_bytes gauge
go_memstats_gc_sys_bytes 2.689944e+06
# HELP go_memstats_heap_alloc_bytes Number of heap bytes allocated and still in use.
# TYPE go_memstats_heap_alloc_bytes gauge
go_memstats_heap_alloc_bytes 2.636064e+06
# HELP go_memstats_heap_idle_bytes Number of heap bytes waiting to be used.
# TYPE go_memstats_heap_idle_bytes gauge
go_memstats_heap_idle_bytes 3.751936e+06
# HELP go_memstats_heap_inuse_bytes Number of heap bytes that are in use.
# TYPE go_memstats_heap_inuse_bytes gauge
go_memstats_heap_inuse_bytes 4.243456e+06
# HELP go_memstats_heap_objects Number of allocated objects.
# TYPE go_memstats_heap_objects gauge
go_memstats_heap_objects 7401
# HELP go_memstats_heap_released_bytes Number of heap bytes released to OS.
# TYPE go_memstats_heap_released_bytes gauge
go_memstats_heap_released_bytes 3.612672e+06
# HELP go_memstats_heap_sys_bytes Number of heap bytes obtained from system.
# TYPE go_memstats_heap_sys_bytes gauge go_memstats_heap_sys_bytes 7.995392e+06
# HELP go_memstats_last_gc_time_seconds Number of seconds since 1970 of last garbage collection.
# TYPE go_memstats_last_gc_time_seconds gauge
go_memstats_last_gc_time_seconds 1.7154225576307242e+09
# HELP go_memstats_lookups_total Total number of pointer lookups.
# TYPE go_memstats_lookups_total counter
go memstats lookups total 0
```

Paso 3: Configurar Prometheus para Recolectar Datos de Windows Exporter

1. Configuración de Targets:

Navega a http://localhost:9090/targets para verificar los targets actuales.
 (Debería estar al menos Up el Endpoint que apunta al 9090, que es prometheus)



 Modifica prometheus.yml en la carpeta de Prometheus para añadir el job de Windows Exporter con el siguiente bloque bajo scrape_configs:

yaml

- job_name: 'windows_exporter' static_configs: - targets: ['localhost:9182']

```
C:\Prometheus\prometheus.yml - Notepad++
Archivo Editar Buscar Vista Codificación Lenguaje Configuración Herramientas Macro Ejecutar Complementos Pestañas ?
change.log 🖸 🔚 prometheus.yml 🖸
        # my global config
      =global:
          scrape_interval: 15s # Set the scrape interval to every 15 seconds. Default is every 1 minute.
          evaluation_interval: 15s # Evaluate rules every 15 seconds. The default is every 1 minute.
          # scrape_timeout is set to the global default (10s).
        # Alertmanager configuration
      alerting:
          alertmanagers:
            - static_configs:
                - targets:
 12
13
14
                  # - alertmanager:9093
        # Load rules once and periodically evaluate them according to the global 'evaluation interval'.
      _rule_files:
          # - "first_rules.yml"
# - "second_rules.yml"
18
19
20
21
       # A scrape configuration containing exactly one endpoint to scrape:
        # Here it's Prometheus itself.
      -scrape configs:
 22
23
24
25
26
27
28
            The job name is added as a label 'job=<job name>' to any timeseries scraped from this config.
           - job_name: "prometheus"
          - job_name: "node_exporter"
            # metrics_path defaults to '/metrics'
            # scheme defaults to 'http'.
            static_configs:
              - targets: ["localhost:9090"]
- targets: ["localhost:9100"]
              - targets: ["localhost:9182"]
```

 Guarda el archivo y reinicia Prometheus para que los cambios surtan efecto.

Paso 4: Descargar e Instalar Grafana

- 1. Descarga:
 - Descarga Grafana desde <u>Grafana Download Page</u>.

2. Instalación:

- Instala Grafana y navega a la carpeta de instalación para ejecutar bin\grafana-server.exe.
- Grafana debería estar accesible a través de http://localhost:3000.

Paso 5: Configurar Grafana

- Abre un navegador y visita http://localhost:3000 para iniciar sesión (admin/admin).
- Añade Prometheus como fuente de datos desde 'Configuration' > 'Data Sources'.
- Configura la URL de Prometheus como http://localhost:9090 y guarda los cambios.

Paso 6: Crear un Dashboard en Grafana

- Selecciona 'Create' > 'Dashboard' y agrega un nuevo panel.
- En 'Metrics', selecciona Prometheus como la fuente de datos y escribe una consulta, por ejemplo, **node_cpu_seconds_total**.
- Para añadir la consulta, simplemente selecciona 'Add Query' y luego 'Run Queries'.
- Configura y guarda tu panel y dashboard.

Paso 7: Monitorear

 Utiliza los dashboards creados para monitorear las métricas de tu sistema en tiempo real. Puedes buscar las métricas disponibles directamente en la interfaz de Grafana.

