









## **Docker Containers: IPC using Sockets — Part 2**

Implementing an echo server and client using Python and deploying them in Docker containers.

<u>In the first part of the this blog</u>, I have demonstrated IPC using sockets in Python between a Docker container that is running the server code and a client script running on the host. The server echoes the message back to the client.

The short of it: Enable networking in docker — application inside the container is agnostic to the changes — Container should be named (using — name flag), which become the DNS name for that container.

As the first step, create a directory titled 'server'. Inside that directory create the following two files - 'ipc\_server.py' and 'Dockerfile'. In the file 'ipc\_server.py', replace line #6 with the following:

HOST = socket.gethostbyname('ipc\_server\_dns\_name')

```
#!/usr/bin/env python3
2
    # ipc_server.py
3
4
   import socket
5
   HOST = '127.0.0.1' # Standard loopback interface address (localhost)
6
7
    PORT = 9898
                      # Port to listen on (non-privileged ports are > 1023)
8
9
   with socket.socket(socket.AF_INET, socket.SOCK_STREAM) as s:
10
        s.bind((HOST, PORT))
11
        s.listen()
12
        conn, addr = s.accept()
13
14
        with conn:
            print('Connected by', addr)
15
            while True:
16
17
                data = conn.recv(1024)
                if not data:
18
                   break
19
                conn.sendall(data)
20
ipc_server.py hosted with ♥ by GitHub
                                                                                             view raw
```

<u>12</u> | Q

Build the docker container for ipc\_server using following command from inside the 'server' directory.

```
>> docker build -t my_ipc_server .
```

Now create a directory titled 'client'. Inside that directory create the following two files — 'ipc\_server.py' and 'Dockerfile'. In the file 'ipc\_client.py', replace line #6 with the following. Note that the hostname 'ipc\_server\_dns\_name' must be consistent with the ipc\_server.py and the 'docker run' command, which we will see later in the post:

```
HOST = socket.gethostbyname('ipc_server_dns_name')
```

Build the docker container for ipc\_client using following command from inside the 'client' directory.

```
>> docker build -t my_ipc_client .
```

If you are running on Linux, running both containers can communicate with each other using following commands (server container first):

```
>> docker run -rm --network=host --name ipc_server_dns_name
my_ipc_server
>> docker run -rm --network=host my_ipc_client
```

On MacOS and Windows, Docker runs inside a virtual machine. Thus, 'network=host' will not bind the IP address for DNS name 'ipc\_server\_dns\_name' to host. We must define <u>bridged network in Docker</u> for containers to be able to communicate via sockets. Use following command to create a network:

```
>> docker network create my_socket_ipc_network
```

Now, running both containers using following commands will enable the server and client containers to communicate with each other(server container first):

```
>> docker run -rm --network=my_socket_ipc_network --name
ipc_server_dns_name my_ipc_server
>> docker run -rm --network=my_socket_ipc_network my_ipc_client
```

You should see the message 'Hello, world. IPC success!' printed on the terminal of client. The message is simply echoed by the server.

Docker Python Sockets Containers

About Help Terms Privacy

Get the Medium app



