# 操作系统lab1: RV64 内核引导与时钟中断处理

教师: 李环、柳晴 学号: 3220104519

姓名: 蔡佳伟

# 一、实验目的和要求

- 学习 RISC-V 汇编,编写 head.S 实现跳转到内核运行的第一个 C 函数;
- 学习 OpenSBI, 理解 OpenSBI 在实验中所起到的作用,并调用 OpenSBI 提供的接口完成字符的输出:
- 学习 Makefile 相关知识,补充项目中的 Makefile 文件,来完成对整个工程的管理;
- 学习 RISC-V 的 trap 处理相关寄存器与指令,完成对 trap 处理的初始化;
- 理解 CPU 上下文切换机制,并正确实现上下文切换功能;
- 编写 trap 处理函数,完成对特定 trap 的处理;
- 调用 OpenSBI 提供的接口,完成对时钟中断事件的设置。

# 二、实验过程

# 2.0 更新qemu版本

实验过程中,做到一大半,完成修改RV64内核引导的所有步骤后,发现无论如何都无法输出2024那一段提示语(make显示正常,修改了很多发现没有问题)。然后就放弃休息了一段时间,再接着就发现实验指导更新了同时gemu需要更新。查看版本后发现是6.2,于是更新。

```
cjw@cjw-virtual-machine:~$ lsb_release -a
No LSB modules are available.
Distributor ID: Ubuntu
Description: Ubuntu 24.04.1 LTS
Release: 24.04
Codename: noble
cjw@cjw-virtual-machine:~$ qemu-system-riscv64 --version
QEMU emulator version 8.2.2 (Debian 1:8.2.2+ds-0ubuntu1.2)
Copyright (c) 2003-2023 Fabrice Bellard and the QEMU Project developers
cjw@cjw-virtual-machine:~$
```

直接更新了ubuntu版本到24.04,结果如上。

# 2.1 RV64内核引导

### 2.1.1 准备工作

clone整个文件夹后,安装tree所需要的文件,显示如下

```
jw@cjw-virtual-machine:~/OSlab1/os24fall-stu/src/lab1$ sudo snap install tree
[sudo] password for cjw:
tree 1.8.0+pkg-3fd6 from 林博仁(Buo-ren Lin) (brlin) installed
cjw@cjw-virtual-machine:~
locales-launch: Data of en_US locale not found, generating, please wait...
locales-launch: Data of zh_CN locale not found, generating, please wait...
 Ubuntu 22.04.4 LTS amd64
              - sbi.h
                head.S
                Makefile
                sbi.c
               - vmlinux.lds
            Makefile
    fw_jump.bin
      — printk.h
       stddef.h
       stdint.h
       main.c
       Makefile
        test.c
       · Makefile
       printk.c
    Makefile
7 directories, 17 files
```

#### 2.1.2 完善Makefile脚本

```
Makefile
 Open ~
            J+1
                                           ~/OSlab1/os24fall-stu/src/lab1/lib
1 C_SRC
               = $(sort $(wildcard *.c))
                        = $(patsubst %.c,%.o,$(C_SRC))
2 OBJ
3
4 all:$(0BJ)
5
6 %.o:%.c
           ${GCC} ${CFLAG} -c $<
7
8 clean:
          $(shell rm *.o 2>/dev/null)
```

完成如上,直接照抄了/init/Makefile的文件

```
cjw@cjw-virtual-machine:~/OSlab1/os24fall-stu/src/lab1$ make
make -C lib clean
make[1]: Entering directory '/home/cjw/OSlab1/os24fall-stu/src/lab1/lib'
make[1]: 'clean' is up to date.
make[1]: Leaving directory '/home/cjw/OSlab1/os24fall-stu/src/lab1/lib'
make -C init clean
make[1]: Entering directory '/home/cjw/OSlab1/os24fall-stu/src/lab1/init'
make[1]: 'clean' is up to date.
make[1]: Leaving directory '/home/cjw/OSlab1/os24fall-stu/src/lab1/init'
make -C arch/riscv clean
make[1]: Entering directory '/home/cjw/OSlab1/os24fall-stu/src/lab1/arch/riscv'
make -C kernel clean
make[2]: Entering directory '/home/cjw/OSlab1/os24fall-stu/src/lab1/arch/riscv/k
ernel'
make[2]: 'clean' is up to date.
make[2]: Leaving directory '/home/cjw/OSlab1/os24fall-stu/src/lab1/arch/riscv/ke
rnel
make[1]: Leaving directory '/home/cjw/OSlab1/os24fall-stu/src/lab1/arch/riscv'
Clean Finished
```

```
riscv64-linux-gnu-ld -T kernel/vmlinux.lds kernel/*.o ../../init/*.o ../../lib/*
.o -o ../../vmlinux
riscv64-linux-gnu-objcopy -O binary ../../vmlinux ./boot/Image
riscv64-linux-gnu-objdump -S ../../vmlinux > ../../vmlinux.asm
nm ../../vmlinux > ../../System.map
make[1]: Leaving directory '/home/cjw/OSlab1/os24fall-stu/src/lab1/arch/riscv'
Build Finished OK
```

可以看到不会再提示 Makefile 的错误,而是 C 或汇编代码中的 #error 错误。

#### 2.1.3 编写head.S

```
™ head.S
home > cjw > OSlab1 > os24fall-stu > src > lab1 > arch > riscv > kernel > 🙉 head.S
      .extern start kernel
          .section .text.entry
          .globl start
      start:
         # - your code here -
         # set sp move to top of boot_stack
         la sp,boot_stack_top
         call start kernel
         # start kernel return and halt
          # ------
          .section .bss.stack
          .globl boot stack
      boot stack:
          .space 4096 # <-- change to your stack size
 19
          .globl boot stack top
      boot stack top:
```

补充如上

#### 2.1.4 补充sbi.c

先将参数ext、fid和arg0到arg5放入相应的寄存器中,然后使用ecall指令进入M模式,等待OpenSBI完成相关操作。最后,它将返回的结果存储在ret结构体中,并返回该结构体。

#### 2.1.5 修改defs.h

```
struct sbiret sbi_debug_console_write_byte(uint8_t byte) {
    struct sbiret ret;
    ret=sbi_ecall(0x4442434e,0x2,byte,0,0,0,0);
    return ret;
}

struct sbiret sbi_system_reset(uint32_t reset_type, uint32_t reset_reason) {
    struct sbiret ret;
    ret=sbi_ecall(0x53525354,0,0,0,0,0,0);
    return ret;
}
```


其中退出函数参数先写了0(因为这里只会用到0),后续我再进行修改。

```
cjw@cjw-virtual-machine:~/OSlab1/os24fall-stu/src/lab1 Q = - □ ×

cjw@cjw-virtual-machine:~/OSlab1/os24fall-stu/src/lab1$ make run

make -C lib clean

make[1]: Entering directory '/home/cjw/OSlab1/os24fall-stu/src/lab1/lib'
```



这里执行make run,发现正确打印了欢迎信息并正常退出。

### 2.2 RV64时钟中断处理

#### 2.2.1 准备工作

修改vmlinux.lds和head.S

```
riscv > kernel > ≡ vmlinux.lds
     /* 目标架构 */
     OUTPUT ARCH("riscv")
     /* 程序入口 */
     ENTRY( start)
     /* kernel 代码起始位置 */
     BASE ADDR = 0x802000000;
     SECTIONS
 11
         /* . 代表当前地址 */
 12
 13
         . = BASE ADDR;
         /* 记录 kernel 代码的起始地址 */
 15
         _skernel = .;
         /* ALIGN(0x1000) 表示 4KiB 对齐 */
         /* stext, etext 分别记录了 text 段的起始与结束地址
         .text : ALIGN(0x1000) {
            _stext = .;
             *(.test.init)
 23
 24
             *(.text.entry)
             *(.text .text.*)
            _etext = .;
```

```
riscv > kernel > xsm head.S

1 .extern start_kernel

2 .section .text.init

3 .globl _start

4 start:
```

#### 2.2.2 初始化CSR

将 traps (traps 在 4.3.2 中实现) 所表示的地址写入 stvec:

```
# set stvec = _traps
la a0, _traps
csrw stvec, a0
```

开启时钟中断,将sie[STIE]置1

```
# set sie[STIE] = 1
li a0,0x20
csrs sie, a0
```

```
# set first time interrupt
rdtime a0
li t0, 100000000
add a0, a0, t0
li a6, 0
li a7, 0x54494d45
ecall
```

注意这里设置a6为0,a7为0x54494d45,因为调用ecall时直接使用了a6,a7寄存器里存储的值。这两个参数是extension id和function id。

将sstatus[SIE]置1

```
# set sstatus[SIE] = 1
csrs sstatus, 1 << 1
```

### 2.2.3 实现上下文切换

在 arch/riscv/kernel/ 目录下添加 entry.S 文件保存 CPU 的寄存器 (上下文) 到内存中(栈上)

```
traps:
  # 1. save 32 registers and sepc to stack
  # 32*8 space to save
  # sd sp, -8(sp)
  addi sp, sp, -256
  sd tp, 0(sp)
  sd ra, 8(sp)
  sd gp, 16(sp)
  sd t0, 24(sp)
  sd t1, 32(sp)
  sd t2, 40(sp)
  sd s0, 48(sp)
  sd s1, 56(sp)
  sd a0, 64(sp)
  sd a1, 72(sp)
  sd a2, 80(sp)
  sd a3, 88(sp)
  sd a4, 96(sp)
  sd a5, 104(sp)
  sd a6, 112(sp)
  sd a7, 120(sp)
  sd s2, 128(sp)
  sd s3, 136(sp)
  sd s4, 144(sp)
  sd s5, 152(sp)
  sd s6, 160(sp)
  sd s7, 168(sp)
  sd s8, 176(sp)
  sd s9, 184(sp)
  sd s10, 192(sp)
  sd s11, 200(sp)
  sd t3, 208(sp)
  sd t4, 216(sp)
  sd t5, 224(sp)
  sd t6, 232(sp)
  csrr t0, sepc
  sd t0, 240(sp)
```

将 scause 和 sepc 中的值传入 trap 处理函数 trap\_handler

```
# 2. call trap_handler
# set scause into a0, set sepc to a1
csrr a0, scause
csrr a1, sepc
call trap_handler
```

在完成对 trap 的处理之后,我们从内存中(栈上)恢复 CPU 的寄存器(上下文)

```
# 3. restore sepc and 32 registers (x2(sp) should be restore last) from stack
ld t0, 240(sp)
csrw sepc, t0
ld tp, 0(sp)
ld ra, 8(sp)
ld gp, 16(sp)
ld t0, 24(sp)
ld t1, 32(sp)
ld t2, 40(sp)
ld s0, 48(sp)
ld s1, 56(sp)
ld a0, 64(sp)
ld a1, 72(sp)
ld a2, 80(sp)
ld a3, 88(sp)
ld a4, 96(sp)
ld a5, 104(sp)
ld a6, 112(sp)
ld a7, 120(sp)
ld s2, 128(sp)
ld s3, 136(sp)
ld s4, 144(sp)
ld s5, 152(sp)
ld s6, 160(sp)
ld s7, 168(sp)
ld s8, 176(sp)
ld s9, 184(sp)
ld s10, 192(sp)
ld s11, 200(sp)
ld t3, 208(sp)
ld t4, 216(sp)
ld t5, 224(sp)
ld t6, 232(sp)
addi sp, sp, 256
```

从trap中返回

```
# 4. return from trap
sret
```

## 2.2.4 实现trap处理函数

一开始先判断是否是中断,如果是中断,判断是否是5(时钟类型),如果是就调用 clock\_set\_next\_event()。

#### 2.2.5 实现时钟中断相关函数

注意调用sbi\_ecall需要设置第一个参数为0x54494d45,这个是设置时钟相关寄存器的extension id, functuon id是0。

```
riscv > kernel > C clock.h > ...
1  #ifndef _CLOCK_H
2  #define _CLOCK_H
3  void clock_set_next_event();
4  #endif
```

此外,为了正常调用clock\_set\_next\_event(),我完成了clock.h文件。

#### 2.2.6 修改test函数

为了让 kernel 持续运行,并使中断更容易观察,将 test.c 中的 test() 函数修改为如下内容:

我还修改了init文件中的makefile文件,添加了file=main.o(试了一下不改也行)

运行结果:

在根目录下使用make run

正常运行。

```
Boot HART MEDELEG
                          : 0x0000000000f0b509
2024 ZJU Operating System
kernel is running!
kernel is running!
kernel is runnina!
[INTERRUPT] S mode timer interrupt!
kernel is runnina!
kernel is running!
kernel is runnina!
[INTERRUPT] S mode timer interrupt!
kernel is running!
kernel is running!
kernel is running!
kernel is running!
[INTERRUPT] S mode timer interrupt!
kernel is running!
kernel is running!
kernel is running!
[INTERRUPT] S mode timer interrupt!
kernel is running!
kernel is running!
kernel is running!
```

# 三、讨论和心得

本次遇到的第一个问题是版本更新,一开始更新qemu一直没有成功,后来拖了两天,发现ubuntu也要更新,且更新完ubuntu后qemu也更新了,那就算解决了这个问题,本来一直更新很奇怪的。

第二个问题是在第一个小实验里一直输出不了欢迎信息。修改尝试了很多次,最后居然是sbi.c里面mva0到a5的顺序是有影响的,测试中是a0在最后面就不行,0-5的顺序可以,稍微交换一点也可以。不是很理解这一段,因为讲道理什么顺序应该是没有影响的才对。

第三个问题是最抽象的,因为vmlinux.asm可以看到汇编的执行顺序嘛,我发现我先执行的是trap,然后怎么修改都不对,找了很多地方都没有发现bug。然后我复制了一份一模一样的vmlinux.lds,就好了?! 就好了?! 真的很离谱。如果不是亲眼所见,真的完全不敢相信的。助教gg肯定觉得是有哪里没有修改,但真的完全一样。

# 四、思考题

# 1.请总结一下 RISC-V 的 calling convention,并解释 Caller / Callee Saved Register 有什么区别?

#### 调用过程:

- 1. 将参数存储到函数能够访问到的位置
- 2. 使用jal指令跳转到函数开始位置
- 3. 获取函数需要的局部存储资源,按需保存寄存器
- 4. 执行函数中的指令
- 5. 将返回值存储到调用者能够访问到的位置,恢复寄存器,释放局部存储资源
- 6. 返回调用函数的位置 (ret指令)


#### 规范:

- 1. 变量应该尽量放在寄存器而不是内存中
- 2. 避免频繁地保存和恢复进村器
- 3. 整型参数保存在a0-a7寄存器中, 浮点型参数存在f0到f7寄存器中
- 4. 整型返回值存在a0寄存器中, 浮点返回值存在f0寄存器中
- 5. 函数调用中其它的寄存器,要么被当做保存寄存器来使用,在函数调用前后值不变,要么被当做淋湿寄存器使用,在函数调用中不保留

#### Caller / Callee Saved Register 区别:

- 1. Caller-Saved寄存器是在函数调用前由调用者保存,如果需要在函数调用之后恢复,则需要调用者自行保存和恢复。用于保存在调用之间不用保留的临时数据。
- 2. Callee-Saved寄存器是被调用的函数保存和恢复的寄存器,被调用的函数负责保存和恢复这些寄存器。用于保存长期使用的寄存器值。

### 2.编译之后,通过 System.map 查看 vmlinux.lds 中自定义符号的值并截图



```
0000000080200000 A BASE ADDR
    0000000080204000 B boot_stack
   0000000080205000 B boot_stack_top
21 000000008020018c T clock_set_next_event
   00000000080205000 B _ebss
0000000080203008 D _edata
24 0000000080205000 B _ekernel
   00000000802020a9 R _erodata
0000000080201408 T _etext
27 0000000080200164 T get cycles
30 0000000080202098 r lowerxdigits.0
0000000080201388 T printk
33 00000000802004f4 T putc
34 000000080200808 t puts_wo_nl
    00000000802002b0 T sbi debug console write byte
36 00000000802001f4 T sbi ecall
0000000080204000 B _sbss
0000000080203000 D _sdata
40 0000000080200000 T _skernel
   0000000080202000 R _srodata
0000000080200000 T _start
43 0000000080200460 T start kernel
   0000000080200000 T _stext
000000008020059c T strtol
46 00000000802004a4 T test
   0000000080203000 D TIMECLOCK
00000000802003fc T trap_handler
49 000000008020004c T traps
     0000000080202080 r upperxdigits.1
     0000000080200b98 T vprintfmt
```

可以查看T,B,D,R变量的地址和sbi\_ecall,start\_kernel等符号的值

# 3.用 csr\_read 宏读取 sstatus 寄存器的值,对照 RISC-V 手册解释其含义并截图。

2024 ZJU Operating System 8000000200006002kernel is running!

sstatus值为80000002 00006002 由手册可知SIE目前是1。

	XLEN-1	X	LEN-2	2					20	19	18	17
Γ	SD					0			1	MXR	SUM	0
	1				XL	EN-21				1	1	1
	16	15	14	13	12 9	8	7 6	5	4	3 2	1	0
_	XS[1	:0]	FS[	1:0]	0	SPP	0	SPIE	UPI	E 0	SIE	UIE
_	2		- 2	2	4	1	2	1	1	2	1	1

图 10.9: sstatus CSR。sstatus 是 mstatus (图 10.4) 的一个子集,因此它们的布局类似。SIE 和 SPIE 中分别保存了当前的和异常发生之前的中断使能,类似于 mstatus 中的 MIE 和 MPIE。RV32 的 XLEN 为 32, RV64 为 40。(来自[Waterman and Asanovic 2017]中的图 4.2; 有关其他域的说明请参见该文档的第 4.1 节。)

由手册可知, SIE=1时中断启用, 进入中断时SIE=0防止其他中断产生, 这时SPP=1表明此时与普通的禁止中断状态不同

# 4.用 csr\_write 宏向 sscratch 寄存器写入数据,并验证是否写入成功并截图。

```
2024 ZJU Operating System
Okernel is running!
kernel is running!
kernel is running!
[INTERRUPT] S mode timer interrupt!
kernel is running!
```

```
2024 ZJU Operating System
666kernel is running!
kernel is running!
kernel is running!
```

说明写入成功。

# 5.详细描述你可以通过什么步骤来得到 arch/arm64/kernel/sys.i, 给出过程以及截图。

1. 安装交叉编译工具 (在linux-6.11-rc7目录下) : sudo apt install gcc-aarch64-linux-gnu

2. 生成config

make ARCH=riscv CROSS\_COMPILE=riscv64-linux-gnu- defconfig

3. make获得文件sys.i

make ARCH=riscv CROSS\_COMPILE=riscv64-linux-gnu- arch/arm64/kernel/sys.i

```
cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7/arch/arm64/kernel$ ls
                          image.h
                                                return_address.c
acpi.c
acpi_numa.c
                         image-vars.h
                                                sdei.c
acpi parking protocol.c io.c
                                                setup.c
alternative.c
                                                signal32.c
                         irq.c
armv8 deprecated.c
                         jump_label.c
                                                signal.c
asm-offsets.c
                         kaslr.c
                                                sigreturn32.S
cacheinfo.c
                         kexec_image.c
                                                sleep.S
compat_alignment.c
                                                smccc-call.S
                         kgdb.c
cpu errata.c
                         kuser32.S
                                                SMD.C
                         machine_kexec.c
                                                smp spin table.c
cpufeature.c
                         machine_kexec_file.c stacktrace.c
cpuinfo.c
                         Makefile
cpu_ops.c
                                                suspend.c
cpu-reset.S
                         Makefile.syscalls
                                                sys32.c
crash_dump.c
                         module.c
                                                sys.c
debug-monitors.c
                         module-plts.c
                                                syscall.c
efi.c
                         mte.c
                                                sys compat.c
efi-header.S
                         paravirt.c
                                                sys.i
efi-rt-wrapper.S
                         patching.c
                                                time.c
elfcore.c
                         pci.c
                                                topology.c
entry-common.c
                         perf_callchain.c
                                                trace-events-emulation.h
entry-fpsimd.S
                         perf_regs.c
                                                traps.c
entry-ftrace.S
entry.S
                         pointer_auth.c
fpsimd.c
                                                vdso32-wrap.S
ftrace.c
                                                vdso.c
                         process.c
head.S
                         proton-pack.c
                                                vdso-wrap.S
hibernate-asm.S
                         psci.c
                                                vmcore_info.c
hibernate.c
                         ptrace.c
                                                vmlinux.lds.S
hw_breakpoint.c
                         relocate kernel.S
                                                watchdog_hld.c
hyp-stub.S
                         reloc test core.c
idle.c
                         reloc_test_syms.S
```

可以看到出现sys.i

#### 6.寻找 Linux v6.0 中 ARM32 RV32 RV64 x86\_64 架构的系统调用表;

请列出源代码文件,展示完整的系统调用表(宏展开后),每一步都需要截图。

#### 1. ARM32

进入linux-6.11-rc7/arch/arm/tools 使用vim syscall.tbl查看

```
cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7/arch$ cd arm
cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7/arch/arm$ cd tools
cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7/arch/arm/tools$ ls
gen-mach-types mach-types Makefile syscallnr.sh syscall.tbl
cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7/arch/arm/tools$ vim syscall.tbl
```

```
SPDX-License-Identifier: GPL-2.0 WITH Linux-syscall-note
# Linux system call numbers and entry vectors
# The format is:
                                      [<entry point>
                                                                      [<oabi compat e
ntry point>]]
# Where abi is:
# common - for system calls shared between oabi and eabi (may have compat)
       common restart_syscall
                                      sys restart syscall
                                       sys_exit
       common exit
                                       sys_fork
       common fork
       common read
                                      sys_read
       common write
                                      sys_write
       common open
                                      sys_open
       common close
6
                                      sys_close
# 7 was sys_waitpid
      common creat
8
                                      sys_creat
      common link
                                      sys_link
10
      common unlink
                                      sys_unlink
11
      common execve
                                      sys_execve
                                      sys_chdir
12
      common chdir
      oabi
       oabi time
common mknod
13
                                      sys_time32
14
                                      sys_mknod
       common chmod
15
                                      sys_chmod
       common lchown
                                      sys_lchown16
16
# 17 was sys_break
# 18 was sys_stat
19
       common lseek
                                      sys_lseek
20
       common getpid
                                       sys_getpid
"syscall.tbl" 479L, 17510B
                                                                                 Top
                                                                   1,1
```

#### 2. RV32

```
cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7/arch/riscv/kernel$ ls
acpi.c
                       hibernate-asm.S sbi.c
acpi numa.c
                       hibernate.c
                                           sbi ecall.c
alternative.c
                       image-vars.h
                                           sbi-ipi.c
asm-offsets.c
                       irq.c
                                           setup.c
                                          signal.c
smpboot.c
asm-offsets.s
                       jump_label.c
cacheinfo.c
                       kernel_mode_fpu.c
cfi.c
                       kernel_mode_vector.c smp.c
compat_signal.c
                       kexec relocate.S
                                           SOC.C
compat_syscall_table.c kgdb.c
                                           stacktrace.c
                       machine kexec.c
                                           suspend.c
                       machine_kexec_file.c suspend_entry.S
copy-unaligned.h
copy-unaligned.S
                       Makefile
                                            syscall_table.c
cpu.c
                       Makefile.syscalls
                                            sys_hwprobe.c
                                            sys_riscv.c
                       mcount-dyn.S
cpufeature.c
                       mcount.S
cpu-hotplug.c
cpu_ops.c
                       module.c
                                            time.c
                       module-sections.c
cpu_ops_sbi.c
                                            traps.c
cpu_ops_spinwait.c
                       paravirt.c
                                             traps_misaligned.c
crash_dump.c
                       patch.c
                                            unaligned_access_speed.c
                       perf_callchain.c
crash_save_regs.S
efi.c
                       perf_regs.c
                                            vdso.c
efi-header.S
                                            vector.c
elf_kexec.c
                                            vendor_extensions.c
entry.S
                       process.c
                                            vmcore_info.c
fpu.S
                       ptrace.c
ftrace.c
                                            vmlinux.lds
                                             vmlinux.lds.S
head.h
                       return_address.c
head.S
                       riscv_ksyms.c
                                            vmlinux-xip.lds.S
```

#### 先进行defconfig编译,需要注意,使用rv32\_defconfig

#### 进行make

```
cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7$ make ARCH=riscv CROSS_COMPILE=riscv
64-linux-gnu- arch/riscv/kernel/syscall_table.i
          include/config/auto.conf.cmd
  UPD
          include/generated/compile.h
  CC
          scripts/mod/empty.o
  MKELF
         scripts/mod/elfconfig.h
  HOSTCC scripts/mod/modpost.o
          scripts/mod/devicetable-offsets.s
  \mathsf{CC}
  UPD
          scripts/mod/devicetable-offsets.h
  HOSTCC scripts/mod/file2alias.o
         scripts/mod/sumversion.o
  HOSTCC
  HOSTCC scripts/mod/symsearch.o
  HOSTLD scripts/mod/modpost
          kernel/bounds.s
  CC
  UPD
          include/generated/bounds.h
  CC
          arch/riscv/kernel/asm-offsets.s
  UPD
          include/generated/asm-offsets.h
  CALL
          scripts/checksyscalls.sh
          arch/riscv/kernel/vdso/vdso.lds
  LDS
          arch/riscv/kernel/vdso/rt_sigreturn.o
  AS
          arch/riscv/kernel/vdso/getcpu.o
  AS
  AS
          arch/riscv/kernel/vdso/flush_icache.o
  CC
          arch/riscv/kernel/vdso/hwprobe.o
          arch/riscv/kernel/vdso/sys_hwprobe.o
  AS
          arch/riscv/kernel/vdso/note.o
  AS
  VDSOLD arch/riscv/kernel/vdso/vdso.so.dbg
  VDSOSYM include/generated/vdso-offsets.h
         arch/riscv/kernel/syscall_table.i
```

可以发现出现syscall\_table.i,可以通过vim来查看

```
cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7$ cd arch/riscv/kernel
 cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7/arch/riscv/kernel$ ls
                                           sbi-ipi.c
setup.c
                          hibernate.c
 acpi_numa.c
                           image-vars.h
                                                  signal.c
                           irq.c
 alternative.c
                                                  smpboot.c
 asm-offsets.c
                           jump_label.c
 asm-offsets.s
                           kernel_mode_fpu.c
                                                    SMD.C
 cacheinfo.c
                           kernel_mode_vector.c soc.c
cfi.c
                          kexec_relocate.S
                                                   stacktrace.c
compat_signal.ckgdb.csuspend.ccompat_syscall_table.cmachine_kexec.csuspend_entry.S
                          machine_kexec_file.c syscall_table.c
copy-unaligned.h
copy-unaligned.S
                          Makefile
                                                  syscall_table.i
                          Makefile.syscalls sys_hwprobe.c
                          mcount-dyn.S
 cpu.c
                                                   sys_riscv.c
                     mcount.s
module.c
dule-si
 cpufeature.c
 cpu-hotplug.c
                                                   time.c
 cpu ops.c
                         module-sections.c
                                                  traps.c
cpu_ops_sbi.c
cpu_ops_spinwait.c
                         paravirt.c
                                                   traps misaligned.c
                         patch.c
                                                   unaligned_access_speed.c
                         perf_callchain.c
 crash_dump.c
crash_save_regs.S
                          perf_regs.c
                                                   vdso.c
 efi.c
                                                   vector.c
                                                 vendor_extensions
vendor_extensions.c
vmcore_info.c
 efi-header.S
elf_kexec.c
                           process.c
                          ptrace.c
entry.S
 fpu.S
                          reset.c
                                                  vmlinux.lds
                          return_address.c
riscv_ksyms.c
 ftrace.c
                                                 vmlinux.lds.S
 head.h
                                                  vmlinux-xip.lds.S
 head.S
                           sbi.c
 hibernate-asm.S
                          sbi_ecall.c
 cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7/arch/riscv/kernel$ vim syscall_table
# 0 "arch/riscv/kernel/syscall_table.c"
# 0 "<built-in>'
# 0 "<command-line>"
# 1 "././include/linux/compiler-version.h" 1
# 0 "<command-line>" 2
# 1 "././include/linux/kconfig.h" 1
# 1 "./include/generated/autoconf.h" 1
# 6 "././include/linux/kconfig.h" 2
# 0 "<command-line>" 2
 1 "././include/linux/compiler_types.h" 1
89 "././include/linux/compiler_types.h"
# 1 "./include/linux/compiler_attributes.h" 1
# 90 "././include/linux/compiler_types.h" 2
# 174 "././include/linux/compiler_types.h"
# 1 "./include/linux/compiler-gcc.h" 1
 175 "././include/linux/compiler_types.h" 2
191 "././include/linux/compiler_types.h"
struct ftrace_branch_data {
 const char *func;
const char *file;
 unsigned line;
  struct {
   unsigned long correct;
   unsigned long incorrect;
  struct {
   unsigned long miss;
   unsigned long hit;
  unsigned long miss_hit[2];
 syscall_table.i" 67923L, 3047627B
                                                                             1,1
                                                                                            Тор
```

#### 直接通过vim查看

```
cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7/arch$ cd x86
cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7/arch/x86$ cd entry
cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7/arch/x86/entry$ cd syscalls
cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7/arch/x86/entry/syscalls$ ls
Makefile syscall_32.tbl syscall_64.tbl
cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7/arch/x86/entry/syscalls$ vim syscall
_32.tbl
```

```
# SPDX-License-Identifier: GPL-2.0 WITH Linux-syscall-note
 32-bit system call numbers and entry vectors
# The format is:
 <number> <abi> <name> <entry point> [<compat entry point> [noreturn]]
 IA32_EMULATION is defined, and expect struct pt_regs *regs as their only
 parameter.
 The abi is always "i386" for this file.
        i386
                restart_syscall
                                        sys_restart_syscall
        i386
                exit
                                        sys_exit
        noreturn
        i386
                fork
                                        sys_fork
        i386
                read
                                        sys_read
                write
        i386
                                        sys_write
       i386
                                        sys_open
                                                                         compat_sys_open
               open
       i386
               close
                                        sys_close
       i386
                waitpid
                                        sys_waitpid
       i386
                                        sys_creat
                creat
                                        sys_link
       i386
                link
        i386
                unlink
                                        sys_unlink
11
       i386
                                        sys_execve
               execve
                                                                         compat_sys_exec
ve
12
       i386
                chdir
                                        sys_chdir
13
       i386
                time
                                        sys_time32
14
                                        sys_mknod
       i386
                mknod
                                        sys_chmod
15
       i386
                chmod
16
        i386
                lchown
                                        sys_lchown16
17
        i386
                break
18
        i386
               oldstat
                                        sys_stat
'syscall 32.tbl" 470L, 18509B
                                                                      1,1
                                                                                     Тор
```

#### 4. x86\_64

cjw@cjw-virtual-machine:~/Downloads/linux-6.11-rc7/arch/x86/entry/syscalls\$ vim syscall 64.thl

```
SPDX-License-Identifier: GPL-2.0 WITH Linux-syscall-note
# The format is:
  <number> <abi> <name> <entry point> [<compat entry point> [noreturn]]
0
        common read
                                          sys read
        common write
                                          sys_write
        common open
                                          sys_open
                                          sys_close
       common close
       common stat
                                          sys_newstat
       common fstat
                                          sys_newfstat
       common lstat
                                          sys_newlstat
       common poll
                                          sys_poll
       common
                 lseek
                                          sys_lseek
       common mmap
                                          sys_mmap
      common mprotect
10
                                         sys_mprotect
      common munmap
                                         sys_munmap
    common brk
64 rt_sigaction
common rt_sigprocmask
64 rt_sigreturn
64 ioctl
common pread64
common pwrite64
                                         sys_brk
13
                                        sys_rt_sigaction
sys_rt_sigprocmask
sys_rt_sigreturn
14
16
                                         sys_ioctl
17
                                         sys pread64
18
                                         sys_pwrite64
      64
19
              readv
                                         sys_readv
20
                writev
                                          sys_writev
       common access
                                          sys_access
22
        common pipe
                                          sys_pipe
       common select
                                          sys_select
23
        common sched yield
24
                                          sys_sched_yield
"syscall_64.tbl" 433L, 15472B
                                                                          1,1
                                                                                         Тор
```

同样直接通过vim查看

# 7.阐述什么是 ELF 文件? 尝试使用 readelf 和 objdump 来查看 ELF 文件,并给出解释和截图。

ELF文件是一种二进制标准文件格式,包含了程序的可执行代码,数据,符号表,重定位信息和其他程序执行相关的元数据,用于表示可执行文件,共享库,共享文件等。

使用了上次的hello.c文件, 生成可执行文件后readelf:

```
cjw@cjw-virtual-machine:~/code$ ls
hello hello.c
cjw@cjw-virtual-machine:~/code$ readelf -a hello
ELF Header:
 Magic: 7f 45 4c 46 02 01 01 00 00 00 00 00 00 00 00 00
                                    ELF64
 Class:
                                    2's complement, little endian
 Data:
 Version:
                                    1 (current)
 OS/ABI:
                                    UNIX - System V
 ABI Version:
 Type:
                                    DYN (Position-Independent Executable file)
 Machine:
                                    RISC-V
 Version:
                                    0x1
 Entry point address:
                                    0x5b0
 Start of program headers:
                                   64 (bytes into file)
 Start of section headers:
                                   6680 (bytes into file)
 Flags:
                                    0x5, RVC, double-float ABI
 Size of this header:
                                   64 (bytes)
 Size of program headers:
                                   56 (bytes)
 Number of program headers:
                                   10
 Size of section headers:
                                    64 (bytes)
 Number of section headers:
                                    28
 Section header string table index: 27
```

#### 使用objdump:

```
cjw@cjw-virtual-machine:~/code$ objdump -s hello
hello:
          file format elf64-little
Contents of section .interp:
0270 2f6c6962 2f6c642d 6c696e75 782d7269 /lib/ld-linux-ri
 0280 73637636 342d6c70 3634642e 736f2e31 scv64-lp64d.so.1
0290 00
Contents of section .note.gnu.build-id:
 0294 04000000 14000000 03000000 474e5500
                                        02a4 78de870d d36e18c7 2d16e97a 6420add4 x....n..-..zd ..
02b4 e4e6ede0
Contents of section .note.ABI-tag:
 02b8 04000000 10000000 01000000 474e5500
                                       02c8 00000000 04000000 0f000000 00000000
Contents of section .gnu.hash:
 02d8 02000000 07000000 01000000 06000000
                                        . . . . . . . . . . . . . . . .
02e8 00000000 00040020 07000000 00000000
                                        . . . . . . . . . . . . . . . . .
02f8 6b7f9a7c
                                        k..|
Contents of section .dynsym:
```

• 运行一个 ELF 文件,然后通过 cat /proc/PID/maps 来给出其内存布局并 截图。

为了使进程一直存在,在代码末尾添加循环,使之不结束,另一个窗口查看PID,并获取maps文件内容查看memory layout。

```
home > cjw > code > C hello.c > ( main()

1  #include<stdio.h>
2  int main()

3  {

4     int a=5;
    printf("%d",a*3);

6     while(1);

7     return 0;

8  }

9
10
```

cjw@cjw-virtual-machine:~/code\$ riscv64-linux-gnu-gcc -o hello hello.c

```
cjw@cjw-virtual-machine:~/code$ ./hello
```

#### 这时另开一个终端

```
cjw@cjw-virtual-machine:~/code$ pgrep hello
11772
cjw@cjw-virtual-machine:~/code$ cat /proc/11772/maps
5afb4de99000-5afb4de9a000 r--p 00000000 08:03 2671564
                                                                          /home/c
jw/code/hello
5afb4de9a000-5afb4de9b000 r-xp 00001000 08:03 2671564
                                                                          /home/c
jw/code/hello
5afb4de9b000-5afb4de9c000 r--p 00002000 08:03 2671564
                                                                          /home/c
jw/code/hello
5afb4de9c000-5afb4de9d000 r--p 00002000 08:03 2671564
                                                                          /home/c
jw/code/hello
5afb4de9d000-5afb4de9e000 rw-p 00003000 08:03 2671564
                                                                          /home/c
jw/code/hello
5afb4e9d4000-5afb4e9f5000 rw-p 00000000 00:00 0
                                                                          [heap]
74420dc00000-74420dc28000 r--p 00000000 08:03 2934062
                                                                          /usr/li
b/x86 64-linux-gnu/libc.so.6
74420dc28000-74420ddb0000 r-xp 00028000 08:03 2934062
                                                                          /usr/li
b/x86 64-linux-gnu/libc.so.6
74420ddb0000-74420ddff000 r--p 001b0000 08:03 2934062
                                                                          /usr/li
b/x86_64-linux-gnu/libc.so.6
74420ddff000-74420de03000 r--p 001fe000 08:03 2934062
                                                                          /usr/li
b/x86 64-linux-gnu/libc.so.6
74420de03000-74420de05000 rw-p 00202000 08:03 2934062
                                                                          /usr/li
b/x86_64-linux-gnu/libc.so.6
```


```
74420ddff000-74420de03000 r--p 001fe000 08:03 2934062
b/x86_64-linux-gnu/libc.so.6
74420de03000-74420de05000 rw-p 00202000 08:03 2934062
                                                                          /usr/li
b/x86_64-linux-gnu/libc.so.6
74420de05000-74420de12000 rw-p 00000000 00:00 0
74420de39000-74420de3c000 rw-p 00000000 00:00 0
74420de4c000-74420de4e000 rw-p 00000000 00:00 0
74420de4e000-74420de4f000 r--p 00000000 08:03 2934059
                                                                          /usr/li
b/x86 64-linux-gnu/ld-linux-x86-64.so.2
                                                                          /usr/li
74420de4f000-74420de7a000 r-xp 00001000 08:03 2934059
b/x86_64-linux-gnu/ld-linux-x86-64.so.2
74420de7a000-74420de84000 r--p 0002c000 08:03 2934059
                                                                          /usr/li
b/x86_64-linux-gnu/ld-linux-x86-64.so.2
74420de84000-74420de86000 r--p 00036000 08:03 2934059
                                                                          /usr/li
b/x86_64-linux-gnu/ld-linux-x86-64.so.2
                                                                          /usr/li
74420de86000-74420de88000 rw-p 00038000 08:03 2934059
b/x86 64-linux-gnu/ld-linux-x86-64.so.2
7ffd43b15000-7ffd43b36000 rw-p 00000000 00:00 0
                                                                          [stack]
7ffd43b41000-7ffd43b45000 r--p 00000000 00:00 0
                                                                          [vvar]
7ffd43b45000-7ffd43b47000 r-xp 00000000 00:00 0
                                                                          [vdso]
fffffffff600000-ffffffffff601000 --xp 00000000 00:00 0
                                                                          [vsysca
111
```

#### 可以看到:

可执行文件hello被映射到地址范围5afb4de99000-5afb4de9a000,可读客执行,摆阔代码和只读数据 共享库libc.so.6被映射到范围74420dc0000-74420ddb0000,包括可读,可写和可执行段,这是c标准库。

还有一些其他映射,比如动态链接器ld-linux-x86-64.so.2,栈区stack,以及内核相关的映射vvar和vdso。

### 8.在我们使用 make run 时,OpenSBI 会产生如下输出:



• 通过查看 <u>RISC-V Privileged Spec</u> 中的 medeleg 和 mideleg 部分,解释 上面 MIDELEG 和 MEDELEG 值的含义。

Boot HART ID : 0 Boot HART Domain : root Boot HART Priv Version : v1.12 Boot HART Base ISA : rv64imafdch Boot HART ISA Extensions : time,sstc Boot HART PMP Count : 16 Boot HART PMP Granularity : 4 Boot HART PMP Address Bits: 54 Boot HART MHPM Count : 16 Boot HART MIDELEG : 0x000000000001666 : 0x0000000000f0b509 Boot HART MEDELEG 2024 ZJU Operating System

#### 3.1.8 Machine Trap Delegation Registers (medeleg and mideleg)

By default, all traps at any privilege level are handled in machine mode, though a machine-mode handler can redirect traps back to the appropriate level with the MRET instruction (Section 3.3.2). To increase performance, implementations can provide individual read/write bits within medeleg and mideleg to indicate that certain exceptions and interrupts should be processed directly by a lower privilege level. The machine exception delegation register (medeleg) and machine interrupt delegation register (mideleg) are MXLEN-bit read/write registers.

In systems with S-mode, the medeleg and mideleg registers must exist, and setting a bit in medeleg or mideleg will delegate the corresponding trap, when occurring in S-mode or U-mode, to the S-mode trap handler. In systems without S-mode, the medeleg and mideleg registers should not exist.

In versions 1.9.1 and earlier, these registers existed but were hardwired to zero in M-mode only, or M/U without N systems. There is no reason to require they return zero in those cases, as the misa register indicates whether they exist.

When a trap is delegated to S-mode, the scause register is written with the trap cause; the sepc register is written with the virtual address of the instruction that took the trap; the stval register is written with an exception-specific datum; the SPP field of mstatus is written with the active privilege mode at the time of the trap; the SPIE field of mstatus is written with the value of the SIE field at the time of the trap; and the SIE field of mstatus is cleared. The mcause, mepc, and mtval registers and the MPP and MPIE fields of mstatus are not written.

一般来说,异常和中断都在M mode下处理,即使是在S mode下的异常和中断也是在M mode处理。 medeleg和mideleg两个寄存器允许系统将部分异常和中断委托给更低特权级别的处理器模式来处理, 而不是强制性地在M mode下处理。通过这种机制,可以让 S mode 处理某些异常和中断,而不需要每次都返回 M mode,这样可以提高操作系统的效率。

本次MIDELEG值为0x000000000001666(二进制为0001011001100110),被委托的中断包括:监督软件中断(bit1设置为1),监督定时器中断(bit5设置为1),监督外部中断(bit9设置为1)。