Transfer Settings & Layout

Export a settings file

Open Settings, then Settings & Layout Backup. Choose Export Settings & Layout and save the JSON file somewhere you can find it. Move that file to the other device by cable, local sharing, or a storage service you choose.

Preview and import

On the other device, open Settings & Layout Backup and choose Import Settings & Layout. Select the JSON file. Review the categories, uncheck any you want to keep as they are, and choose Import selected settings. Studio reopens with the selected preferences. Cancel leaves your settings as they were.

What travels with the file

Section order, collapsed sections, favorite sections and tools, recent tools, panel visibility, accessibility, Single or Dual Chart, safe-copy defaults, phone toolbar preferences, saved lettering styles, and favorites for Studio's built-in crochet references.

Back up projects separately

The settings JSON contains no charts, photos, notes, layers, progress, or Recycle Bin records. Use Studio's project ZIP backup for those. Existing project ZIPs still work, and full project ZIPs can still optionally include workspace preferences.

Use it offline

Export and import work offline. A phone toolbar preference applies on phone layouts. Tablet menus and safe-area spacing still adapt to the destination device. Device update choices, temporary files, and local diagnostics stay on their original device.

Start and edit a chart

Create or open a project

Open File > New Project, enter a name and the number of columns and rows, then create the chart. Open Project reveals the existing library. Studio saves edits locally as you work.

Read and edit the grid

Row 1 is at the bottom. Column 1 is at the left. Use Select to locate a stitch, choose a yarn color and use Paint to change it. Erase restores the base background or removes a stitch from the selected text layer, depending on the brush target shown beside the chart.

Import a reference image

Open Tools > Image to Chart or search for Import photo. Choose an image, review the crop and conversion settings, then preview the result. Apply only after checking the chart. Use a separate project copy when you want to keep the original.

Add or change lettering

In Text to Chart, choose horizontal or upright vertical lettering, height, width and spacing. Lock proportions links the dimensions. Preview and apply to create an editable layer. Select that layer and choose Edit layer to revise the text.

Paint editable lettering

Select a text layer and turn on Text layer tools. Check that the brush target names the intended layer. Layer Lock protects that layer. Pattern Lock protects the entire chart. Flatten selected merges the stitches into the base chart and removes separate layer editability.

Crochet and change dimensions

Follow row colors

Open Crochet View and expand Row Color Instructions. Select a stitch or use Previous row and Next row. The panel shows the yarn name, symbol, run size and next change using your chart direction. The instructions describe colorwork. Follow your pattern for stitch type and turning instructions.

Mark progress

Use Mark stitch, Mark row, or complete a color run in Crochet View. Undo and Redo are available for progress. The row panel can collapse while you work.

Resize from a chart edge

In Chart Settings, set Columns and Rows, then choose Add/remove rows at and Add/remove columns at. Apply dimensions shows the exact changes and a diagram. Gray stays, red is removed, and blue is added blank. Review the warning before confirming.

Insert or delete in the middle

Select a stitch and open Rows & columns. Choose an action and review the affected line. Inserted stitches start incomplete. Existing artwork and completion shift to their new coordinates. Notes on a removed line move to the nearest surviving position.

Keep an original

Leave the safe-copy option enabled for a saved copy before major edits. Undo or Redo reverses or repeats the current change. After a dimension change, Studio keeps the reference photo and hides its overlay so you can review the alignment.

Arrange and protect your workspace

Find a Tool

Use the top bar or Ctrl+K. Try Add a row, Erase a letter, or Save all my projects. A result takes you to the original control. Star frequently used tools and find them in Favorite Tools. Recently Used lists selected results.

Make Settings easier to scan

Use Jump to Section or a Favorite Settings shortcut. Select a heading to expand or collapse it. Customize Layout lets you move whole sections using the grip or the up and down buttons. Choose Done when finished. Reset to Default restores the original order.

Free up chart space

Use View > Show / Hide Projects or the Hide Projects button in the Projects panel. On smaller screens the panel opens as a drawer. Find a Tool and the File menu can bring it back when you need it.

Back up and restore

Use File > Back Up All Projects and save the ZIP outside Studio. In Settings, enable Include workspace preferences in full backups when you want to transfer layout choices. Restore Backup adds project copies. Choose whether to use the backed-up preferences or keep the destination device's layout.

Work offline

The installed app supports chart editing and ZIP backups offline. For the website, open Studio online first so its files can be cached. Update checks and online reference searches need connectivity. The following pages preserve the earlier illustrated guide. Use these quick-start pages for current controls.

DORETTE CROCHET STUDIO

VERSION 1.8.0

RELIABILITY / SPEED / POLISH

SAFE MULTI-TAB EDITING

Only one local browser tab writes at a time.

FASTER IMAGE OPERATIONS

Conversion and grid analysis can run off the UI thread.

SAFE PROJECT CHANGES

Major transformations work on copies by default.

CONFIDENT RELEASES

Color checks, screenshot regression tests and offline-asset audits.

Includes the earlier 36-page complete Studio reference.

No cloud backup. No online accounts. User projects remain local.

New features and quick navigation

Tap a chapter to jump to its page.

Editing ownership and browser storage 3

Background jobs, cancellation and large charts 4

Safe copies, export previews and consistency 5

Find tools, accessibility and tablet workflow 6

Testing: image, offline, visual and golden fixtures 7

Release checklist and safe installation 8

Complete v1.7.2 user guide (earlier features) 9

Important: start every website update by downloading Back up all.

App ZIP archives are program files, not project backups. Never use the Restore backup control with an application ZIP.

1. Ownership and storage monitoring

Protect the same project when multiple Studio tabs are open

First tab: editing enabled

The first browser tab owns a local editing lock. Its saves continue normally. A second tab can browse but cannot write or silently overwrite newer work.

Second tab: read-only warning

The top banner explains why editing is disabled. Close the editing tab, then choose Retry editing. The Studio reopens fresh data after ownership changes.

Browser storage capacity

Open Studio health & updates and choose Check storage usage. The Studio shows the browser estimate, quota and approximate local project sizes. A warning appears near 80% usage.

A storage warning is not a backup.

Keep a private Back up all project ZIP in Google Drive or another location you control. Cloud synchronization and automated recovery have not been added.

2. Background work and large charts

Photo conversion and grid analysis run without unnecessary waiting

A

Import and crop

Select the source image and trim unnecessary surroundings.

B

Start preview

Preview stitches, detect a grid, or inspect tiny color islands.

C

Processing indicator

The Studio shows current progress and a Cancel button.

D

Accept or cancel

Only Apply chart or Apply cleanup commits a design change.

Large chart rendering

Small-screen chart colors use a compact raster; zoomed regions use bounded stitch-tile caches. This reduces rendering overhead without changing stitch colors.

3. Safer editing and export review

Create a copy for major edits

The default setting under Chart settings makes a separate project before mirroring, resizing, replacing colors, simplifying stitches, and other major transformations. Turn it off only when intentional.

Preview the finished chart before export

Choose Preview export & verify colors in the printable PDF section. The preview displays effective stitches, including visible layers, and checks sampled pixel colors against the saved chart model.

PDF, PNG and SVG do not share identical page layouts

All exports use the effective chart colors. Printable PDFs add paper margins, sections, numbering and legends. The color checker verifies the model, not byte-for-byte visual parity.

Before large changes

Make a private project backup, keep Safe edits enabled, inspect the new copy, then confirm that project ZIP restore and PDF export still reflect your intended pattern.

4. Find tools and navigate accessibly


Use the Studio more quickly

Find a tool (Ctrl+K)

Search for grayscale, resize, layers, written PDF, project backup, or other controls. Select a result to move to the relevant tool. Escape closes the dialog.

Create / Edit / Crochet workspaces

The existing three workspaces group related controls. Beginner and Advanced modes, number sizing, color cues, and high-contrast grids remain available.



Example: v1.8.0 desktop toolbar with Find a tool.

5. Release tests and known limitations

What is checked before packaging?

Functional browser

Projects, editing, safe copy, save failure/retry, conversion cancel

Golden reference charts

10x10, 79x117, 120x165, 200x300, irregular 23x17

Visual regression

Desktop, tablet and phone screenshots compared to baselines

Offline asset audit

Script URLs and same-release files verified in the cached shell

Work isolation

Two-tab ownership tests using a controlled lock simulation

Export and backup

PDF worker, PNG/SVG signatures, project ZIP v1 restore

Still requires physical-device verification

Samsung S Pen/palm rejection, installed PWA behavior, service-worker activation, real offline use, and storage behavior in a genuine hosted browser remain essential on-device checks.

6. Safe installation and continued testing

Install only after testing with a practice chart

1. In the currently installed Studio, choose Back up all and save the PROJECT ZIP privately.
2. Download v1.8.0 GitHub Update ZIP and extract it on the computer.
3. Upload the extracted CONTENTS into the existing repository root, replacing matching application files.
4. Commit, wait for GitHub Pages to deploy, then open the SAME website and browser profile.
5. Confirm badge v1.8.0; test a small chart, copy, ZIP restore, PDF export and normal reload.
6. On the tablet, test touch/S Pen, single/dual charts, portrait/landscape, and offline opening.

Never clear browser data, change the GitHub Pages address, or uninstall the PWA to update.

Hands-free voice features and automated cloud backup/recovery remain postponed. This release is local-first and does not send charts to an external service.

DORETTE

CROCHET STUDIO

VERSION 1.7.0

THE RELIABILITY & POLISH UPDATE

Safe saves	Verified database writes and persistent failure warnings
Project checks	Non-destructive integrity checks and raw recovery export
Design history	Undo/Redo separate from crochet completion progress
Fast PDFs	Off-thread generation where supported
Safer updates	Finish saving before the app shell refreshes
Diagnostics	Privacy-safe report for troubleshooting

Includes the complete 30-page v1.6 Studio reference.

No cloud account. No automatic cloud backup. Your local projects stay local.

CONTENTS / QUICK NAVIGATION

Using the v1.7 reliability tools

Tap a chapter entry in this PDF to open it.

Save statuses and project integrity 3

Undo, Redo and crochet progress 4

Updates, performance and export checks 5

Diagnostics, tablet checks and limitations 6

Complete v1.6 Studio reference starts here 7

BEFORE EVERY UPGRADE

Use Back up all in the current Studio and keep the project ZIP privately.

Never clear browser/site data or uninstall the existing app to refresh it.

Install app files only after checking the release and your existing projects.

CONFIRMED SAVE STATUS & PROJECT HEALTH

A save is not complete until storage confirms it

Unsaved changes

The latest edit is queued.

Keep this tab open.

Saving...

The browser database is writing.

A confirmation is still pending.

Saved at 5:32 PM

The database transaction finished.

Time is based on your device.

Save failed

A persistent warning stays visible.

Use Retry saving; preserve a ZIP.

Project integrity is checked before saving and when the Studio opens.

An invalid stored project is kept unchanged, not automatically repaired.

Use Studio health > Run project check, then export raw records if necessary.

Raw recovery exports are NOT ordinary project-backup ZIPs.

Do not use them with the in-app Restore command.

Your regular Back up all ZIP remains the recommended portable backup.

EDIT HISTORY & CROCHET PROGRESS

Two independent kinds of history

Design Undo / Redo

Changes to yarn colors and design tools are tracked in the Design history panel.

Example: recolor a stitch, move text, or resize a layer; Undo restores the previous design.

Crochet progress Undo

Finishing stitches is not a design edit. Use Undo progress for recent stitch and row completion actions.

The design Undo preserves progress when chart dimensions are unchanged.

Saved design milestones remain the long-term history.

The current-session Undo stack is not a substitute for a project ZIP.

Changing chart dimensions may require remapping crochet progress.

Check stitch counts after resizing, undoing a resize, or restoring a milestone.

Tip: On the laptop, Ctrl+Z / Ctrl+Shift+Z control design Undo and Redo.

RELIABLE APP UPDATES & FASTER EXPORTS

A safer path to the next Studio version

1

Open a project

Continue using the installed version

2

New update is ready

A banner appears when a new app shell is waiting

3

Confirm current save

Wait for the latest database write to finish

4

Choose Save and update

The new worker takes control and the page reloads

Large printable PDFs use a background worker where supported.

The Studio keeps a compatible local fallback for unsupported environments.

Versioned application files are cached together for offline reuse.

DIAGNOSTICS & DEVICE CHECKLIST

How to verify the update on Dorette's device

1. Open a practice project. Confirm the version badge says v1.7.0.

2. Edit one stitch. Watch Unsaved > Saving > Saved at a time.

3. Run project integrity check and read the result.

4. Mark a crochet stitch, then Undo a separate design edit.

5. Export a small PDF, PNG, SVG and written-pattern PDF.

6. Back up the practice project and restore it as a new copy.

7. Disconnect temporarily: verify the installed app opens offline.

8. Test the S Pen, pinch zoom, palm contact and screen-awake option.

Copy diagnostic report excludes personal pattern content.

It includes version, storage status, device capabilities and timings.


Important: physical device and hosted offline tests require your tablet.

DORETTE

CROCHET STUDIO

Version 1.6.0

A practical guide to design milestones, stitch notes, accessible chart viewing, measurement, grid-snapped shapes, and simulated crochet texture.



FOR DORETTE | NOVEMBER 2026

New in v1.6.0 + the complete v1.5 tool reference

Contents and navigation

NEW IN VERSION 1.6.0

Safe upgrade and practice test 3

Beginner view and visibility se... 4

Save and compare design versions 5

Attach stitch, row and section ... 6

Measure and draw grid shapes 7

Simulated finished-stitch preview 8

Release testing and boundaries 9

COMPLETE STUDIO REFERENCE

Cover 10

Contents 11

Getting started and safeguardin... 12

Explore the workspace 13

Read the numbered grid 14

Detect an imported crochet grid 15

Straighten photos and remove ba... 16

Simplify photos to fewer colors 17

Text, symbols and favorite styles 18

Edit, drag and resize layers 19

Expand, crop or scale the chart 20

Crochet technique presets 21

Work on large chart sections 22

Analyze yarn-color changes 23

Pattern quality and cleanup 24

Personal yarn colors and size 25

Project gallery, templates and ... 26

Export as PDF, PNG or SVG 27

Samsung tablet and screen-awake... 28

Backups, compatibility and limi... 29

Real-device testing checklist 30

Tap a chapter to jump to it. The PDF sidebar also includes chapter bookmarks.

Start safely: protect existing work

1 Back up projects in the CURRENT Studio

On your existing GitHub Pages website, choose Back up all and save the PROJECT backup ZIP privately. Do not confuse the project backup with an application source-code ZIP.

2 Install the GitHub update

Extract v1.6.0-GitHub-Update.zip, upload its CONTENTS to the ROOT of the existing Dorette-Crochet-Studio repository, then commit. Do not upload the enclosing folder.

3 Refresh without erasing browser storage

Open the same GitHub Pages address in the same browser and profile. Confirm the v1.6.0 badge. Never clear site data or uninstall the installed app as a troubleshooting step.

4 Practice first

Use a new 10 x 10 or 25 x 25 project to test versions, notes, shapes, Undo, guide buttons, chart PDF, and ZIP restore before modifying a cherished design.

What is and is not synchronized

Projects and their design versions/notes stay in this browser and are included in project ZIP backups. Separate yarn libraries, motifs, and text favorites are device-local and do not sync automatically.


Original website

mythrilman86.github.io/Dorette-Crochet-Studio/

Append ?v=160 to check the new deployment online.

Beginner mode and visual accessibility

Use the display bar above the chart



Beginner and Advanced

Beginner hides the more complex editing panels and tools but leaves project data intact. Switch back to Advanced when you need layers, quality analysis, shapes or version history.

High-contrast and color cues


High-contrast grid darkens the grid outlines. Yarn shape cues overlays distinct marks on colored stitch squares when they are large enough to draw. Emphasize yarn letters displays yarn symbols at smaller zoom levels when legible.

Bigger number labels and rulers

Set Number size to Standard, Large or Extra large. The ruler switch is in Stitch Ruler & Measurement and places tick marks along the chart margins every five squares.

Tip: if two yarn shades look similar, enable both high contrast and yarn shape cues. These are viewing aids; they do not change yarn colors or the exported chart.

Project version history



SAVE

Give the current design a meaningful name, then Save design version.

COMPARE

Choose an earlier version to see side-by-side thumbnails and a changed-stitch count.


RESTORE

Restore as copy creates a new project. Your current one stays untouched.

Why this is useful

Save a design before changing wording, resizing motifs or trying new colors. The Studio stores up to eight named versions per project. If there are more, the oldest named milestone is replaced. Versions are included in project-backup ZIPs.

Stitch, row and section notes



ATTACH

Select a square or working section, choose the note scope, type a reminder, then tap Add reminder.

JUMP OR REMOVE


Tap a saved reminder to move the working chart to its stitch, row or section. Remove deletes that reminder.

ON THE CHART

Small orange indicators identify attached reminders. The note never changes the stitch color.

To print reminders, enable the extra checklist and project notes pages in Printable PDF Export. The PDF notes text has a length limit; keep your full notes in the project ZIP.

Measure stitches and draw shapes



SELECT AN AREA

Choose Select area, then drag across the working chart to establish two corners.

MEASURE

Click Measure selected area. The panel shows stitch columns, rows, totals, and approximate real dimensions if you entered a measured gauge.


DRAW A SHAPE

Choose straight line, outline/filled rectangle, ellipse or circle. Preview the orange cells. Select a yarn color and Apply shape. Undo is available.

Keep stitch placement precise

All shapes snap to the square stitch grid. Circles/ellipses are pixel-like approximations. Physical size depends on your swatch, yarn, crochet technique and tension.

Preview a crocheted appearance



1. Choose a stitch texture style.
2. Click Preview crocheted appearance.
3. Compare the chart and simulated texture.

Important limitation

The texture shows a repeatable visual suggestion of stitches. It does not model true fabric tension, stitch height, physical yarn fibers, hook size, drape, or finished garment shape. It never modifies chart cells.

Release testing and device checklist

- [ ] Create a small practice chart, then save and compare a named version.
- [ ] Add a stitch note, open it, remove it, and create a row reminder.
- [ ] Use Select area; preview and apply a line, rectangle, and circle.
- [ ] Confirm Undo removes a shape without changing an editable text layer.
- [ ] Measure 10 x 10 stitches using a real swatch and inspect the ruler.
- [ ] Switch Beginner / Advanced, high contrast, number size and yarn cues.
- [ ] Preview soft and detailed simulated crochet textures side by side.
- [ ] Export a chart PDF with extra notes; inspect the printed reminder.
- [ ] Back up and restore an updated project ZIP as a NEW project.
- [ ] Try pinch/zoom and stylus on the actual Samsung tablet.
- [ ] Open the installed Studio while online once, then check offline use.

Safety and compatibility

Database name/version, active-project key and the project-backup version remain unchanged. No background cloud synchronization or hands-free voice controls were added. Samsung S Pen behavior and offline installation require real-device checks.


The following appendix preserves the full v1.5 tool reference.

DORETTE CROCHET STUDIO

Create. Edit. Crochet.

Version 1.5.0

Illustrated guide to accurate crochet grids, editable layers, yarn planning, guided progress, pattern exports, and safe project backups.



Row 1 is always at the bottom. Every square represents one chart cell.

Contents

Select a chapter to jump directly to that page. Use the bookmark panel in your PDF reader for navigation.

03 Getting started and safeguarding projects

04 Explore the workspace

05 Read the numbered grid

06 Detect an imported crochet grid

07 Straighten photos and remove backgrounds

08 Simplify photos to fewer colors

09 Text, symbols and favorite styles

10 Edit, drag and resize layers

11 Expand, crop or scale the chart

12 Crochet technique presets

13 Work on large chart sections

14 Analyze yarn-color changes

15 Pattern quality and cleanup

16 Personal yarn colors and size

17 Project gallery, templates and duplicates

18 Export as PDF, PNG or SVG

19 Samsung tablet and screen-awake controls

20 Backups, compatibility and limitations

21 Real-device testing checklist

Getting started and safeguarding projects


- Open the published Dorette Crochet Studio URL in the browser profile where your projects already live. The v1.5.0 version badge confirms the code has updated.

- Before replacing GitHub files, use Back up all in the previous Studio and privately save that ZIP. Application ZIP files are not project backups.

- Projects use the same existing IndexedDB database and are saved on that device; downloading a ZIP does not upload or share the project.

- Restore project backups through the Studio Restore button. Restores create new project copies instead of overwriting originals.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Note: Some advanced features may depend on device or browser support.

Explore the workspace

- Use Create for images and lettering, Edit for painting and layered design, and Crochet for following a pattern.
- Switch Single or Dual charts. The left overview fits the whole design; the working chart lets you pan and zoom.
- Show/hide the Projects and Settings panels when you need more space. Chart split allocates width between the two charts on wider screens.
- Pin crochet controls to keep the progress dock visible; unpin it if you prefer it to scroll.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Note: Some advanced features may depend on device or browser support.

Read the numbered grid

- Every square is one crochet chart cell. Column 1 is at the LEFT and column numbers increase toward the RIGHT.
- Row 1 starts at the BOTTOM. Row numbers increase upward. This orientation is preserved in PDF exports.
- At an overview scale, only some row and column numbers appear for legibility; zoom in to inspect each boundary.
- The highlighted square, row and column appear in both views and share exactly the same project data.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Row 1 at bottom; column 1 at left

Note: Some advanced features may depend on device or browser support.

Detect an imported crochet grid


- Import an existing gridded image in Image to Chart; open Detect existing chart grid & clean photo background.

- Analyze visible source grid estimates the count of repeated dark grid lines. Results include an approximate line-regularity score.

- Compare detected numbers with the ORIGINAL squares, not line counts. Correct the Columns and Rows fields manually if necessary.

- The detector works best with high-contrast, unwarped grid images. Complex art, shadows, warped grids or missing borders may not detect reliably.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Verify 12 columns and 9 rows

Note: Some advanced features may depend on device or browser support.

Straighten photos and remove backgrounds

- If an imported photo is slightly rotated, use the rotation correction slider and Straighten source image; this rotates the reference image, not the saved stitch colors.
- Remove similar background from edges uses the colors at the four photo corners as a starting estimate, removing matching connected background.
- Choose Background tolerance carefully; high values can remove parts of a light-colored subject. Undo or reimport the source if the result is too aggressive.
- Always Preview stitches and inspect the full chart before applying converted colors.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Note: Some advanced features may depend on device or browser support.

Simplify photos to fewer colors


- Choose Grayscale conversion to reduce the chart to a limited number of black, white and gray yarns.

- The side-by-side 2 / 3 / 4 gray comparison displays the same source with different shade counts. Choose Preview on chart for a candidate.

- A limited palette can make crocheting simpler but may lose fine details. Preview both overall shapes and fine lettering at high zoom.

- Use the existing color-palette and Replace Everywhere tools when you need to merge a particular yarn shade.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Preview 2, 3 and 4 gray variations

Note: Some advanced features may depend on device or browser support.

Text, symbols and favorite styles


- Enter letters, words, numbers or symbols; choose a stitch-friendly style, letter height, spacing, wrapping, rotation and layout.

- Preview before Apply. Applying creates an editable text layer instead of permanently painting the base pattern.

- Select an area with Select area, then use Auto-fit or Center in selected area for precise placement.

- Save your preferred font/spacing/size combinations under Saved lettering style and reuse them in another project. The style library is stored on this device.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Note: Some advanced features may depend on device or browser support.

Edit, drag and resize layers


- Select an editable text or motif layer in the Layers list. It can be shown, hidden, locked, reordered, duplicated or flattened.

- Enable Drag or resize selected layer directly on the working chart. Drag inside the orange outline to move the layer.

- Drag the orange upper-right handle to resize on the stitch grid, or select an area and press Fit selected layer into chosen area.

- Resizing converts the artwork into a stitched shape. The original typeface metrics may no longer be editable after resizing; Undo or keep a duplicate layer.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Note: Some advanced features may depend on device or browser support.

Expand, crop or scale the chart


- In Chart settings, choose new column and row counts, then open Advanced canvas resize / crop.

- Expand / crop canvas maintains original stitch size. Choose center, left, right, top or bottom anchor to control where existing stitches land.

- Scale entire chart remaps all the stitch cells and editable layers using nearest-neighbor mapping; it changes visual proportions and can lose detail.

- Cropping removes cells outside the smaller grid. Make a project backup beforehand and review the result before further work.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Resize with care: expand != scale

Note: Some advanced features may depend on device or browser support.

Crochet technique presets


- Standard colorwork, tapestry colorwork and single-crochet graph presets use normal row-by-row chart progression.

- The Corner-to-corner (C2C) preset adds a separate diagonal chart-cell progress path and buttons for stepping backward or completing the next diagonal cell.

- C2C chart cells are NOT full instructions for C2C block construction, shaping, turning chains, increases or decreases. Follow a trustworthy technique pattern for those details.

- You can switch presets without changing the saved yarn-color grid.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



C2C chart-cell path moves diagonally

Note: Some advanced features may depend on device or browser support.

Work on large chart sections


- Choose 20, 25, 30 or 40-stitch sections. Each section specifies its absolute column and row range.

- Jump to section centers the working chart on the selected area. Complete section marks those chart cells finished without recoloring the yarn.

- Purple boundaries are shown on both chart views and numbered PDF detail pages.

- The PDF can include a section checklist. Large charts may have more sections than fit on its first checklist page; the Studio remains the complete section list.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Purple boundaries mark working sections

Note: Some advanced features may depend on device or browser support.

Analyze yarn-color changes

- Use Analyze yarn changes by row to review total horizontal color transitions and the rows with the most changes.
- The isolated-stitch suggestion highlights a limited set of cells whose color differs from both horizontal neighbors.
- The orange preview is a PROPOSAL, not proof of an error. Preserve highlights such as eyes, letters, outlines and deliberate accent stitches.
- Apply previewed suggestions changes only base chart cells. Undo restores the previous version.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Inspect isolated colors before simplifying

Note: Some advanced features may depend on device or browser support.

Pattern quality and cleanup

- Run the existing quality checker to see isolated islands, edge colors, empty rows and overall transitions.
- Use Inspect row to jump to color-heavy rows. Also zoom to problem areas and look at neighboring rows.
- Smart cleanup previews orange proposed fixes for isolated color patches. Protect important selected areas and apply only after reviewing the preview.
- Cleanups do not automatically change the intended technique, carried yarns, or construction methods.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Zoom to inspect possible problem stitches

Note: Some advanced features may depend on device or browser support.

Personal yarn colors and size


- Save regularly used yarn names, RGB colors and available inventory in the personal yarn library.

- Find closest saved yarn offers an approximate computer color-distance match. It is not a guarantee about brand, dye lot or how a real skein appears in daylight.

- Enter an actual crochet swatch to estimate project size and yarn amount. Generic counts alone cannot accurately predict yardage.

- Yarn and motif libraries are stored locally in that browser and are not automatically included with project backup ZIPs.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Note: Some advanced features may depend on device or browser support.

Project gallery, templates and duplicates

- Search your projects by name or category. Select the category filter or show favorites only to narrow the gallery.
- Use the star on a gallery item to favorite it. Use Duplicate current project to experiment safely with a separate copy.
- New-project templates offer square designs, blankets, border strips and initials, with editable dimensions in the Create form.
- Thumbnails are generated from the saved color cells and visible layers; they are not uploaded online.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Note: Some advanced features may depend on device or browser support.

Export as PDF, PNG or SVG


- Printable PDF exports the full chart, yarn legend, numbered stitch pages, and optional completed-stitch indicators and page overlap.

- Select Include section checklist & project notes PDF pages to append a checklist and the notes you typed in PDF Export.

- PNG provides a convenient raster picture. SVG is a vector image suitable for further resizing. Export sizes depend on your selected pixels-per-stitch scale.

- Use the project ZIP, not an image or printed PDF, if the recipient needs to continue editing the pattern and progress.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Note: Some advanced features may depend on device or browser support.

Samsung tablet and screen-awake controls

- On the Galaxy Tab, test single and dual layouts, zoom and finger gestures, and the S Pen before starting an important pattern.
- Pattern lock can prevent accidental paint changes during crochet. Stylus-only editing lets a pen paint while fingers navigate.
- Keep screen awake is optional and requests the browser Screen Wake Lock API while Crochet View is active. It may be unavailable or denied by device policies or power-saving mode.
- Switch out of Crochet View or turn the setting off when you do not need the display to stay awake.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Note: Some advanced features may depend on device or browser support.

Backups, compatibility and limitations


- Back up all projects before installing code updates. Do not clear browser storage, uninstall the PWA, or change the GitHub Pages site origin when you have unsynced projects.

- Version 1.5 keeps the existing dorette-crochet-studio IndexedDB database and version 1 ZIP project payload.

- Older projects can be restored into this version as separate copies. Versions older than 1.4 may not preserve new editable-layer metadata if a newer ZIP is restored into those old versions.

- The app remains offline-first/local; motif, yarn and favorite-lettering libraries do not automatically sync between devices.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Note: Some advanced features may depend on device or browser support.

Real-device testing checklist

- Test a fresh 10 x 10 practice chart first. Check paints, Undo, layers, row progress, diagonal chart cells, and section completion.
- Import a high-contrast gridded image. Check detected columns/rows manually, then preview grayscale and background-removal results.
- Export and restore a practice project ZIP. Verify layers, notes, category, technique and progress after restore.
- Generate chart PDFs, PNG and SVG files. On the physical Galaxy Tab, verify S Pen, touch mode, screen awake and installed-app offline reload.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Note: Some advanced features may depend on device or browser support.