

T2032 - RIIP - TP02 [pka] RIPv2 (ISP et NAT déjà configurés).pka

☐ Nom de Périphérique ou Commutateur

☐ Commande

☐ Valeur variable d'une commande

☐ Commentaires

PC1

Ip address : 192.168.1.1

Subnet Mask : 255.255.255.128

Default Gateway : 192.168.1.126

PC130

Ip address : 192.168.1.130

Subnet Mask : 255.255.255.192

Default Gateway : 192.168.1.190

PC-01

Ip address : 10.1.1.1

Subnet Mask : 255.255.255.0

Default Gateway : 10.1.1.254

PC-02

Ip address : 10.1.2.1

Subnet Mask : 255.255.255.0

Default Gateway : 10.1.2.254

S1

enable

conf t

enable secret admin

hostname S1

ip default-gateway 192.168.1.126

interface vlan1

ip addr 192.168.1.104 255.255.255.128

no shut

exit

line vty 0 15

password cisco

login

exit

service password-encryption

S2

enable

conf t

enable secret admin

hostname S2

ip default-gateway 192.168.1.190

interface vlan1

ip addr 192.168.1.182 255.255.255.192

no shut

exit

line vty 0 15

password cisco

login

exit

service password-encryption

SW-01

enable

conf t

hostname SW-01

ip default-gateway 10.1.1.254

ip ssh version 2

ip domain-name formation.lab

username admin secret cisco

crypto key generate rsa

1024

line vty 0 15

login local

transport input ssh

exit

interface vlan1

```
ip addr 10.1.1.201 255.255.255.0
no shut

exit
```

SW-02

```
enable

conf t

hostname SW-02

ip default-gateway 10.1.2.254

ip ssh version 2

ip domain-name formation.lab

username admin secret cisco

crypto key generate rsa

    1024
```

```
line vty 0 15

login local

transport input ssh

exit
```

```
interface vlan1

ip addr 10.1.2.202 255.255.255.0
no shut

exit
```

SW-12

Pas configuration pour celui-ci

R1

enable

conf t

hostname R1

enable secret admin

line vty 0 15

password cisco

login

exit

int G0/0/0

ip addr 192.168.1.126 255.255.255.128

no shut

exit

int S0/2/0

ip addr 192.168.1.254 255.255.255.252

no shut

exit

router rip

version 2

network 192.168.1.0

passive-interface G0/0/0

exit

RT-01

enable

conf t

hostname RT-01

ip ssh version 2

ip domain-name formation.lab

username admin secret cisco

crypto key generate rsa

1024

line vty 0 15

login local

transport input ssh

exit

int G0/0/0

ip addr 10.1.1.254 255.255.255.0

no shut

exit

int G0/0/1

ip addr 10.1.0.1 255.255.255.0

no shut

exit

```
int S0/2/0
ip addr 200.0.0.100 255.255.255.0
no shut
exit
```

```
router rip
version 2
default information originate
network 200.0.0.0
network 10.1.0.0
network 10.1.1.0
passive-interface G0/0/0
exit
```

```
ip route 0.0.0.0 0.0.0.0 200.0.0.200
```

RT-02

```
enable
conf t
hostname RT-02
ip ssh version 2
ip domain-name formation.lab
username admin secret cisco
crypto key generate rsa
```

1024

line vty 0 15

login local

transport input ssh

exit

int G0/0/0

ip addr 10.1.2.254 255.255.255.0

no shut

exit

int G0/0/1

ip addr 10.1.0.2 255.255.255.248

no shut

exit

router rip

version 2

network 10.1.0.0

network 10.1.2.0

passive-interface G0/0/0

exit

RT-03

enable

conf t

hostname RT-03

ip ssh version 2

ip domain-name formation.lab

username admin secret cisco

crypto key generate rsa

1024

line vty 0 15

login local

transport input ssh

exit

int G0/0/0

ip addr 192.168.1.190 255.255.255.192

no shut

exit

int G0/0/1

ip addr 10.1.0.3 255.255.255.248

no shut

exit

int S0/2/0

ip addr 192.168.1.254 255.255.255.252 ici l'ip n'est pas donne car c'est un reseau de /30 donc il y a que 2 ip disponible, comme R1 a 192.168.1.253 celui-ci aura automatique l'autre ip dispo qui est 192.168.1.254

no shut

exit

router rip

version 2

network 192.168.1.0

network 10.1.0.0

passive-interface G0/0/0

exit

default-information originate : commande RIP qui dit au routeur « je connais une route par défaut vers Internet, diffuse-la aux autres routeurs ».

- À mettre **seulement sur le routeur connecté à l'ISP**.
- Les autres routeurs reçoivent la route par défaut automatiquement et savent où envoyer le trafic inconnu.

The Ghostwriter 25