How to setup local database for store attachments

- 1. Login with your local super-admin (postgres user) on PostgreSQL server (via PgAdmin or your favorite tool)
- 2. Execute sql script from below (the script is available also on project inside folder attachments-db-setup/createdb.sql

```
3. 1 -- create user --
2 CREATE ROLE "num-attachment" WITH LOGIN PASSWORD '<password>';
3
4 -- create database --
5 CREATE DATABASE "num-attachment" WITH OWNER = 'num-attachment' ENCODING = 'UTF8' CONNECTION LIMIT = -1;
6 GRANT ALL PRIVILEGES ON DATABASE "num-attachment" TO "num-attachment";
7
8 \c num-attachment
9 CREATE SCHEMA IF NOT EXISTS num AUTHORIZATION "num-attachment";
10 GRANT ALL PRIVILEGES ON SCHEMA num TO "num-attachment";
11 GRANT INSERT, SELECT, UPDATE, DELETE, TRUNCATE, REFERENCES ON ALL TABLES IN SCHEMA num TO "num-attachment";
12 GRANT EXECUTE ON ALL FUNCTIONS IN SCHEMA num TO "num-attachment";
13 GRANT ALL PRIVILEGES ON ALL SEQUENCES IN SCHEMA num TO "num-attachment";
```

4. Update your local spring profile (application-local.yaml) with the right values for numportal-attachment configuration

```
spring:
 config:
   activate:
     on-profile: local
 datasource:
   hikari:
     data-source-properties:
       stringtype: unspecified
   numportal:
     url: jdbc:postgresql://localhost:5432/numportal?currentSchema=num
     driver-class-name: org.postgresql.Driver
     username: postgres
     password
   numportal-attachment:
     url: jdbc:postgresql://localhost:5432/num-attachment?currentSchema=num
     driver-class-name: org.postgresql.Driver
     username: num-attachment
     password:
 # migration done via configuration class
 flyway:
   enabled: false
```

- 5. The connection to this database is based on flag num.enableAttachmentDatabase, so the connection to this database is setup only if the flag is true → this means that also all components that are depending on this database connection are initialized only when this flag is set to true (controller, service, repository : @ConditionalOnProperty(prefix = "num", name = "enableAttachmentDatabase", havingValue = "true")).
- 6. Flyway changes for this attachment database must be placed under folder db/migration/num-portal-attachment