Basic C Types

Integer Types

Integer types in C represent whole numbers. There are several different variants of integer types (for more information see 1 integer types (for more inform

Туре	Size (minimum)	Range (minimum)
char	8 bits	signed: -128 to 127
		unsigned: 0 to 255
short	16 bits	signed: -32768 to 32767
unsigned short		unsigned: 0 to 65535
int	32 bits	signed: -2147483648 to 2147483647
unsigned int		unsigned: 0 to 4294967295
long	32 bits	signed: -2147483648 to 2147483647
unsigned long		unsigned: 0 to 4294967295
long long (C99)	64 bits	signed: -9223372036854775808 to 9223372036854775807
		unsigned: 0 to 18446744073709551615

Note the word **minimum**: Integer sizes are platform dependent

Beyond these minimums, don't make assumptions about the width or ranges of integer types. Historical note: integers haven't always had minimum width 32 bits: they used to be 16 bit!

Architectural Data models and C

Туре		Data model		
	LP32	ILP32	P64	LP64
(unsigned) short	16 bits	16 bits	16 bits	16 bits
(unsigned) int	16 bits	32 bits	32 bits	32 bits
(unsigned) long	32 bits	32 bits	32 bits	64 bits
(unsigned) long long	64 bits	64 bits	64 bits	64 bits
all pointers	32 bits	32 bits	64 bits	64 bits

- 32-bit systems:
 - LP32 or 2/4/4 (int is 16-bit, long and pointer are 32-bit): Win16 API
 - ILP32 or 4/4/4 (int, long and pointer are 32-bit): Win32 API, Unix, Linux and MAC OS X
- 64-bit systems:
 - P64 or 4/4/8 (int and long are 32-bits and pointer is 64-bit): Win64 API
 - LP64 or 4/8/8 (int is 32-bit, long and pointer are 64-bit): Unix, Linux and MAC OS X

Types Information

The C operator <code>sizeof()</code> can be applied to any type or value in C to determine its width in bytes

sizeof() is used extensively in portable C programs

All we can be sure of is that:

- sizeof(char) <= sizeof(short) <= sizeof(int) <= sizeof(long) <= sizeof(long)
- sizeof(char) == 1
- sizeof(long) == sizeof(pointer) == native address bus width (in bytes)

Integers may be signed or unsigned. All integer types are signed by default, except for char - whether char is signed or unsigned is platform-dependent

Signed types: two's complement

Unsigned types: minimum value = 0; maximum value = $2^{size} - 1$

Note that (signed and unsigned) arithmetic **silently wraps round on overflow**, eg. exceeding the max value wraps silently to the min value

stdint.h

Sizes and ranges of integer types can vary by platform in C

C99 introduced the header <stdint.h> which provides exact width integer types. New advice: use these when you care about width, and use int when you don't care:

Туре	Size	Range	Printf Spec
uint8_t	8 bits	0 to 255	%u
$uint16_t$	16 bits	0 to 65535	%u
$uint32_t$	32 bits	0 to 4294967295	%lu
${\tt uint64_t}$	64 bits	0 to 18446744073709551615	%llu
int8_t	8 bits	-128 to 127	%d
$int16_t$	16 bits	-32768 to 32767	%d
$int32_t$	32 bits	-2147483648 to 2147483647	%ld
$int64_{-}t$	64 bits	-9223372036854775808 to 9223372036854775807	%11d

Floating Point Types

Follow IEEE 754

Basic C Types

Туре	Size	Range	Precision (decimal)
float	32 bits	1.2e-38 to 3.4e+38	6 places
double	64 bits	2.3e-308 to 1.7e+308	15 places
long double	128 bits	3.4e-4932 to 1.1e+4932	34 places

LONG DOUBLE: 80 bits, not 128 bits!

Some numbers can be represented in floating point exactly: an integer that fits in the mantissa, or a binary fraction such as 0.25

Most decimal fractions (e.g. 0.1) cannot be represented exactly as binary fractions - they are recurring binary fractions

This means that it is rare to get exact answers from floating point arithmetic

You should assume that all floating pointer values are approximations.

Floating Point Inaccuracies

Hence: equality often fails

Instead of x == y, write fabs(x-y) < EPSILON, where fabs() comes from <math.h>

#define EPSILON to a suitable value

Note that when using <math.h>, you have to add -lm to the gcc link command, in Make and CB terms that means setting LDLIBS = -lm

Associativity and commutativity don't always apply

The limited precision (especially of float) can easily result in a loss of the least significant parts of numbers. eg. adding a big and a small number together

Addition and subtraction are the largest contributors to floating point error, especially when the numbers are very different in magnitude

Multiplication and division generally preserve relative error (but can take us outside the floating point range)