

UX Scenario — Cronômetro do Tatame

Reference document for LG QA testers. Describes every screen, every remote key and the expected behaviour of each function.

App name	Cronômetro do Tatame
App ID	com.nailson.cronometrotatame
Version	1.0.0
Category	Sports / Fitness
Language	Portuguese (pt-BR)
Target resolution	1280x720
Login required	No
Network required	No — the app is fully self-contained and works offline
In-app purchase	No
Personal data collected	None. Settings are stored locally via <code>localStorage</code>
Age rating	All ages

What the app does

An interval timer for Brazilian Jiu-Jitsu training. It counts a training round ("rola"), then a rest period, then repeats. It is designed to be read from across a training mat, so the countdown fills the screen.

Remote control mapping

Key	Action
OK / Enter	Activates the focused button
Left / Right	Moves focus within the current button row
Up / Down	Moves focus between rows (top icons ↔ bottom buttons)
Back	Closes the settings panel; on the main screen, exits the app
Magic Remote pointer	Click works on every control

On launch, focus is placed on the main button, so OK works immediately. The focused control is filled with the phase colour and scaled up, so the focus position is readable from a distance.

Screen 1 — Main screen

Layout, top to bottom: phase label and status dot, total elapsed time, two icon buttons (fullscreen, settings); large countdown; round label; rest message; three buttons (reset, start/pause, skip); remote legend.

Test steps

1. Launch the app. Expect: **PREPARAR** (prepare) and **00:10**, stopped, focus on the centre button labelled **INICIAR**.
2. Press **OK**. Expect: countdown starts. Short beeps during the final seconds, then a rising chime, then the phase changes to **ROLA** at **05:00**.
3. During **ROLA**, observe the colour: it moves continuously from green through yellow and orange to red as the round progresses. The final 10 seconds are red, with one beep per second — the last three higher pitched and the final one longer.
4. At zero, a three-blast horn sounds and the phase changes to **DESCANSO** (rest) at **01:00**, in blue, showing the message "Descanse. Aproveite e tome uma água." (Rest. Take the chance to drink water.)
5. At the end of the rest, a rising chime sounds and the next round starts. The round counter increments.
6. Press **OK** again. Expect: countdown pauses, the number dims, the button reads **INICIAR**.
7. Press **Right**, then **OK**. Expect: the skip button advances to the next phase immediately.
8. Press **Left** twice, then **OK**. Expect: the reset button returns to the initial state with the total cleared.

Screen 2 — Settings

Reached by moving focus **Up** to the top row and pressing **OK** on the gear icon. Opens full screen.

Test steps

1. **Up / Down** moves between rows; **Left / Right** moves within a row, reaching the **-** and **+** buttons of each value.
2. Press **OK** on **+** next to "Tempo de rola" (round time). Expect: value increases by 15 seconds. Holding OK repeats.
3. The shortcut row (**5 + 1**, **6 + 1**, ...) sets round and rest together.
4. Toggles: sound, final countdown, vibration, keep screen on, TV mode.
5. "Testar som" (test sound) plays the end-of-round horn followed by the start-of-round chime, so volume can be checked.
6. Press **OK** on "Pronto" (done), or press **Back**. Expect: the panel closes and focus returns to the main button.
7. Reopen the settings. Expect: every value persists.

Audio

All sound is generated at runtime with the Web Audio API — there are no audio files. Frequencies sit between 500 Hz and 2 kHz so they carry over gym noise. Sound can be disabled entirely in the settings.

Exit

Pressing **Back** on the main screen closes the app. No data is left running in the background.

Notes for the tester

- The app never requests the network. Testing with the TV offline is expected to behave identically, including fonts.
- Text is Portuguese (pt-BR); the audience is Brazilian jiu-jitsu academies.