

Exceptional service in the national interest

ME469: Boundary Conditions

Stefan P. Domino^{1,2}

¹ Computational Thermal and Fluid Mechanics, Sandia National Laboratories


This presentation has been authored by an employee of National Technology & Engineering Solutions of Sandia, LLC under Contract No. DE-NA0003525 with the U.S. Department of Energy (DOE). The employee owns all right, title and interest in and to the presentation and its solely responsible for its contents. The United States Government retains and the publisher, by accepting the article for publication, acknowledges that the United States Government retains a non-exclusive, paid-up, irrevocable, world-wide license to publish or reproduce the published form of this article or allow others to do so, for United States Government purposes. The DOE will provide public access to these results of federally sponsored research in accordance with the DOE Public Access Plan



 $^{^{\}rm 2}\, {\rm Institute}$ for Computational and Mathematical Engineering, Stanford

Review of Discretization Options: New, emphasis on boundaries...

- Degree-of-freedom (DOF) for:
 - Cell-centered: Stencil is based on a element:face:element
 - DOFs at vertices of elements, or "nodes", element:node (CVFEM, FEM), edge:node (EBVC)




 Definition of an interpolation function:

$$\phi_{ip} = \sum_{n} N_n^{ip} \phi_n$$

- N_n^{ip} is the Lagrange function associated with node n
- ϕ_n is the value of the DOF at node n
- The nodal basis functions obey equipartition of unity and satisfy, $N_n^{x_j} = \delta_{nj}$

Review of Discretization Options: New, emphasis on boundaries...

- Degree-of-freedom (DOF) for:
 - Cell-centered: Stencil is based on a element:face:element
 - DOFs at vertices of elements, or "nodes", element:node (CVFEM, FEM), edge:node (EBVC)



 Definition of an interpolation function:

$$\phi_{ip} = \sum_{n} N_n^{ip} \phi_n$$

- N_n^{ip} is the Lagrange function associated with node n
- ϕ_n is the value of the DOF at node n
- The nodal basis functions obey equipartition of unity and satisfy, $N_n^{x_j} = \delta_{nj}$



Integration Over the Domain: The "Finite" in Finite-Volume and Finite Element

 Consider a simple model equation with the heart domain in mind:


$$\frac{\partial F_j}{\partial x_j} = S$$

Where F_j is a flux and S is a source term

- Integrating over the entire domain, Ω : $\int_{\Omega} \frac{\partial F_j}{\partial x_j} d\Omega = \int_{\Omega} S d\Omega$
- Without loss of generality, let us define a set of subdomains, Ω_k :

$$\sum_{k} \int_{\Omega_{k}} \frac{\partial F_{j}}{\partial x_{j}} d\Omega_{k} = \sum_{k} \int_{\Omega_{k}} Sd\Omega_{k}$$

As present, only volumetric integrals appear



Note:

• The formality of Σ_k and Ω_k is implied to exist over the full domain and is often times dropped – integral type implied by dV (volume) and dS (domain boundary)

Integration Over the Domain: The "Finite" in Finite-Volume and Finite Element

 Consider a simple model equation with the heart domain in mind:


$$\frac{\partial F_j}{\partial x_i} = S$$

Where \boldsymbol{F}_{j} is a flux and \boldsymbol{S} is a source term

- Integrating over the entire domain, Ω : $\int_{\Omega} \frac{\partial F_j}{\partial x_j} d\Omega = \int_{\Omega} S d\Omega$
- Without loss of generality, let us define a set of subdomains, Ω_k :

$$\sum_{k} \int_{\Omega_{k}} \frac{\partial F_{j}}{\partial x_{j}} d\Omega_{k} = \sum_{k} \int_{\Omega_{k}} Sd\Omega_{k}$$

As present, only volumetric integrals appear



Note:

• The formality of the same is implied to exist over the same and is often times drop d - in the same and is often ype implied by dV (volume)

Towards Boundary Contributions

• Given a partial differential equation (PDE) and associated volumetric form:

$$\int_{\Omega} \frac{\partial F_j}{\partial x_j} d\Omega = \int_{\Omega} S d\Omega$$

• Applying Gauss Divergence provides the standard finite volume form for fluxes in surface integral form (no distinction between internal control volume faces and boundary faces):

$$\sum_{k} \int_{\Omega_{k}} \frac{\partial F_{j}}{\partial x_{j}} d\Omega_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega_{k} \longrightarrow \sum_{k} \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int F_{j} n_{j} dS = \int S dV$$

We can also multiple PDE by an arbitrary test function, w, and integrate over a volume,

$$\int w \frac{\partial F_j}{\partial x_j} dV = \int w S dV$$

$$\int w \frac{\partial F_j}{\partial x_j} dV = \int w S dV$$

$$\int Gauss-Divergence. Note, that test function must be differentiable – shown here, at least once..$$

$$-\int F_j \frac{\partial w}{\partial x_j} dV + \int \frac{\partial w F_j}{\partial x_j} dV = -\int F_j \frac{\partial w}{\partial x_j} dV + \int w F_j n_j dS$$

$$\frac{\partial w F_j}{\partial x_j} = w \frac{\partial F_j}{\partial x_j} + \frac{\partial w}{\partial x_j} F_j$$
Interior
Boundary

Towards Boundary Contributions

• Given a partial differential equation (PDE) and associated volumetric form:

$$\int_{\Omega} \frac{\partial F_j}{\partial x_j} d\Omega = \int_{\Omega} S d\Omega$$

 Applying Gauss Divergence provides the standard finite volume form for fluxes in surface integral form (no distinction between internal control volume faces and boundary faces):

$$\sum_{k} \int_{\Omega_{k}} \frac{\partial F_{j}}{\partial x_{j}} d\Omega_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega_{k} \longrightarrow \sum_{k} \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} F_{j} n_{j} d\Gamma_{k} = \sum_{k} \int_{\Omega_{k}} S d\Omega \longrightarrow \int_{\Gamma_{k}} S d\Omega \longrightarrow \int$$

We can also multiple PDE by an arbitrary test function, w, and integrate over a volume,


$$\int w \frac{\partial F_j}{\partial x_j} dV = \int w S dV$$
Next, integrate by parts and apply Gauss-Divergence. Note, that test function must be differentiable – shown here, at least once..
$$-\int F_j \frac{\partial w}{\partial x_j} dV + \int \frac{\partial w F_j}{\partial x_j} dV = -\int F_j \frac{\partial w}{\partial x_j} dV + \int \frac{\partial w}{\partial x_j} dV + \int \frac{\partial w F_j}{\partial x_j} dS$$

$$\frac{\partial w F_j}{\partial x_j} = w \frac{\partial F_j}{\partial x_j} + \frac{\partial w}{\partial x_j} F_j$$
Interior Boundary

7

Cell-Centered vs Vertex-Centered Differences


• For a CC scheme, boundary condition is flux-based, while for VC and FEM, there is an option of flux-based, i.e., "weak", or Dirichlet, i.e., "strong"



For Example, a Cell-Centered Inflow Boundary

Consider an inflow boundary condition where the advection term is of interest


- You may have a pipe flow with a given inflow velocity to match a Reynolds number:
- A well-posed condition provides the inlet density, velocity and scalar values



For Example, a Vertex-Centered (EBVC/CVFEM) Inflow Boundary Flux-based (Weak treatment)

Consider an inflow boundary condition where the advection term is of interest

- You may have a pipe flow with a given inflow velocity to match a Reynolds number:
- A well-posed condition provides the inlet density, velocity and scalar values



For Example, a Vertex-Centered (EBVC/CVFEM) Inflow Boundary Dirichlet-based (Strong treatment)

Consider an inflow boundary condition where the advection term is of interest


- You may have a pipe flow with a given inflow velocity to match a Reynolds number:
- A well-posed condition provides the inlet density, velocity and scalar values

Inflow

$$\phi = \phi^{spec}$$

Dirichelt conditions are applied when you know the precise value at the boundary, i.e., an inflow, or a wall

Often times, boundary conditions are naturally flux-based, e.g., at an adiabatic wall you know the heat flux, open-bc (zero flux), etc.



Weak vs Strong: A Practical Heat Conduction Example

Consider a simple heat conduction solution in which temperature is known at the boundaries, T = T^{spec}

Governing Equation:


$$\int \rho C_p \frac{\partial T}{\partial t} dV - \int \lambda \frac{\partial T}{\partial x_j} n_j dS = 0$$

• It can be shown (see Svard and Nordstrom, JCP, 2008) that a stable and accurate weak BC implementation is provided by: $\partial T = \lambda$

$$q_n = -\lambda \frac{\partial T}{\partial x_j} n_j + \gamma \frac{\lambda}{L} \left(T - T^{spec} \right)$$

 Consider the MMS temperature solution (and convergence to the right):

$$T^{mms}(x) = \frac{k}{4} \left(\cos(2\pi x) + \cos(2\pi y) + \cos(2\pi z) \right)$$






Types of Boundary Conditions in Practical CFD

Flow-past a heated cylinder


Symmetry, "flow slips along" (normal stress pn_idS applied with tangential stress = 0)



Types of Boundary Conditions in Practical CFD

Flow past a 2-dimensional cylinder (the midterm assignment)

Symmetry, "flow slips along" (normal stress pn_idS applied with tangential stress = 0)







Types of Boundary Conditions in Practical CFD

Flow past a series of rotating blades: Zero normal gradient at open bc?

Symmetry







Mathematical Description

See: https://nalu.readthedocs.io/en/latest/source/theory/boundaryConditions.html