
CISCO Academy

Lab - Switch Security Configuration

Topology



Addressing Table

Device	Interface / VLAN	IP Address	Subnet Mask
R1	G0/0/1	192.168.10.1	255.255.255.0
	Loopback 0	10.10.1.1	255.255.255.0
S1	VLAN 10	192.168.10.201	255.255.255.0
S2	VLAN 10	192.168.10.202	255.255.255.0
PC – A	NIC	DHCP	255.255.255.0
PC – B	NIC	DHCP	255.255.255.0

Objectives

Part 1: Configure the Network Devices.

- Cable the network.
- Configure R1.
- Configure and verify basic switch settings.

Part 2: Configure VLANs on Switches.

• Configure VLAN 10.

- Configure the SVI for VLAN 10.
- Configure VLAN 333 with the name Native on S1 and S2.
- Configure VLAN 999 with the name ParkingLot on S1 and S2.

Part 3: Configure Switch Security.

- Implement 802.1Q trunking.
- Configure access ports.
- Secure and disable unused switchports.
- Document and implement port security features.
- Implement DHCP snooping security.
- Implement PortFast and BPDU guard.
- Verify end-to-end-connectivity.

Background / Scenario

This is a comprehensive lab to review previously covered Layer 2 security features.

Note: The routers used with CCNA hands-on labs are Cisco 4221 with Cisco IOS XE Release 16.9.3 (universalk9 image). The switches used in the labs are Cisco Catalyst 2960s with Cisco IOS Release 15.0(2) (lanbasek9 image). Other routers, switches, and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and the output produced might vary from what is shown in the labs. Refer to the Router Interface Summary Table at the end of the lab for the correct interface identifiers.

Note: Make sure that the switches have been erased and have no startup configurations. If you are unsure, contact your instructor.

Required Resources

- 1 Router (Cisco 4221 with Cisco IOS XE Release 16.9.3 universal image or comparable)
- 2 Switches (Cisco 2960 with Cisco IOS Release 15.0(2) lanbasek9 image or comparable)
- 2 PCs (Windows with a terminal emulation program, such as Tera Term)
- Console cables to configure the Cisco IOS devices via the console ports
- Ethernet cables as shown in the topology

Instructions

Part 1: Configure the Network Devices.

Step 1: Cable the network.

- a. Cable the network as shown in the topology.
- b. Initialize the devices.

Step 2: Configure R1.

- a. Erase Startup Configuration.
- b. Load the following configuration script on R1.

```
hostname R1
no ip domain lookup
ip dhcp excluded-address 192.168.10.1 192.168.10.9
ip dhcp excluded-address 192.168.10.201 192.168.10.202
ip dhcp pool Students
 network 192.168.10.0 255.255.255.0
 default-router 192.168.10.1
 domain-name CCNA2.Lab-11.6.1
interface Loopback0
 ip address 10.10.1.1 255.255.255.0
interface GigabitEthernet0/0/1
 description Link to S1 Port 5
ip dhcp relay information trusted
 ip address 192.168.10.1 255.255.255.0
no shutdown
line con 0
 logging synchronous
 exec-timeout 0 0
```

c. Verify the running-configuration on R1 using the following command:

```
R1# show ip interface brief
```

c. Verify IP addressing and interfaces are in an up / up state (troubleshoot as necessary).

Step 3: Configure and verify basic switch settings.

- a. Erase Startup Configuration.
- b. Delete VLAN database (vlan.dat)
- c. Configure the hostname for switches S1 and S2.
- d. Prevent unwanted DNS lookups on both switches.
- e. Configure interface descriptions for the ports that are in use in S1 and S2.
- Set the default-gateway for the Management VLAN to 192.168.10.1 on both switches.

Part 2: Configure VLANs on Switches.

Step 1: Configure VLAN 10.

Add VLAN 10 to S1 and S2 and name the VLAN Management.

Step 2: Configure the SVI for VLAN 10.

Configure the IP address according to the Addressing Table for SVI for VLAN 10 on S1 and S2. Enable the SVI interfaces and provide a description for the interface.

Step 3: Configure VLAN 333 with the name Native on S1 and S2.

Step 4: Configure VLAN 999 with the name ParkingLot on S1 and S2.

Part 3: Configure Switch Security.

Step 1: Implement 802.1Q trunking.

- a. On both switches, configure trunking on F0/1 to use VLAN 333 as the native VLAN.
- b. Verify that trunking is configured on both switches.

S1# show interface trunk

Port	Mode	Encapsulation	Status	Native vlan
Fa0/1	on	802.1q	trunking	333
Port	Vlans allowed or	n trunk		
Fa0/1	1-4094			
Port	Vlans allowed ar	nd active in man	nagement domair	n
Fa0/1	1,10,333,999			
Port	Vlans in spannir	ng tree forwardi	ng state and r	not pruned
Fa0/1	1,10,333,999			-

S2# show interface trunk

Port	Mode	Encapsulation	Status	Native vlan
Fa0/1	on	802.1q	trunking	333
Port	Vlans allowed on	trunk		
Fa0/1	1-4094			
Port	Vlans allowed and	d active in man	agement domain	
Fa0/1	1,10,333,999		-	
	, , ,			
Port	Vlans in spanning	g tree forwardi	ng state and n	ot pruned
Fa0/1	1,10,333,999	,		1111111111111
140/1	1,10,000,000			

- c. Disable DTP negotiation on F0/1 on S1 and S2.
- d. Verify with the **show interfaces** command.

```
S1# show interfaces f0/1 switchport | include Negotiation
Negotiation of Trunking: Off

S2# show interfaces f0/1 switchport | include Negotiation
Negotiation of Trunking: Off
```

Step 2: Configure access ports.

a. On S1, configure F0/5 and F0/6 as access ports that are associated with VLAN 10.

b. On S2, configure F0/18 as an access port that is associated with VLAN 10.

Step 3: Secure and disable unused switchports.

- a. On S1 and S2, move the unused ports from VLAN 1 to VLAN 999 and disable the unused ports.
- b. Verify that unused ports are disabled and associated with VLAN 999 by issuing the **show** command.

S1# show interfaces status

Port	Name	Status	Vlan	Duplex	Speed	Туре
Fa0/1	Link to S2	connected	trunk	a-full	a-100	10/100BaseTX
Fa0/2		disabled	999	auto	auto	10/100BaseTX
Fa0/3		disabled	999	auto	auto	10/100BaseTX
Fa0/4		disabled	999	auto	auto	10/100BaseTX
Fa0/5	Link to R1	connected	10	a-full	a-100	10/100BaseTX
Fa0/6	Link to PC-A	connected	10	a-full	a-100	10/100BaseTX
Fa0/7		disabled	999	auto	auto	10/100BaseTX
Fa0/8		disabled	999	auto	auto	10/100BaseTX
Fa0/9		disabled	999	auto	auto	10/100BaseTX
Fa0/10		disabled	999	auto	auto	10/100BaseTX

<output omitted>

S2# show interfaces status

Por	t Name		Status	Vlan	Duplex	Speed	Type
Fa0	/1 Link	to S1	connected	trunk	a-full	a-100	10/100BaseTX
Fa0	/2		disabled	999	auto	auto	10/100BaseTX
Fa0	/3		disabled	999	auto	auto	10/100BaseTX
<ou< td=""><td>tput omitted</td><td>></td><td></td><td></td><td></td><td></td><td></td></ou<>	tput omitted	>					
Fa0	/14		disabled	999	auto	auto	10/100BaseTX
Fa0	/15		disabled	999	auto	auto	10/100BaseTX
Fa0	/16		disabled	999	auto	auto	10/100BaseTX
Fa0	/17		disabled	999	auto	auto	10/100BaseTX
Fa0	/18 Link	to PC-B	connected	10	a-full	a-100	10/100BaseTX
Fa0	/19		disabled	999	auto	auto	10/100BaseTX
Fa0	/20		disabled	999	auto	auto	10/100BaseTX
Fa0	/21		disabled	999	auto	auto	10/100BaseTX
Fa0	/22		disabled	999	auto	auto	10/100BaseTX
Fa0	/23		disabled	999	auto	auto	10/100BaseTX
Fa0	/24		disabled	999	auto	auto	10/100BaseTX
Gi0	/1		disabled	999	auto	auto	10/100/1000BaseTX
Gi0	/2		disabled	999	auto	auto	10/100/1000BaseTX

Step 4: Document and implement port security features.

The interfaces F0/6 on S1 and F0/18 on S2 are configured as access ports. In this step, you will also configure port security on these two access ports.

a. On S1, issue the **show port-security interface f0/6** command to display the default port security settings for interface F0/6. Record your answers in the table below.

Default Port Security Configuration					
Feature	Default Setting				
Port Security					
Maximum number of MAC addresses					
Violation Mode					
Aging Time					
Aging Type					
Secure Static Address Aging					
Sticky MAC Address					

b. On S1, enable port security on F0/6 with the following settings:

o Maximum number of MAC addresses: 3

Violation type: restrictAging time: 60 min

Aging type: inactivity

S1(config)# interface f0/6

S1(config-if)# switchport port-security

S1(config-if)# switchport port-security maximum 3

S1(config-if) # switchport port-security violation restrict

S1(config-if)# switchport port-security aging time 60

S1(config-if)# switchport port-security aging type inactivity

c. Verify port security on S1 F0/6.

S1# show port-security interface f0/6

Port Security : Enabled
Port Status : Secure-up
Violation Mode : Restrict
Aging Time : 60 mins
Aging Type : Inactivity
SecureStatic Address Aging : Disabled

Maximum MAC Addresses : 3
Total MAC Addresses : 1
Configured MAC Addresses : 0
Sticky MAC Addresses : 0

Last Source Address:Vlan : 0022.5646.3411:10

Security Violation Count : 0

S1# show port-security address

Secure Mac Address Table

Vlan Mac Address Type Ports Remaining Age

(mins)

10 0022.5646.3411 SecureDynamic Fa0/6 60 (I)

Total Addresses in System (excluding one mac per port) : 0

Max Addresses limit in System (excluding one mac per port) : 8192

d. Enable port security for F0/18 on S2. Configure the port to add MAC addresses learned on the port automatically to the running configuration.

S2(config)# interface f0/18
S2(config-if)# switchport port-security
S2(config-if)# switchport port-security mac-address sticky

- e. Configure the following port security settings on S2 F/18:
 - Maximum number of MAC addresses: 2
 - Violation type: Protect
 - o Aging time: **60 min**

S2(config)# interface f0/18

S2(config-if)# switchport port-security aging time 60

S2(config-if)# switchport port-security maximum 2

S2(config-if)# switchport port-security violation protect

f. Verify port security on S2 F0/18.

S2# show port-security interface f0/18

Port Security : Enabled
Port Status : Secure-up
Violation Mode : Protect
Aging Time : 60 mins
Aging Type : Absolute
SecureStatic Address Aging : Disabled

Maximum MAC Addresses : 2
Total MAC Addresses : 1
Configured MAC Addresses : 0
Sticky MAC Addresses : 0

Last Source Address:Vlan : 0022.5646.3413:10

Security Violation Count : 0

S2# show port-security address

Secure Mac Address Table

Vlan	Mac Address	Туре	Ports	Remaining Age (mins)
10	0022.5646.3413	SecureSticky	Fa0/18	-

Total Addresses in System (excluding one mac per port) : 0 Max Addresses limit in System (excluding one mac per port) : 8192

Step 5: Implement DHCP snooping security.

a. On S2, enable DHCP snooping and configure DHCP snooping on VLAN 10.

S2(config)# ip dhcp snooping
S2(config)# ip dhcp snooping vlan 10

b. Configure the trunk port on S2 as a trusted port.

S2(config)# interface f0/1
S2(config-if)# ip dhcp snooping trust

c. Limit the untrusted port, F18 on S2, to five DHCP packets per second.

S2(config)# interface f0/18 S2(config-if)# ip dhcp snooping limit rate 5

d. Verify DHCP Snooping on S2.

S2# show ip dhcp snooping

Switch DHCP snooping is enabled

DHCP snooping is configured on following VLANs:

10

DHCP snooping is operational on following VLANs:

10

DHCP snooping is configured on the following L3 Interfaces:

Insertion of option 82 is enabled

circuit-id default format: vlan-mod-port

remote-id: 0cd9.96d2.3f80 (MAC)

Option 82 on untrusted port is not allowed

Verification of hwaddr field is enabled

Verification of giaddr field is enabled

DHCP snooping trust/rate is configured on the following Interfaces:

Interface	Trusted	Allow option	Rate limit (pps)
FastEthernet0/1	yes	yes	unlimited
Custom circuit-ids:			
FastEthernet0/18	no	no	5

Custom circuit-ids:

e. From the command prompt on PC-B, release and then renew the IP address.

C:\Users\Student> ipconfig /release

C:\Users\Student> ipconfig /renew

f. Verify the DHCP snooping binding using the **show ip dhcp snooping binding** command.

S2# show ip dhcp snooping binding

MacAddress	IpAddress	Lease(sec)	Туре	VLAN	Interface	
00:50:56:90:D0:8E	192.168.10.11	86213	dhcp-snooping	10	FastEthernet0/18	
Total number of bindings: 1						

Step 6: Implement PortFast and BPDU guard.

a. Configure PortFast on all the access ports that are in use on both switches.

```
S1(config)# interface range f0/5 - 6
S1(config-if)# spanning-tree portfast
S2(config)# interface f0/18
S2(config-if)# spanning-tree portfast
```

b. Enable BPDU guard on S1 and S2 VLAN 10 access ports connected to PC-A and PC-B.

```
S1(config)# interface f0/6
S1(config-if)# spanning-tree bpduguard enable
S2(config)# interface f0/18
S2(config-if)# spanning-tree bpduguard enable
```

c. Verify that BPDU guard and PortFast are enabled on the appropriate ports.

```
S1# show spanning-tree interface f0/6 detail

Port 8 (FastEthernet0/6) of VLAN0010 is designated forwarding

Port path cost 19, Port priority 128, Port Identifier 128.6.

<output omitted for brevity>

Number of transitions to forwarding state: 1

The port is in the portfast mode

Link type is point-to-point by default

Bpdu guard is enabled

BPDU: sent 128, received 0
```

Step 7: Verify end-to-end connectivity.

Verify PING connectivity between all devices in the IP Addressing Table. If the pings fail, you may need to disable the firewall on the PC hosts.

Reflection Questions

- 1. In reference to Port Security on S2, why is there no timer value for the remaining age in minutes when sticky learning was configured?
- 2. In reference to Port Security on S2, if you load the running-config script on S2, why will PC-B on port 18 never get an IP address via DHCP?
- 3. In reference to Port Security, what is the difference between the absolute aging type and inactivity aging type?