

General

CREAR UN USUARIO

CREATE USER fulanito

IDENTIFIED BY contraseña

[DEFAULT TABLESPACE nombre_ts]

[TEMPORARY TABLESPACE nombre_ts_temp]

[QUOTA {num {K | M} | UNLIMITED } ON nombre_ts]

[PROFILE perfil];

MODIFICAR USUARIO

ALTER USER fulanito

IDENTIFIED BY contraseña

account lock

account unlock

password expire

[DEFAULT TABLESPACE nombre_ts]

[TEMPORARY TABLESPACE nombre_ts_temp]

[QUOTA {num {K | M} | UNLIMITED } ON nombre_ts]

[PROFILE perfil];

BORRAR USUARIO

DROP USER fulanito [CASCADE];

PRIVILEGIOS OBJETOS

Los privilegios son: SELECT, INSERT, UPDATE, DELETE, ALTER, EXECUTE, INDEX, REFERENCES y ALL.

Para concederlos:

GRANT privilegio ON propietario.objeto TO [usuario | rol | PUBLIC]

[WITH GRANT OPTION];

Para quitar privilegios:

REVOKE privilegio ON propietario.objeto FROM [usuario | rol];

LOS PRIVILEGIOS DEL SISTEMA

CREATE, ALTER y DROP de cada tipo de objeto. (create session,user,table,role,profile)

CREATE ANY, ALTER ANY y DROP ANY para cada tipo de objeto.

SELECT, INSERT, UPDATE o DELETE ANY TABLE.

La sintaxis para concederlos es:

GRANT privilegio TO [usuario | rol | PUBLIC]

[WITH ADMIN OPTION];

Para quitar privilegios:

REVOKE privilegio FROM [usuario | rol];

ROLES

Para crear un rol: CREATE ROLE nombre;

Para añadir privilegios: GRANT priv [ON obj] TO nombrerol;

Para quitar privilegios: REVOKE priv FROM nombrerol;

Para dárselo a un usuario: GRANT nombrerol TO usuario;

Para quitárselo a un usuario: REVOKE nombrerol FROM usuario;

Para borrarlo: DROP ROLE nombrerol;

Para añadir un rol a otro: GRANT nombrerol TO nombrerol;

PERFILES

ALTER SYSTEM SET RESOURCE_LIMIT=TRUE

La sintaxis para crear un perfil es la siguiente:

CREATE PROFILE nombreperfil LIMIT

parametrorecurso | parametrocontraseña [valor [K|M] | UNLIMITED]

parametrorecurso | parametrocontraseña [valor [K|M] | UNLIMITED]

Parametros

SESSIONS_PER_USER, CONNECT_TIME , IDLE_TIME, CPU_PER_SESSION, CPU_PER_CALL,
LOGICAL_READS_PER_SESSION,

LOGICAL_READS_PER_CALL, PRIVATE_SGA, COMPOSITE_LIMIT, FAILED_LOGIN_ATTEMPTS, PASSWORD_LIFE_TIME,
PASSWORD_REUSE_TIME, PASSWORD_REUSE_MAX, PASSWORD_LOCK_TIME, PASSWORD_GRACE_TIME,
PASSWORD_VERIFY_FUNCTION

Para asignar un perfil a un usuario:

ALTER USER fulanito PROFILE nombreperfil;

Para modificar un perfil

ALTER PROFILE nombreperfil limit

{parametrorecurso | parametrocontraseña} [valor [K|M] | UNLIMITED];

Para borrar un perfil:

DROP PROFILE nombreperfil;

Vistas del diccionario de datos:

DBA_PROFILES: Muestra los perfiles existentes con sus límites.

DBA_USERS: Muestra los perfiles de los usuarios.

Las cláusulas de almacenamiento son:

INITIAL (tamaño extensión inicial) (en K o M)

NEXT (tamaño 2ª extensión)

PCTINCREASE (porcentaje de incremento para la 3ª y siguientes),

MINEXTENTS (extensiones reservadas en principio)

MAXEXTENTS (número total de extensiones como máximo).

MAS PRIVILEGIOS IMPORTANTES del sistema:

CREATE PROFILE Create profiles

ALTER PROFILE Alter profiles

DROP PROFILE Drop profiles

CREATE ROLE Create roles

ALTER ANY ROLE Alter any role in the database

DROP ANY ROLE Drop roles

GRANT ANY ROLE Grant any role in the database

CREATE SEQUENCE Create sequences in grantee's schema

CREATE ANY SEQUENCE Create sequences in any schema

ALTER ANY SEQUENCE Alter any sequence in the database

DROP ANY SEQUENCE Drop sequences in any schema

SELECT ANY SEQUENCE Reference sequences in any schema

CREATE SESSION Connect to the database

CREATE SYNONYM Create synonyms in grantee's schema

CREATE ANY SYNONYM Create private synonyms in any schema

CREATE PUBLIC SYNONYM Create public synonyms

DROP ANY SYNONYM Drop private synonyms in any schema

DROP PUBLIC SYNONYM Drop public synonyms

CREATE TABLE Create tables in grantee's schema

CREATE ANY TABLE Create tables in any schema. The owner of the schema containing the table must have space quota on the tablespace to contain the table.

ALTER ANY TABLE Alter any table or view in any schema

DELETE ANY TABLE Delete rows from tables, table partitions, or views in any schema

DROP ANY TABLE Drop or truncate tables or table partitions in any schema

INSERT ANY TABLE Insert rows into tables and views in any schema

LOCK ANY TABLE Lock tables and views in any schema

SELECT ANY TABLE Query tables, views, or materialized views in any schema

UPDATE ANY TABLE Update rows in tables and views in any schema

CREATE TABLESPACE Create tablespaces

ALTER TABLESPACE Alter tablespaces

DROP TABLESPACE Drop tablespaces

MANAGE TABLESPACE Take tablespaces offline and online and begin and end tablespace backups

UNLIMITED TABLESPACE Use an unlimited amount of any tablespace. This privilege overrides any specific quotas assigned. If you revoke this privilege from a user, then the user's schema objects remain but further tablespace allocation is denied unless authorized by specific tablespace quotas. You cannot grant this system privilege to roles.

CREATE USER Create users. This privilege also allows the creator to: Assign quotas on any tablespace, Set default and temporary tablespaces, Assign a profile as part of a

ALTER USER Alter any user. This privilege authorizes the grantee to: Change another user's password or authentication method, Assign quotas on any tablespace, Set default and temporary tablespaces, Assign a profile and default roles

DROP USER Drop users

CREATE VIEW Create views in grantee's schema

CREATE ANY VIEW Create views in any schema

DROP ANY VIEW Drop views in any schema

ALTER SESSION Conceder privilegios para activar traza