## The Python/C API

Release 3.8.0

# Guido van Rossum and the Python development team

October 17, 2019

Python Software Foundation Email: docs@python.org

## **CONTENTS**

1	Intro	duction	3
	1.1	Coding standards	3
	1.2	Include Files	3
	1.3	Useful macros	4
	1.4	Objects, Types and Reference Counts	5
	1.5	Exceptions	9
	1.6	Embedding Python	10
	1.7	Debugging Builds	11
2	Stabl	e Application Binary Interface	13
3	The V	Very High Level Layer	15
4	Refer	rence Counting	21
5	Exce	ption Handling	23
	5.1	Printing and clearing	23
	5.2	Raising exceptions	24
	5.3	Issuing warnings	26
	5.4	Querying the error indicator	27
	5.5	Signal Handling	29
	5.6	Exception Classes	29
	5.7	Exception Objects	30
	5.8	Unicode Exception Objects	30
	5.9	Recursion Control	31
	5.10	Standard Exceptions	32
	5.11	Standard Warning Categories	34
6	Utilit		35
	6.1		35
	6.2	System Functions	37
	6.3	Process Control	39
	6.4	Importing Modules	39
	6.5	Data marshalling support	43
	6.6		44
	6.7	String conversion and formatting	51
	6.8		53
	6.9	Codec registry and support functions	53
7	Absti	ract Objects Layer	57
	7.1	Object Protocol	57

	7.2	Number Protocol	52
	7.3	Sequence Protocol	55
	7.4	Mapping Protocol	67
	7.5	Iterator Protocol	58
	7.6	Buffer Protocol	59
	7.7	Old Buffer Protocol	75
8	Conc	rete Objects Layer	77
	8.1	Fundamental Objects	77
	8.2	Numeric Objects	80
	8.3	Sequence Objects	86
	8.4	Container Objects	11
	8.5	Function Objects	15
	8.6	Other Objects	19
9	Initia	lization, Finalization, and Threads	37
	9.1	Before Python Initialization	
	9.2	Global configuration variables	
	9.3	Initializing and finalizing the interpreter	
	9.4	Process-wide parameters	
	9.5	Thread State and the Global Interpreter Lock	
	9.6	Sub-interpreter support	
	9.7	Asynchronous Notifications	
	9.8	Profiling and Tracing	
	9.9	Advanced Debugger Support	
	9.10	Thread Local Storage Support	
10	Pytho	n Initialization Configuration	55
10		PyWideStringList	
		PyStatus	
		PyPreConfig	
		Preinitialization with PyPreConfig	
	10.5	PyConfig	
	10.6	Initialization with PyConfig	
	10.7	Isolated Configuration	
	10.8	Python Configuration	
		Path Configuration	
		Py_RunMain()	
		Multi-Phase Initialization Private Provisional API	
11	N. f	M	71
11	11.1	ory Management Overview	
	11.2	Raw Memory Interface	
	11.3	Memory Interface	
	11.4	Object allocators	-
	11.5	Default Memory Allocators	
	11.6	Customize Memory Allocators	
	11.7	The pymalloc allocator	
	11.7	tracemalloc C API	
	11.9	Examples	
12	Ohio		
12	12.1	t Implementation Support Allocating Objects on the Heap	
	12.1	8 - J	
		Common Object Structures	
	12.3	Type Objects	չ4

Inc	ndex	259
D	Copyright	257
	C.2 Terms and conditions for accessing or otherwise using Python	. 240
C	History and License C.1 History of the software	<b>239</b>
В	About these documents  B.1 Contributors to the Python Documentation	237 . 237
A	Glossary	223
13	3 API and ABI Versioning	221
	12.10 Examples	
	12.9 Slot Type typedefs	. 213
	12.7 Buffer Object Structures	
	12.6 Sequence Object Structures	. 211
	<ul><li>12.4 Number Object Structures</li><li>12.5 Mapping Object Structures</li></ul>	

This manual documents the API used by C and C++ programmers who want to write extension modules or embed Python. It is a companion to extending-index, which describes the general principles of extension writing but does not document the API functions in detail.

CONTENTS 1

2 CONTENTS

**CHAPTER** 

ONE

## INTRODUCTION

The Application Programmer's Interface to Python gives C and C++ programmers access to the Python interpreter at a variety of levels. The API is equally usable from C++, but for brevity it is generally referred to as the Python/C API. There are two fundamentally different reasons for using the Python/C API. The first reason is to write *extension modules* for specific purposes; these are C modules that extend the Python interpreter. This is probably the most common use. The second reason is to use Python as a component in a larger application; this technique is generally referred to as *embedding* Python in an application.

Writing an extension module is a relatively well-understood process, where a "cookbook" approach works well. There are several tools that automate the process to some extent. While people have embedded Python in other applications since its early existence, the process of embedding Python is less straightforward than writing an extension.

Many API functions are useful independent of whether you're embedding or extending Python; moreover, most applications that embed Python will need to provide a custom extension as well, so it's probably a good idea to become familiar with writing an extension before attempting to embed Python in a real application.

## 1.1 Coding standards

If you're writing C code for inclusion in CPython, you **must** follow the guidelines and standards defined in **PEP 7**. These guidelines apply regardless of the version of Python you are contributing to. Following these conventions is not necessary for your own third party extension modules, unless you eventually expect to contribute them to Python.

## 1.2 Include Files

All function, type and macro definitions needed to use the Python/C API are included in your code by the following line:

```
#define PY_SSIZE_T_CLEAN
#include <Python.h>
```

This implies inclusion of the following standard headers: <stdio.h>, <string.h>, <errno.h>, imits.h>, <assert.h> and <stdlib.h> (if available).

**Note:** Since Python may define some pre-processor definitions which affect the standard headers on some systems, you *must* include Python.h before any standard headers are included.

It is recommended to always define PY\_SSIZE\_T\_CLEAN before including Python.h. See *Parsing arguments and building values* for a description of this macro.

All user visible names defined by Python.h (except those defined by the included standard headers) have one of the prefixes Py or Py. Names beginning with Py are for internal use by the Python implementation and should not be used by extension writers. Structure member names do not have a reserved prefix.

**Note:** User code should never define names that begin with Py or Py. This confuses the reader, and jeopardizes the portability of the user code to future Python versions, which may define additional names beginning with one of these prefixes.

The header files are typically installed with Python. On Unix, these are located in the directories prefix/include/pythonversion/ and  $exec\_prefix/include/pythonversion/$ , where prefix and  $exec\_prefix$  are defined by the corresponding parameters to Python's **configure** script and *version* is '%d.%d' % sys.  $version\_info[:2]$ . On Windows, the headers are installed in prefix/include, where prefix is the installation directory specified to the installer.

To include the headers, place both directories (if different) on your compiler's search path for includes. Do *not* place the parent directories on the search path and then use #include <pythonX.Y/Python.h>; this will break on multi-platform builds since the platform independent headers under prefix include the platform specific headers from exec\_prefix.

C++ users should note that although the API is defined entirely using C, the header files properly declare the entry points to be extern "C". As a result, there is no need to do anything special to use the API from C++.

## 1.3 Useful macros

Several useful macros are defined in the Python header files. Many are defined closer to where they are useful (e.g.  $PY\_RETURN\_NONE$ ). Others of a more general utility are defined here. This is not necessarily a complete listing.

## Py\_UNREACHABLE()

Use this when you have a code path that you do not expect to be reached. For example, in the default: clause in a switch statement for which all possible values are covered in case statements. Use this in places where you might be tempted to put an assert (0) or abort () call.

New in version 3.7.

## $Py\_ABS(x)$

Return the absolute value of x.

New in version 3.3.

## $Py_MIN(x, y)$

Return the minimum value between x and y.

New in version 3.3.

## $Py_MAX(x, y)$

Return the maximum value between x and y.

New in version 3.3.

## Py\_STRINGIFY(X)

Convert x to a C string. E.g. Py\_STRINGIFY (123) returns "123".

New in version 3.4.

## **Py\_MEMBER\_SIZE** (type, member)

Return the size of a structure (type) member in bytes.

New in version 3.6.

#### Py\_CHARMASK (c)

Argument must be a character or an integer in the range [-128, 127] or [0, 255]. This macro returns c cast to an unsigned char.

### Py\_GETENV(s)

Like getenv(s), but returns *NULL* if -E was passed on the command line (i.e. if Py\_IgnoreEnvironmentFlag is set).

#### Py UNUSED (arg)

Use this for unused arguments in a function definition to silence compiler warnings. Example: int func(int a, int Py\_UNUSED(b)) { return a; }.

New in version 3.4.

#### Py DEPRECATED (version)

Use this for deprecated declarations. The macro must be placed before the symbol name.

Example:

```
Py_DEPRECATED(3.8) PyAPI_FUNC(int) Py_OldFunction(void);
```

Changed in version 3.8: MSVC support was added.

## 1.4 Objects, Types and Reference Counts

Most Python/C API functions have one or more arguments as well as a return value of type <code>PyObject\*</code>. This type is a pointer to an opaque data type representing an arbitrary Python object. Since all Python object types are treated the same way by the Python language in most situations (e.g., assignments, scope rules, and argument passing), it is only fitting that they should be represented by a single C type. Almost all Python objects live on the heap: you never declare an automatic or static variable of type <code>PyObject</code>, only pointer variables of type <code>PyObject\*</code> can be declared. The sole exception are the type objects; since these must never be deallocated, they are typically static <code>PyTypeObject</code> objects.

All Python objects (even Python integers) have a *type* and a *reference count*. An object's type determines what kind of object it is (e.g., an integer, a list, or a user-defined function; there are many more as explained in types). For each of the well-known types there is a macro to check whether an object is of that type; for instance, PyList\_Check (a) is true if (and only if) the object pointed to by *a* is a Python list.

## 1.4.1 Reference Counts

The reference count is important because today's computers have a finite (and often severely limited) memory size; it counts how many different places there are that have a reference to an object. Such a place could be another object, or a global (or static) C variable, or a local variable in some C function. When an object's reference count becomes zero, the object is deallocated. If it contains references to other objects, their reference count is decremented. Those other objects may be deallocated in turn, if this decrement makes their reference count become zero, and so on. (There's an obvious problem with objects that reference each other here; for now, the solution is "don't do that.")

Reference counts are always manipulated explicitly. The normal way is to use the macro  $Py\_INCREF()$  to increment an object's reference count by one, and  $Py\_DECREF()$  to decrement it by one. The  $Py\_DECREF()$  macro is considerably more complex than the incref one, since it must check whether the reference count becomes zero and then cause the object's deallocator to be called. The deallocator is a function pointer contained in the object's type structure. The type-specific deallocator takes care of decrementing the reference counts for other objects contained in the object if this is a compound object type, such as a list, as well as performing any additional finalization that's needed. There's no chance that the reference count can overflow; at least as many bits are used to hold the reference count as there are distinct memory locations in virtual memory (assuming sizeof( $Py\_ssize\_t$ ) >= sizeof(void\*). Thus, the reference count increment is a simple operation.

It is not necessary to increment an object's reference count for every local variable that contains a pointer to an object. In theory, the object's reference count goes up by one when the variable is made to point to it and it goes down by one when the variable goes out of scope. However, these two cancel each other out, so at the end the reference count hasn't changed. The only real reason to use the reference count is to prevent the object from being deallocated as long as our variable is pointing to it. If we know that there is at least one other reference to the object that lives at least as long as our variable, there is no need to increment the reference count temporarily. An important situation where this arises is in objects that are passed as arguments to C functions in an extension module that are called from Python; the call mechanism guarantees to hold a reference to every argument for the duration of the call.

However, a common pitfall is to extract an object from a list and hold on to it for a while without incrementing its reference count. Some other operation might conceivably remove the object from the list, decrementing its reference count and possibly deallocating it. The real danger is that innocent-looking operations may invoke arbitrary Python code which could do this; there is a code path which allows control to flow back to the user from a  $Py\_DECREF()$ , so almost any operation is potentially dangerous.

A safe approach is to always use the generic operations (functions whose name begins with PyObject\_, PyNumber\_, PySequence\_ or PyMapping\_). These operations always increment the reference count of the object they return. This leaves the caller with the responsibility to call  $Py\_DECREF()$  when they are done with the result; this soon becomes second nature.

### **Reference Count Details**

The reference count behavior of functions in the Python/C API is best explained in terms of *ownership of references*. Ownership pertains to references, never to objects (objects are not owned: they are always shared). "Owning a reference" means being responsible for calling Py\_DECREF on it when the reference is no longer needed. Ownership can also be transferred, meaning that the code that receives ownership of the reference then becomes responsible for eventually decref'ing it by calling Py\_DECREF() or Py\_XDECREF() when it's no longer needed—or passing on this responsibility (usually to its caller). When a function passes ownership of a reference on to its caller, the caller is said to receive a *new* reference. When no ownership is transferred, the caller is said to *borrow* the reference. Nothing needs to be done for a borrowed reference.

Conversely, when a calling function passes in a reference to an object, there are two possibilities: the function *steals* a reference to the object, or it does not. *Stealing a reference* means that when you pass a reference to a function, that function assumes that it now owns that reference, and you are not responsible for it any longer.

Few functions steal references; the two notable exceptions are <code>PyList\_SetItem()</code> and <code>PyTuple\_SetItem()</code>, which steal a reference to the item (but not to the tuple or list into which the item is put!). These functions were designed to steal a reference because of a common idiom for populating a tuple or list with newly created objects; for example, the code to create the tuple (1, 2, "three") could look like this (forgetting about error handling for the moment; a better way to code this is shown below):

```
PyObject *t;

t = PyTuple_New(3);
PyTuple_SetItem(t, 0, PyLong_FromLong(1L));
PyTuple_SetItem(t, 1, PyLong_FromLong(2L));
PyTuple_SetItem(t, 2, PyUnicode_FromString("three"));
```

Here,  $PyLong\_FromLong()$  returns a new reference which is immediately stolen by  $PyTuple\_SetItem()$ . When you want to keep using an object although the reference to it will be stolen, use  $Py\_INCREF()$  to grab another reference before calling the reference-stealing function.

Incidentally,  $PyTuple\_SetItem()$  is the *only* way to set tuple items;  $PySequence\_SetItem()$  and  $PyObject\_SetItem()$  refuse to do this since tuples are an immutable data type. You should only use  $PyTuple\_SetItem()$  for tuples that you are creating yourself.

Equivalent code for populating a list can be written using PyList\_New() and PyList\_SetItem().

However, in practice, you will rarely use these ways of creating and populating a tuple or list. There's a generic function,  $Py\_BuildValue()$ , that can create most common objects from C values, directed by a *format string*. For example, the above two blocks of code could be replaced by the following (which also takes care of the error checking):

```
PyObject *tuple, *list;

tuple = Py_BuildValue("(iis)", 1, 2, "three");
list = Py_BuildValue("[iis]", 1, 2, "three");
```

It is much more common to use PyObject\_SetItem() and friends with items whose references you are only borrowing, like arguments that were passed in to the function you are writing. In that case, their behaviour regarding reference counts is much saner, since you don't have to increment a reference count so you can give a reference away ("have it be stolen"). For example, this function sets all items of a list (actually, any mutable sequence) to a given item:

```
int
set_all(PyObject *target, PyObject *item)
{
    Py_ssize_t i, n;
    n = PyObject_Length(target);
    if (n < 0)
        return -1;
    for (i = 0; i < n; i++) {
        PyObject *index = PyLong_FromSsize_t(i);
        if (!index)
            return -1;
        if (PyObject_SetItem(target, index, item) < 0) {
            Py_DECREF(index);
            return -1;
        }
        Py_DECREF(index);
    }
    return 0;
}</pre>
```

The situation is slightly different for function return values. While passing a reference to most functions does not change your ownership responsibilities for that reference, many functions that return a reference to an object give you ownership of the reference. The reason is simple: in many cases, the returned object is created on the fly, and the reference you get is the only reference to the object. Therefore, the generic functions that return object references, like  $PyObject\_GetItem()$  and  $PySequence\_GetItem()$ , always return a new reference (the caller becomes the owner of the reference).

It is important to realize that whether you own a reference returned by a function depends on which function you call only — the plumage (the type of the object passed as an argument to the function) doesn't enter into it! Thus, if you extract an item from a list using <code>PyList\_GetItem()</code>, you don't own the reference — but if you obtain the same item from the same list using <code>PySequence\_GetItem()</code> (which happens to take exactly the same arguments), you do own a reference to the returned object.

Here is an example of how you could write a function that computes the sum of the items in a list of integers; once using  $PyList\_GetItem()$ , and once using  $PySequence\_GetItem()$ .

```
long
sum_list(PyObject *list)
{
    Py_ssize_t i, n;
    long total = 0, value;
    PyObject *item;
```

(continues on next page)

(continued from previous page)

```
n = PyList_Size(list);
if (n < 0)
    return -1; /* Not a list */
for (i = 0; i < n; i++) {
    item = PyList_GetItem(list, i); /* Can't fail */
    if (!PyLong_Check(item)) continue; /* Skip non-integers */
    value = PyLong_AsLong(item);
    if (value == -1 && PyErr_Occurred())
        /* Integer too big to fit in a C long, bail out */
        return -1;
    total += value;
}
return total;
}</pre>
```

```
long
sum_sequence(PyObject *sequence)
    Py_ssize_t i, n;
    long total = 0, value;
   PyObject *item;
    n = PySequence_Length(sequence);
   if (n < 0)
        return -1; /* Has no length */
    for (i = 0; i < n; i++) {</pre>
        item = PySequence_GetItem(sequence, i);
        if (item == NULL)
            return -1; /* Not a sequence, or other failure */
        if (PyLong_Check(item)) {
            value = PyLong_AsLong(item);
            Py_DECREF(item);
            if (value == -1 && PyErr_Occurred())
                /* Integer too big to fit in a C long, bail out */
                return -1;
            total += value;
        else {
            Py_DECREF(item); /* Discard reference ownership */
    return total;
```

## **1.4.2 Types**

There are few other data types that play a significant role in the Python/C API; most are simple C types such as int, long, double and char\*. A few structure types are used to describe static tables used to list the functions exported by a module or the data attributes of a new object type, and another is used to describe the value of a complex number. These will be discussed together with the functions that use them.

## 1.5 Exceptions

The Python programmer only needs to deal with exceptions if specific error handling is required; unhandled exceptions are automatically propagated to the caller, then to the caller's caller, and so on, until they reach the top-level interpreter, where they are reported to the user accompanied by a stack traceback.

For C programmers, however, error checking always has to be explicit. All functions in the Python/C API can raise exceptions, unless an explicit claim is made otherwise in a function's documentation. In general, when a function encounters an error, it sets an exception, discards any object references that it owns, and returns an error indicator. If not documented otherwise, this indicator is either *NULL* or -1, depending on the function's return type. A few functions return a Boolean true/false result, with false indicating an error. Very few functions return no explicit error indicator or have an ambiguous return value, and require explicit testing for errors with <code>PyErr\_Occurred()</code>. These exceptions are always explicitly documented.

Exception state is maintained in per-thread storage (this is equivalent to using global storage in an unthreaded application). A thread can be in one of two states: an exception has occurred, or not. The function  $PyErr\_Occurred()$  can be used to check for this: it returns a borrowed reference to the exception type object when an exception has occurred, and NULL otherwise. There are a number of functions to set the exception state:  $PyErr\_SetString()$  is the most common (though not the most general) function to set the exception state, and  $PyErr\_Clear()$  clears the exception state.

The full exception state consists of three objects (all of which can be *NULL*): the exception type, the corresponding exception value, and the traceback. These have the same meanings as the Python result of <code>sys.exc\_info()</code>; however, they are not the same: the Python objects represent the last exception being handled by a Python <code>try...except</code> statement, while the C level exception state only exists while an exception is being passed on between C functions until it reaches the Python bytecode interpreter's main loop, which takes care of transferring it to <code>sys.exc\_info()</code> and friends.

Note that starting with Python 1.5, the preferred, thread-safe way to access the exception state from Python code is to call the function <code>sys.exc\_info()</code>, which returns the per-thread exception state for Python code. Also, the semantics of both ways to access the exception state have changed so that a function which catches an exception will save and restore its thread's exception state so as to preserve the exception state of its caller. This prevents common bugs in exception handling code caused by an innocent-looking function overwriting the exception being handled; it also reduces the often unwanted lifetime extension for objects that are referenced by the stack frames in the traceback.

As a general principle, a function that calls another function to perform some task should check whether the called function raised an exception, and if so, pass the exception state on to its caller. It should discard any object references that it owns, and return an error indicator, but it should *not* set another exception — that would overwrite the exception that was just raised, and lose important information about the exact cause of the error.

A simple example of detecting exceptions and passing them on is shown in the sum\_sequence() example above. It so happens that this example doesn't need to clean up any owned references when it detects an error. The following example function shows some error cleanup. First, to remind you why you like Python, we show the equivalent Python code:

```
def incr_item(dict, key):
    try:
        item = dict[key]
    except KeyError:
        item = 0
    dict[key] = item + 1
```

Here is the corresponding C code, in all its glory:

```
int
incr_item(PyObject *dict, PyObject *key)
{
    /* Objects all initialized to NULL for Py_XDECREF */
    PyObject *item = NULL, *const_one = NULL, *incremented_item = NULL;
```

(continues on next page)

1.5. Exceptions 9

(continued from previous page)

```
int rv = -1; /* Return value initialized to -1 (failure) */
   item = PyObject_GetItem(dict, key);
   if (item == NULL) {
       /* Handle KeyError only: */
       if (!PyErr_ExceptionMatches(PyExc_KeyError))
       /* Clear the error and use zero: */
       PyErr_Clear();
       item = PyLong_FromLong(0L);
       if (item == NULL)
           goto error;
   }
   const_one = PyLong_FromLong(1L);
   if (const_one == NULL)
       goto error;
   incremented_item = PyNumber_Add(item, const_one);
   if (incremented_item == NULL)
       goto error;
   if (PyObject_SetItem(dict, key, incremented_item) < 0)</pre>
       goto error;
   rv = 0; /* Success */
   /* Continue with cleanup code */
error:
   /* Cleanup code, shared by success and failure path */
   /* Use Py_XDECREF() to ignore NULL references */
   Py_XDECREF (item);
   Py_XDECREF (const_one);
   Py_XDECREF(incremented_item);
   return rv; /* -1 for error, 0 for success */
```

This example represents an endorsed use of the goto statement in C! It illustrates the use of  $PyErr\_ExceptionMatches()$  and  $PyErr\_Clear()$  to handle specific exceptions, and the use of  $Py\_XDECREF()$  to dispose of owned references that may be NULL (note the 'X' in the name;  $Py\_DECREF()$  would crash when confronted with a NULL reference). It is important that the variables used to hold owned references are initialized to NULL for this to work; likewise, the proposed return value is initialized to  $Py\_DECREF()$  and only set to success after the final call made is successful.

## 1.6 Embedding Python

The one important task that only embedders (as opposed to extension writers) of the Python interpreter have to worry about is the initialization, and possibly the finalization, of the Python interpreter. Most functionality of the interpreter can only be used after the interpreter has been initialized.

The basic initialization function is  $Py_Initialize()$ . This initializes the table of loaded modules, and creates the fundamental modules builtins, \_\_main\_\_, and sys. It also initializes the module search path (sys.path).

Py\_Initialize() does not set the "script argument list" (sys.argv). If this variable is needed by Python code that

will be executed later, it must be set explicitly with a call to PySys\_SetArgvEx(argc, argv, updatepath) after the call to Py\_Initialize().

On most systems (in particular, on Unix and Windows, although the details are slightly different),  $Py\_Initialize()$  calculates the module search path based upon its best guess for the location of the standard Python interpreter executable, assuming that the Python library is found in a fixed location relative to the Python interpreter executable. In particular, it looks for a directory named lib/pythonX. Y relative to the parent directory where the executable named python is found on the shell command search path (the environment variable PATH).

For instance, if the Python executable is found in /usr/local/bin/python, it will assume that the libraries are in / usr/local/lib/pythonX. Y. (In fact, this particular path is also the "fallback" location, used when no executable file named python is found along PATH.) The user can override this behavior by setting the environment variable PYTHONHOME, or insert additional directories in front of the standard path by setting PYTHONPATH.

The embedding application can steer the search by calling  $Py\_SetProgramName(file)$  before calling  $Py\_Initialize()$ . Note that PYTHONHOME still overrides this and PYTHONPATH is still inserted in front of the standard path. An application that requires total control has to provide its own implementation of  $Py\_GetPath()$ ,  $Py\_GetPrefix()$ ,  $Py\_GetExecPrefix()$ , and  $Py\_GetProgramFullPath()$  (all defined in Modules/getpath.c).

Sometimes, it is desirable to "uninitialize" Python. For instance, the application may want to start over (make another call to  $Py\_Initialize()$ ) or the application is simply done with its use of Python and wants to free memory allocated by Python. This can be accomplished by calling  $Py\_FinalizeEx()$ . The function  $Py\_IsInitialized()$  returns true if Python is currently in the initialized state. More information about these functions is given in a later chapter. Notice that  $Py\_FinalizeEx()$  does *not* free all memory allocated by the Python interpreter, e.g. memory allocated by extension modules currently cannot be released.

## 1.7 Debugging Builds

Python can be built with several macros to enable extra checks of the interpreter and extension modules. These checks tend to add a large amount of overhead to the runtime so they are not enabled by default.

A full list of the various types of debugging builds is in the file Misc/SpecialBuilds.txt in the Python source distribution. Builds are available that support tracing of reference counts, debugging the memory allocator, or low-level profiling of the main interpreter loop. Only the most frequently-used builds will be described in the remainder of this section.

Compiling the interpreter with the Py\_DEBUG macro defined produces what is generally meant by "a debug build" of Python. Py\_DEBUG is enabled in the Unix build by adding --with-pydebug to the ./configure command. It is also implied by the presence of the not-Python-specific \_DEBUG macro. When Py\_DEBUG is enabled in the Unix build, compiler optimization is disabled.

In addition to the reference count debugging described below, the following extra checks are performed:

- Extra checks are added to the object allocator.
- Extra checks are added to the parser and compiler.
- Downcasts from wide types to narrow types are checked for loss of information.
- A number of assertions are added to the dictionary and set implementations. In addition, the set object acquires a test\_c\_api() method.
- Sanity checks of the input arguments are added to frame creation.
- The storage for ints is initialized with a known invalid pattern to catch reference to uninitialized digits.
- Low-level tracing and extra exception checking are added to the runtime virtual machine.
- Extra checks are added to the memory arena implementation.

• Extra debugging is added to the thread module.

There may be additional checks not mentioned here.

Defining  $Py\_TRACE\_REFS$  enables reference tracing. When defined, a circular doubly linked list of active objects is maintained by adding two extra fields to every PyObject. Total allocations are tracked as well. Upon exit, all existing references are printed. (In interactive mode this happens after every statement run by the interpreter.) Implied by  $Py\_DEBUG$ .

Please refer to Misc/SpecialBuilds.txt in the Python source distribution for more detailed information.

**CHAPTER** 

**TWO** 

## STABLE APPLICATION BINARY INTERFACE

Traditionally, the C API of Python will change with every release. Most changes will be source-compatible, typically by only adding API, rather than changing existing API or removing API (although some interfaces do get removed after being deprecated first).

Unfortunately, the API compatibility does not extend to binary compatibility (the ABI). The reason is primarily the evolution of struct definitions, where addition of a new field, or changing the type of a field, might not break the API, but can break the ABI. As a consequence, extension modules need to be recompiled for every Python release (although an exception is possible on Unix when none of the affected interfaces are used). In addition, on Windows, extension modules link with a specific pythonXY.dll and need to be recompiled to link with a newer one.

Since Python 3.2, a subset of the API has been declared to guarantee a stable ABI. Extension modules wishing to use this API (called "limited API") need to define  $Py\_LIMITED\_API$ . A number of interpreter details then become hidden from the extension module; in return, a module is built that works on any 3.x version (x>=2) without recompilation.

In some cases, the stable ABI needs to be extended with new functions. Extension modules wishing to use these new APIs need to set Py\_LIMITED\_API to the PY\_VERSION\_HEX value (see *API and ABI Versioning*) of the minimum Python version they want to support (e.g. 0x03030000 for Python 3.3). Such modules will work on all subsequent Python releases, but fail to load (because of missing symbols) on the older releases.

As of Python 3.2, the set of functions available to the limited API is documented in **PEP 384**. In the C API documentation, API elements that are not part of the limited API are marked as "Not part of the limited API."

## THE VERY HIGH LEVEL LAYER

The functions in this chapter will let you execute Python source code given in a file or a buffer, but they will not let you interact in a more detailed way with the interpreter.

Several of these functions accept a start symbol from the grammar as a parameter. The available start symbols are Py\_eval\_input, Py\_file\_input, and Py\_single\_input. These are described following the functions which accept them as parameters.

Note also that several of these functions take FILE\* parameters. One particular issue which needs to be handled carefully is that the FILE structure for different C libraries can be different and incompatible. Under Windows (at least), it is possible for dynamically linked extensions to actually use different libraries, so care should be taken that FILE\* parameters are only passed to these functions if it is certain that they were created by the same library that the Python runtime is using.

## int Py\_Main (int argc, wchar\_t \*\*argv)

The main program for the standard interpreter. This is made available for programs which embed Python. The *argc* and *argv* parameters should be prepared exactly as those which are passed to a C program's main() function (converted to wchar\_t according to the user's locale). It is important to note that the argument list may be modified (but the contents of the strings pointed to by the argument list are not). The return value will be 0 if the interpreter exits normally (i.e., without an exception), 1 if the interpreter exits due to an exception, or 2 if the parameter list does not represent a valid Python command line.

Note that if an otherwise unhandled SystemExit is raised, this function will not return 1, but exit the process, as long as Py\_InspectFlag is not set.

## int Py\_BytesMain (int argc, char \*\*argv)

Similar to Py Main () but argv is an array of bytes strings.

New in version 3.8.

## int **PyRun\_AnyFile** (FILE \*fp, const char \*filename)

This is a simplified interface to PyRun\_AnyFileExFlags() below, leaving *closeit* set to 0 and *flags* set to *NULL*.

## int PyRun\_AnyFileFlags (FILE \*fp, const char \*filename, PyCompilerFlags \*flags)

This is a simplified interface to PyRun\_AnyFileExFlags () below, leaving the closeit argument set to 0.

## int **PyRun\_AnyFileEx** (FILE \*fp, const char \*filename, int closeit)

This is a simplified interface to PyRun\_AnyFileExFlags () below, leaving the flags argument set to NULL.

## int PyRun\_AnyFileExFlags (FILE \*fp, const char \*filename, int closeit, PyCompilerFlags \*flags)

If fp refers to a file associated with an interactive device (console or terminal input or Unix pseudo-terminal), return the value of  $PyRun\_InteractiveLoop()$ , otherwise return the result of  $PyRun\_SimpleFile()$ . filename is decoded from the filesystem encoding (sys.getfilesystemencoding()). If filename is NULL, this function uses "???" as the filename.

#### int PyRun\_SimpleString (const char \*command)

This is a simplified interface to PyRun\_SimpleStringFlags() below, leaving the PyCompilerFlags\* argument set to NULL.

## int PyRun\_SimpleStringFlags (const char \*command, PyCompilerFlags \*flags)

Executes the Python source code from *command* in the \_\_main\_\_ module according to the *flags* argument. If \_\_main\_\_ does not already exist, it is created. Returns 0 on success or -1 if an exception was raised. If there was an error, there is no way to get the exception information. For the meaning of *flags*, see below.

Note that if an otherwise unhandled SystemExit is raised, this function will not return -1, but exit the process, as long as Py\_InspectFlag is not set.

## int **PyRun\_SimpleFile** (FILE \*fp, const char \*filename)

This is a simplified interface to PyRun\_SimpleFileExFlags() below, leaving closeit set to 0 and flags set to NULL.

## int PyRun\_SimpleFileEx (FILE \*fp, const char \*filename, int closeit)

This is a simplified interface to PyRun\_SimpleFileExFlags () below, leaving flags set to NULL.

## int PyRun\_SimpleFileExFlags (FILE \*fp, const char \*filename, int closeit, PyCompilerFlags \*flags)

Similar to <code>PyRun\_SimpleStringFlags()</code>, but the Python source code is read from <code>fp</code> instead of an inmemory string. <code>filename</code> should be the name of the file, it is decoded from the filesystem encoding (<code>sys.getfilesystemencoding()</code>). If <code>closeit</code> is true, the file is closed before <code>PyRun\_SimpleFileExFlags</code> returns.

**Note:** On Windows, *fp* should be opened as binary mode (e.g. fopen (filename, "rb"). Otherwise, Python may not handle script file with LF line ending correctly.

## int PyRun\_InteractiveOne (FILE \*fp, const char \*filename)

This is a simplified interface to PyRun\_InteractiveOneFlags () below, leaving flags set to NULL.

## int PyRun\_InteractiveOneFlags (FILE \*fp, const char \*filename, PyCompilerFlags \*flags)

Read and execute a single statement from a file associated with an interactive device according to the *flags* argument. The user will be prompted using sys.ps1 and sys.ps2. *filename* is decoded from the filesystem encoding (sys.getfilesystemencoding()).

Returns 0 when the input was executed successfully, -1 if there was an exception, or an error code from the errorde.h include file distributed as part of Python if there was a parse error. (Note that errorde.h is not included by Python.h, so must be included specifically if needed.)

## int PyRun InteractiveLoop (FILE \*fp, const char \*filename)

This is a simplified interface to PyRun\_InteractiveLoopFlags () below, leaving flags set to NULL.

## int PyRun\_InteractiveLoopFlags (FILE \*fp, const char \*filename, PyCompilerFlags \*flags)

Read and execute statements from a file associated with an interactive device until EOF is reached. The user will be prompted using sys.ps1 and sys.ps2. *filename* is decoded from the filesystem encoding (sys.getfilesystemencoding()). Returns 0 at EOF or a negative number upon failure.

## int (\*PyOS\_InputHook) (void)

Can be set to point to a function with the prototype int func(void). The function will be called when Python's interpreter prompt is about to become idle and wait for user input from the terminal. The return value is ignored. Overriding this hook can be used to integrate the interpreter's prompt with other event loops, as done in the Modules/\_tkinter.c in the Python source code.

## char\* (\*PyOS\_ReadlineFunctionPointer) (FILE \*, FILE \*, const char \*)

Can be set to point to a function with the prototype char \*func(FILE \*stdin, FILE \*stdout, char \*prompt), overriding the default function used to read a single line of input at the interpreter's prompt. The function is expected to output the string *prompt* if it's not *NULL*, and then read a line of input from the provided

standard input file, returning the resulting string. For example, The readline module sets this hook to provide line-editing and tab-completion features.

The result must be a string allocated by <code>PyMem\_RawMalloc()</code> or <code>PyMem\_RawRealloc()</code>, or <code>NULL</code> if an error occurred.

Changed in version 3.4: The result must be allocated by <code>PyMem\_RawMalloc()</code> or <code>PyMem\_RawRealloc()</code>, instead of being allocated by <code>PyMem\_Malloc()</code> or <code>PyMem\_Realloc()</code>.

- struct \_node\* PyParser\_SimpleParseString (const char \*str, int start)
  - This is a simplified interface to PyParser\_SimpleParseStringFlagsFilename () below, leaving filename set to NULL and flags set to 0.
- struct \_node\* PyParser\_SimpleParseStringFlags (const char \*str, int start, int flags)

  This is a simplified interface to PyParser\_SimpleParseStringFlagsFilename () below, leaving filename set to NULL.
- struct\_node\* PyParser\_SimpleParseStringFlagsFilename (const char \*str, const char \*filename, int start, int flags)

Parse Python source code from *str* using the start token *start* according to the *flags* argument. The result can be used to create a code object which can be evaluated efficiently. This is useful if a code fragment must be evaluated many times. *filename* is decoded from the filesystem encoding (sys.getfilesystemencoding ()).

- struct \_node\* PyParser\_SimpleParseFile (FILE \*fp, const char \*filename, int start)

  This is a simplified interface to PyParser\_SimpleParseFileFlags() below, leaving flags set to 0.
- struct \_node\* PyParser\_SimpleParseFileFlags (FILE \*fp, const char \*filename, int start, int flags)

  Similar to PyParser\_SimpleParseStringFlagsFilename(), but the Python source code is read from fp instead of an in-memory string.
- PyObject\* PyRun\_String (const char \*str, int start, PyObject \*globals, PyObject \*locals)

  Return value: New reference. This is a simplified interface to PyRun\_StringFlags() below, leaving flags set to NULL.
- PyObject\* PyRun\_StringFlags (const char \*str, int start, PyObject \*globals, PyObject \*locals, PyCompiler-Flags \*flags)

Return value: New reference. Execute Python source code from str in the context specified by the objects globals and locals with the compiler flags specified by flags. globals must be a dictionary; locals can be any object that implements the mapping protocol. The parameter start specifies the start token that should be used to parse the source code.

Returns the result of executing the code as a Python object, or NULL if an exception was raised.

- PyObject\* PyRun\_File (FILE \*fp, const char \*filename, int start, PyObject \*globals, PyObject \*locals)

  Return value: New reference. This is a simplified interface to PyRun\_FileExFlags() below, leaving closeit set to 0 and flags set to NULL.
- PyObject\* PyRun\_FileEx (FILE \*fp, const char \*filename, int start, PyObject \*globals, PyObject \*locals, int closeit)

  Return value: New reference. This is a simplified interface to PyRun\_FileExFlags() below, leaving flags set to NULL.
- PyObject\* PyRun\_FileFlags (FILE \*fp, const char \*filename, int start, PyObject \*globals, PyObject \*locals, PyCompilerFlags \*flags)

  Return value: New reference. This is a simplified interface to PyRun\_FileExFlags() below, leaving closeit set to 0.
- PyObject\* PyRun\_FileExFlags (FILE \*fp, const char \*filename, int start, PyObject \*globals, PyObject \*locals, int closeit, PyCompilerFlags \*flags)

  Return value: New reference. Similar to PyRun\_StringFlags(), but the Python source code is read from fp instead of an in-memory string. filename should be the name of the file, it is decoded from the filesystem encoding

(sys.getfilesystemencoding()). If *closeit* is true, the file is closed before *PyRun\_FileExFlags()* returns.

*PyObject\** **Py\_CompileString** (const char \*str, const char \*filename, int start)

*Return value: New reference.* This is a simplified interface to *Py\_CompileStringFlags()* below, leaving *flags* set to *NULL*.

PyObject\* Py\_CompileStringFlags (const char \*str, const char \*filename, int start, PyCompiler-Flags \*flags)

Return value: New reference. This is a simplified interface to Py\_CompileStringExFlags() below, with optimize set to -1.

PyObject\* Py\_CompileStringObject (const char \*str, PyObject \*filename, int start, PyCompiler-Flags \*flags, int optimize)

Return value: New reference. Parse and compile the Python source code in str, returning the resulting code object. The start token is given by start; this can be used to constrain the code which can be compiled and should be Py\_eval\_input, Py\_file\_input, or Py\_single\_input. The filename specified by filename is used to construct the code object and may appear in tracebacks or SyntaxError exception messages. This returns NULL if the code cannot be parsed or compiled.

The integer *optimize* specifies the optimization level of the compiler; a value of -1 selects the optimization level of the interpreter as given by -0 options. Explicit levels are 0 (no optimization; \_\_debug\_\_ is true), 1 (asserts are removed, \_\_debug\_\_ is false) or 2 (docstrings are removed too).

New in version 3.4.

PyObject\* Py\_CompileStringExFlags (const char \*str, const char \*filename, int start, PyCompiler-Flags \*flags, int optimize)

Return value: New reference. Like Py\_CompileStringObject(), but filename is a byte string decoded from the filesystem encoding (os.fsdecode()).

New in version 3.2.

PyObject\* PyEval EvalCode (PyObject \*co, PyObject \*globals, PyObject \*locals)

*Return value: New reference.* This is a simplified interface to  $PyEval\_EvalCodeEx()$ , with just the code object, and global and local variables. The other arguments are set to *NULL*.

```
PyObject* PyEval_EvalCodeEx (PyObject *co, PyObject *globals, PyObject *locals, PyObject *const *args, int argcount, PyObject *const *kws, int kwcount, PyObject *const *defs, int defcount, PyObject *kwdefs, PyObject *closure)
```

Return value: New reference. Evaluate a precompiled code object, given a particular environment for its evaluation. This environment consists of a dictionary of global variables, a mapping object of local variables, arrays of arguments, keywords and defaults, a dictionary of default values for keyword-only arguments and a closure tuple of cells.

### PyFrameObject

The C structure of the objects used to describe frame objects. The fields of this type are subject to change at any time.

PyObject\* PyEval\_EvalFrame (PyFrameObject \*f)

*Return value:* New reference. Evaluate an execution frame. This is a simplified interface to PyEval\_EvalFrameEx(), for backward compatibility.

PyObject\* PyEval\_EvalFrameEx (PyFrameObject \*f, int throwflag)

Return value: New reference. This is the main, unvarnished function of Python interpretation. The code object associated with the execution frame f is executed, interpreting bytecode and executing calls as needed. The additional throwflag parameter can mostly be ignored - if true, then it causes an exception to immediately be thrown; this is used for the throw () methods of generator objects.

Changed in version 3.4: This function now includes a debug assertion to help ensure that it does not silently discard an active exception.

## int PyEval\_MergeCompilerFlags (PyCompilerFlags \*cf)

This function changes the flags of the current evaluation frame, and returns true on success, false on failure.

## int Py\_eval\_input

The start symbol from the Python grammar for isolated expressions; for use with Py\_CompileString().

#### int Py file input

The start symbol from the Python grammar for sequences of statements as read from a file or other source; for use with Py\_CompileString(). This is the symbol to use when compiling arbitrarily long Python source code.

## int Py\_single\_input

The start symbol from the Python grammar for a single statement; for use with Py\_CompileString(). This is the symbol used for the interactive interpreter loop.

## struct PyCompilerFlags

This is the structure used to hold compiler flags. In cases where code is only being compiled, it is passed as int flags, and in cases where code is being executed, it is passed as PyCompilerFlags \*flags. In this case, from \_\_future\_\_ import can modify flags.

Whenever PyCompilerFlags \*flags is NULL, cf\_flags is treated as equal to 0, and any modification due to from \_\_future\_\_ import is discarded.

#### int cf\_flags

Compiler flags.

## int cf\_feature\_version

cf\_feature\_version is the minor Python version. It should be initialized to PY\_MINOR\_VERSION.

The field is ignored by default, it is used if and only if PyCF\_ONLY\_AST flag is set in *cf\_flags*.

Changed in version 3.8: Added *cf\_feature\_version* field.

## int CO\_FUTURE\_DIVISION

This bit can be set in *flags* to cause division operator / to be interpreted as "true division" according to **PEP 238**.

## REFERENCE COUNTING

The macros in this section are used for managing reference counts of Python objects.

#### void **Py INCREF** (*PyObject* \*o)

Increment the reference count for object o. The object must not be NULL; if you aren't sure that it isn't NULL, use  $PY\_XINCREF()$ .

## void Py\_XINCREF (PyObject \*o)

Increment the reference count for object o. The object may be NULL, in which case the macro has no effect.

## void **Py\_DECREF** (*PyObject* \*o)

Decrement the reference count for object o. The object must not be NULL; if you aren't sure that it isn't NULL, use  $Py\_XDECREF()$ . If the reference count reaches zero, the object's type's deallocation function (which must not be NULL) is invoked.

**Warning:** The deallocation function can cause arbitrary Python code to be invoked (e.g. when a class instance with a  $\__del\__()$  method is deallocated). While exceptions in such code are not propagated, the executed code has free access to all Python global variables. This means that any object that is reachable from a global variable should be in a consistent state before  $Py\_DECREF()$  is invoked. For example, code to delete an object from a list should copy a reference to the deleted object in a temporary variable, update the list data structure, and then call  $Py\_DECREF()$  for the temporary variable.

#### void **Py\_XDECREF** (*PyObject* \*o)

Decrement the reference count for object o. The object may be NULL, in which case the macro has no effect; otherwise the effect is the same as for  $Py\_DECREF()$ , and the same warning applies.

## void Py\_CLEAR (PyObject \*o)

Decrement the reference count for object o. The object may be NULL, in which case the macro has no effect; otherwise the effect is the same as for  $PY\_DECREF()$ , except that the argument is also set to NULL. The warning for  $PY\_DECREF()$  does not apply with respect to the object passed because the macro carefully uses a temporary variable and sets the argument to NULL before decrementing its reference count.

It is a good idea to use this macro whenever decrementing the reference count of an object that might be traversed during garbage collection.

The following functions are for runtime dynamic embedding of Python: Py\_IncRef(PyObject \*o), Py\_DecRef(PyObject \*o). They are simply exported function versions of Py\_XINCREF() and Py XDECREF(), respectively.

The following functions or macros are only for use within the interpreter core: \_Py\_Dealloc(), \_Py\_ForgetReference(), \_Py\_NewReference(), as well as the global variable \_Py\_RefTotal.

**CHAPTER** 

**FIVE** 

## **EXCEPTION HANDLING**

The functions described in this chapter will let you handle and raise Python exceptions. It is important to understand some of the basics of Python exception handling. It works somewhat like the POSIX errno variable: there is a global indicator (per thread) of the last error that occurred. Most C API functions don't clear this on success, but will set it to indicate the cause of the error on failure. Most C API functions also return an error indicator, usually *NULL* if they are supposed to return a pointer, or -1 if they return an integer (exception: the PyArg\_\* () functions return 1 for success and 0 for failure).

Concretely, the error indicator consists of three object pointers: the exception's type, the exception's value, and the traceback object. Any of those pointers can be NULL if non-set (although some combinations are forbidden, for example you can't have a non-NULL traceback if the exception type is NULL).

When a function must fail because some function it called failed, it generally doesn't set the error indicator; the function it called already set it. It is responsible for either handling the error and clearing the exception or returning after cleaning up any resources it holds (such as object references or memory allocations); it should *not* continue normally if it is not prepared to handle the error. If returning due to an error, it is important to indicate to the caller that an error has been set. If the error is not handled or carefully propagated, additional calls into the Python/C API may not behave as intended and may fail in mysterious ways.

**Note:** The error indicator is **not** the result of <code>sys.exc\_info()</code>. The former corresponds to an exception that is not yet caught (and is therefore still propagating), while the latter returns an exception after it is caught (and has therefore stopped propagating).

## 5.1 Printing and clearing

```
void PyErr_Clear()
```

Clear the error indicator. If the error indicator is not set, there is no effect.

```
void PyErr_PrintEx (int set_sys_last_vars)
```

Print a standard traceback to sys.stderr and clear the error indicator. **Unless** the error is a SystemExit, in that case no traceback is printed and the Python process will exit with the error code specified by the SystemExit instance.

Call this function **only** when the error indicator is set. Otherwise it will cause a fatal error!

If set\_sys\_last\_vars is nonzero, the variables sys.last\_type, sys.last\_value and sys.last\_traceback will be set to the type, value and traceback of the printed exception, respectively.

```
void PyErr_Print()
```

Alias for PyErr\_PrintEx(1).

#### void PyErr WriteUnraisable (PyObject \*obj)

Call sys.unraisablehook() using the current exception and obj argument.

This utility function prints a warning message to sys.stderr when an exception has been set but it is impossible for the interpreter to actually raise the exception. It is used, for example, when an exception occurs in an \_\_del\_\_() method.

The function is called with a single argument *obj* that identifies the context in which the unraisable exception occurred. If possible, the repr of *obj* will be printed in the warning message.

An exception must be set when calling this function.

## 5.2 Raising exceptions

These functions help you set the current thread's error indicator. For convenience, some of these functions will always return a NULL pointer for use in a return statement.

```
void PyErr_SetString (PyObject *type, const char *message)
```

This is the most common way to set the error indicator. The first argument specifies the exception type; it is normally one of the standard exceptions, e.g. PyExc\_RuntimeError. You need not increment its reference count. The second argument is an error message; it is decoded from 'utf-8'.

```
void PyErr_SetObject (PyObject *type, PyObject *value)
```

This function is similar to PyErr\_SetString() but lets you specify an arbitrary Python object for the "value" of the exception.

```
PyObject* PyErr_Format (PyObject *exception, const char *format, ...)
```

Return value: Always NULL. This function sets the error indicator and returns NULL. exception should be a Python exception class. The *format* and subsequent parameters help format the error message; they have the same meaning and values as in PyUnicode\_FromFormat(). format is an ASCII-encoded string.

```
PyObject* PyErr_FormatV (PyObject *exception, const char *format, va_list vargs)
```

Return value: Always NULL. Same as  $PyErr\_Format()$ , but taking a  $va\_list$  argument rather than a variable number of arguments.

New in version 3.5.

## void PyErr\_SetNone (PyObject \*type)

This is a shorthand for PyErr\_SetObject (type, Py\_None).

## int PyErr\_BadArgument()

This is a shorthand for PyErr\_SetString (PyExc\_TypeError, message), where *message* indicates that a built-in operation was invoked with an illegal argument. It is mostly for internal use.

```
PyObject* PyErr_NoMemory()
```

Return value: Always NULL. This is a shorthand for PyErr\_SetNone (PyExc\_MemoryError); it returns NULL so an object allocation function can write return PyErr\_NoMemory (); when it runs out of memory.

```
PyObject* PyErr_SetFromErrno (PyObject *type)
```

Return value: Always NULL. This is a convenience function to raise an exception when a C library function has returned an error and set the C variable errno. It constructs a tuple object whose first item is the integer errno value and whose second item is the corresponding error message (gotten from strerror()), and then calls PyErr\_SetObject(type, object). On Unix, when the errno value is EINTR, indicating an interrupted system call, this calls PyErr\_CheckSignals(), and if that set the error indicator, leaves it set to that. The function always returns NULL, so a wrapper function around a system call can write return PyErr\_SetFromErrno(type); when the system call returns an error.

## PyObject\* PyErr\_SetFromErrnoWithFilenameObject (PyObject \*type, PyObject \*filenameObject)

Return value: Always NULL. Similar to PyErr\_SetFromErrno(), with the additional behavior that if filenameObject is not NULL, it is passed to the constructor of type as a third parameter. In the case of OSError exception, this is used to define the filename attribute of the exception instance.

## PyObject\* PyErr\_SetFromErrnoWithFilenameObjects (PyObject \*type, PyObject \*filenameObject, PyObject \*filenameObject)

Return value: Always NULL. Similar to PyErr\_SetFromErrnoWithFilenameObject(), but takes a second filename object, for raising errors when a function that takes two filenames fails.

New in version 3.4.

## PyObject\* PyErr\_SetFromErrnoWithFilename (PyObject \*type, const char \*filename)

Return value: Always NULL. Similar to PyErr\_SetFromErrnoWithFilenameObject(), but the filename is given as a C string. filename is decoded from the filesystem encoding (os.fsdecode()).

## PyObject\* PyErr\_SetFromWindowsErr (int ierr)

Return value: Always NULL. This is a convenience function to raise WindowsError. If called with ierr of 0, the error code returned by a call to GetLastError() is used instead. It calls the Win32 function FormatMessage() to retrieve the Windows description of error code given by ierr or GetLastError(), then it constructs a tuple object whose first item is the ierr value and whose second item is the corresponding error message (gotten from FormatMessage()), and then calls PyErr\_SetObject(PyExc\_WindowsError, object). This function always returns NULL.

Availability: Windows.

## PyObject\* PyErr\_SetExcFromWindowsErr (PyObject \*type, int ierr)

*Return value:* Always NULL. Similar to PyErr\_SetFromWindowsErr(), with an additional parameter specifying the exception type to be raised.

Availability: Windows.

#### PyObject\* PyErr SetFromWindowsErrWithFilename (int ierr, const char \*filename)

*Return value:* Always NULL. Similar to PyErr\_SetFromWindowsErrWithFilenameObject(), but the filename is given as a C string. filename is decoded from the filesystem encoding (os.fsdecode()).

Availability: Windows.

## PyObject\* PyErr\_SetExcFromWindowsErrWithFilenameObject (PyObject \*type, int ierr, PyObject \*filename)

*Return value:* Always NULL. Similar to PyErr\_SetFromWindowsErrWithFilenameObject(), with an additional parameter specifying the exception type to be raised.

Availability: Windows.

## PyObject\* PyErr\_SetExcFromWindowsErrWithFilenameObjects (PyObject \*type, int ierr, PyObject \*filename, PyO

name2)

Return value: Always NULL. Similar to PyErr\_SetExcFromWindowsErrWithFilenameObject (), but accepts a second filename object.

Availability: Windows.

New in version 3.4.

## $PyObject * \verb"PyErr_SetExcFromWindowsErrWithFilename" (PyObject * type, int ierr, const char * file-type, const c$

name)
Return value: Always NULL. Similar to PyErr\_SetFromWindowsErrWithFilename(), with an addi-

tional parameter specifying the exception type to be raised.

Availability: Windows.

#### PyObject\* PyErr\_SetImportError (PyObject \*msg, PyObject \*name, PyObject \*path)

Return value: Always NULL. This is a convenience function to raise ImportError. msg will be set as the exception's message string. name and path, both of which can be NULL, will be set as the ImportError's respective name and path attributes.

New in version 3.3.

## void PyErr\_SyntaxLocationObject (PyObject \*filename, int lineno, int col\_offset)

Set file, line, and offset information for the current exception. If the current exception is not a SyntaxError, then it sets additional attributes, which make the exception printing subsystem think the exception is a SyntaxError.

New in version 3.4.

### void PyErr\_SyntaxLocationEx (const char \*filename, int lineno, int col\_offset)

Like PyErr\_SyntaxLocationObject(), but filename is a byte string decoded from the filesystem encoding (os.fsdecode()).

New in version 3.2.

## void PyErr\_SyntaxLocation (const char \*filename, int lineno)

Like PyErr\_SyntaxLocationEx(), but the col\_offset parameter is omitted.

#### void PyErr\_BadInternalCall()

This is a shorthand for PyErr\_SetString (PyExc\_SystemError, message), where *message* indicates that an internal operation (e.g. a Python/C API function) was invoked with an illegal argument. It is mostly for internal use.

## 5.3 Issuing warnings

Use these functions to issue warnings from C code. They mirror similar functions exported by the Python warnings module. They normally print a warning message to *sys.stderr*; however, it is also possible that the user has specified that warnings are to be turned into errors, and in that case they will raise an exception. It is also possible that the functions raise an exception because of a problem with the warning machinery. The return value is 0 if no exception is raised, or -1 if an exception is raised. (It is not possible to determine whether a warning message is actually printed, nor what the reason is for the exception; this is intentional.) If an exception is raised, the caller should do its normal exception handling (for example,  $P_{Y\_DECREF}$  () owned references and return an error value).

## int PyErr\_WarnEx (PyObject \*category, const char \*message, Py\_ssize\_t stack\_level)

Issue a warning message. The *category* argument is a warning category (see below) or *NULL*; the *message* argument is a UTF-8 encoded string. *stack\_level* is a positive number giving a number of stack frames; the warning will be issued from the currently executing line of code in that stack frame. A *stack\_level* of 1 is the function calling <code>PyErr\_WarnEx()</code>, 2 is the function above that, and so forth.

Warning categories must be subclasses of PyExc\_Warning; PyExc\_Warning is a subclass of PyExc\_Exception; the default warning category is PyExc\_RuntimeWarning. The standard Python warning categories are available as global variables whose names are enumerated at *Standard Warning Categories*.

For information about warning control, see the documentation for the warnings module and the -W option in the command line documentation. There is no C API for warning control.

```
PyObject* PyErr_SetImportErrorSubclass (PyObject *exception, PyObject *msg, PyObject *name, Py-Object *path)
```

Return value: Always NULL. Much like PyErr\_SetImportError() but this function allows for specifying a subclass of ImportError to raise.

New in version 3.6.

int PyErr\_WarnExplicitObject (PyObject \*category, PyObject \*message, PyObject \*filename, int lineno, PyObject \*module, PyObject \*registry)

Issue a warning message with explicit control over all warning attributes. This is a straightforward wrapper around the Python function warnings.warn\_explicit(), see there for more information. The *module* and *registry* arguments may be set to *NULL* to get the default effect described there.

New in version 3.4.

int PyErr\_WarnExplicit (*PyObject \*category*, const char \*message, const char \*filename, int lineno, const char \*module, *PyObject \*registry*)

Similar to PyErr\_WarnExplicitObject () except that message and module are UTF-8 encoded strings, and filename is decoded from the filesystem encoding (os.fsdecode()).

int PyErr\_WarnFormat (PyObject \*category, Py\_ssize\_t stack\_level, const char \*format, ...)

Function similar to PyErr\_WarnEx(), but use PyUnicode\_FromFormat() to format the warning message. format is an ASCII-encoded string.

New in version 3.2.

int PyErr\_ResourceWarning (PyObject \*source, Py\_ssize\_t stack\_level, const char \*format, ...)

Function similar to PyErr\_WarnFormat(), but category is ResourceWarning and pass source to warnings.WarningMessage().

New in version 3.6.

## 5.4 Querying the error indicator

### PyObject\* PyErr\_Occurred()

Return value: Borrowed reference. Test whether the error indicator is set. If set, return the exception type (the first argument to the last call to one of the PyErr\_Set\*() functions or to  $PyErr_Restore()$ ). If not set, return NULL. You do not own a reference to the return value, so you do not need to  $Py_DECREF()$  it.

**Note:** Do not compare the return value to a specific exception; use <code>PyErr\_ExceptionMatches()</code> instead, shown below. (The comparison could easily fail since the exception may be an instance instead of a class, in the case of a class exception, or it may be a subclass of the expected exception.)

### int PyErr ExceptionMatches (PyObject \*exc)

Equivalent to PyErr\_GivenExceptionMatches (PyErr\_Occurred(), exc). This should only be called when an exception is actually set; a memory access violation will occur if no exception has been raised.

int PyErr\_GivenExceptionMatches (PyObject \*given, PyObject \*exc)

Return true if the *given* exception matches the exception type in *exc*. If *exc* is a class object, this also returns true when *given* is an instance of a subclass. If *exc* is a tuple, all exception types in the tuple (and recursively in subtuples) are searched for a match.

```
void PyErr_Fetch (PyObject **ptype, PyObject **ptraceback)
```

Retrieve the error indicator into three variables whose addresses are passed. If the error indicator is not set, set all three variables to *NULL*. If it is set, it will be cleared and you own a reference to each object retrieved. The value and traceback object may be *NULL* even when the type object is not.

**Note:** This function is normally only used by code that needs to catch exceptions or by code that needs to save and restore the error indicator temporarily, e.g.:

```
PyObject *type, *value, *traceback;
PyErr_Fetch(&type, &value, &traceback);

/* ... code that might produce other errors ... */
PyErr_Restore(type, value, traceback);
}
```

## void PyErr\_Restore (PyObject \*type, PyObject \*value, PyObject \*traceback)

Set the error indicator from the three objects. If the error indicator is already set, it is cleared first. If the objects are *NULL*, the error indicator is cleared. Do not pass a *NULL* type and non-*NULL* value or traceback. The exception type should be a class. Do not pass an invalid exception type or value. (Violating these rules will cause subtle problems later.) This call takes away a reference to each object: you must own a reference to each object before the call and after the call you no longer own these references. (If you don't understand this, don't use this function. I warned you.)

**Note:** This function is normally only used by code that needs to save and restore the error indicator temporarily. Use  $PyErr\_Fetch()$  to save the current error indicator.

## void PyErr\_NormalizeException (PyObject\*\*exc, PyObject\*\*val, PyObject\*\*tb)

Under certain circumstances, the values returned by  $PyErr\_Fetch()$  below can be "unnormalized", meaning that \*exc is a class object but \*val is not an instance of the same class. This function can be used to instantiate the class in that case. If the values are already normalized, nothing happens. The delayed normalization is implemented to improve performance.

**Note:** This function *does not* implicitly set the \_\_traceback\_\_ attribute on the exception value. If setting the traceback appropriately is desired, the following additional snippet is needed:

```
if (tb != NULL) {
    PyException_SetTraceback(val, tb);
}
```

## void PyErr\_GetExcInfo (PyObject \*\*ptype, PyObject \*\*pvalue, PyObject \*\*ptraceback)

Retrieve the exception info, as known from sys.exc\_info(). This refers to an exception that was *already* caught, not to an exception that was freshly raised. Returns new references for the three objects, any of which may be *NULL*. Does not modify the exception info state.

**Note:** This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use  $PyErr\_SetExcInfo()$  to restore or clear the exception state.

New in version 3.3.

#### void PyErr\_SetExcInfo (PyObject \*type, PyObject \*value, PyObject \*traceback)

Set the exception info, as known from  $sys.exc\_info()$ . This refers to an exception that was *already caught*, not to an exception that was freshly raised. This function steals the references of the arguments. To clear the exception state, pass *NULL* for all three arguments. For general rules about the three arguments, see  $PyErr\_Restore()$ .

**Note:** This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code

needs to save and restore the exception state temporarily. Use  $PyErr\_GetExcInfo()$  to read the exception state.

New in version 3.3.

## 5.5 Signal Handling

#### int PyErr\_CheckSignals()

This function interacts with Python's signal handling. It checks whether a signal has been sent to the processes and if so, invokes the corresponding signal handler. If the signal module is supported, this can invoke a signal handler written in Python. In all cases, the default effect for SIGINT is to raise the KeyboardInterrupt exception. If an exception is raised the error indicator is set and the function returns -1; otherwise the function returns 0. The error indicator may or may not be cleared if it was previously set.

#### void PyErr\_SetInterrupt()

Simulate the effect of a SIGINT signal arriving. The next time <code>PyErr\_CheckSignals()</code> is called, the Python signal handler for <code>SIGINT</code> will be called.

If SIGINT isn't handled by Python (it was set to signal.SIG\_DFL or signal.SIG\_IGN), this function does nothing.

### int PySignal\_SetWakeupFd (int fd)

This utility function specifies a file descriptor to which the signal number is written as a single byte whenever a signal is received. fd must be non-blocking. It returns the previous such file descriptor.

The value -1 disables the feature; this is the initial state. This is equivalent to signal.set\_wakeup\_fd() in Python, but without any error checking. fd should be a valid file descriptor. The function should only be called from the main thread.

Changed in version 3.5: On Windows, the function now also supports socket handles.

## 5.6 Exception Classes

### PyObject\* PyErr\_NewException (const char \*name, PyObject \*base, PyObject \*dict)

Return value: New reference. This utility function creates and returns a new exception class. The name argument must be the name of the new exception, a C string of the form module.classname. The base and dict arguments are normally NULL. This creates a class object derived from Exception (accessible in C as PyExc\_Exception).

The \_\_module\_\_ attribute of the new class is set to the first part (up to the last dot) of the *name* argument, and the class name is set to the last part (after the last dot). The *base* argument can be used to specify alternate base classes; it can either be only one class or a tuple of classes. The *dict* argument can be used to specify a dictionary of class variables and methods.

PyObject\* PyErr\_NewExceptionWithDoc (const char \*name, const char \*doc, PyObject \*base, PyObject \*dict)

Return value: New reference. Same as PyErr\_NewException(), except that the new exception class can easily be given a docstring: If doc is non-NULL, it will be used as the docstring for the exception class.

New in version 3.2.

## 5.7 Exception Objects

```
PyObject* PyException_GetTraceback (PyObject *ex)
```

Return value: New reference. Return the traceback associated with the exception as a new reference, as accessible from Python through traceback. If there is no traceback associated, this returns NULL.

```
int PyException SetTraceback (PyObject *ex, PyObject *tb)
```

Set the traceback associated with the exception to tb. Use Py\_None to clear it.

```
PyObject* PyException_GetContext (PyObject *ex)
```

Return value: New reference. Return the context (another exception instance during whose handling ex was raised) associated with the exception as a new reference, as accessible from Python through \_\_context\_\_. If there is no context associated, this returns NULL.

```
void PyException_SetContext (PyObject *ex, PyObject *ctx)
```

Set the context associated with the exception to ctx. Use NULL to clear it. There is no type check to make sure that ctx is an exception instance. This steals a reference to ctx.

```
PyObject* PyException_GetCause (PyObject *ex)
```

*Return value: New reference.* Return the cause (either an exception instance, or None, set by raise . . . from . . . ) associated with the exception as a new reference, as accessible from Python through \_\_cause\_\_.

```
void PyException_SetCause (PyObject *ex, PyObject *cause)
```

Set the cause associated with the exception to *cause*. Use *NULL* to clear it. There is no type check to make sure that *cause* is either an exception instance or None. This steals a reference to *cause*.

```
__suppress_context__ is implicitly set to True by this function.
```

## 5.8 Unicode Exception Objects

The following functions are used to create and modify Unicode exceptions from C.

```
PyObject* PyUnicodeDecodeError_Create (const char *encoding, const char *object, Py_ssize_t length,
Py_ssize_t start, Py_ssize_t end, const char *reason)
```

Return value: New reference. Create a UnicodeDecodeError object with the attributes encoding, object, length, start, end and reason. encoding and reason are UTF-8 encoded strings.

```
PyObject* PyUnicodeError_Create (const char *encoding, const Py_UNICODE *object, Py_ssize_t length, Py_ssize_t start, Py_ssize_t end, const char *reason)
```

Return value: New reference. Create a UnicodeEncodeError object with the attributes encoding, object, length, start, end and reason. encoding and reason are UTF-8 encoded strings.

```
PyObject* PyUnicodeTranslateError_Create (const Py_UNICODE *object, Py_ssize_t length,
Py_ssize_t start, Py_ssize_t end, const char *reason)
```

Return value: New reference. Create a UnicodeTranslateError object with the attributes object, length, start, end and reason. reason is a UTF-8 encoded string.

```
PyObject* PyUnicodeDecodeError_GetEncoding (PyObject *exc)
```

```
PyObject* PyUnicodeEncodeError_GetEncoding (PyObject *exc)
```

Return value: New reference. Return the encoding attribute of the given exception object.

```
PyObject* PyUnicodeDecodeError GetObject (PyObject *exc)
```

```
PyObject* PyUnicodeEncodeError_GetObject (PyObject *exc)
```

```
PyObject* PyUnicodeTranslateError_GetObject (PyObject *exc)
```

Return value: New reference. Return the object attribute of the given exception object.

```
int PyUnicodeDecodeError_GetStart (PyObject *exc, Py_ssize_t *start)
```

```
int PyUnicodeEncodeError GetStart (PyObject *exc, Py ssize t *start)
int PyUnicodeTranslateError GetStart (PyObject *exc, Py ssize t *start)
     Get the start attribute of the given exception object and place it into *start. start must not be NULL. Return 0 on
     success, -1 on failure.
int PyUnicodeDecodeError_SetStart (PyObject *exc, Py_ssize_t start)
int PyUnicodeEncodeError SetStart (PyObject *exc, Py ssize t start)
int PyUnicodeTranslateError SetStart (PyObject *exc, Py ssize t start)
     Set the start attribute of the given exception object to start. Return 0 on success, -1 on failure.
int PyUnicodeDecodeError_GetEnd (PyObject *exc, Py_ssize_t *end)
int PyUnicodeEncodeError_GetEnd (PyObject *exc, Py_ssize_t *end)
int PyUnicodeTranslateError_GetEnd (PyObject *exc, Py_ssize_t *end)
     Get the end attribute of the given exception object and place it into *end. end must not be NULL. Return 0 on
     success, -1 on failure.
int PyUnicodeDecodeError_SetEnd (PyObject *exc, Py_ssize_t end)
int PyUnicodeEncodeError_SetEnd (PyObject *exc, Py_ssize_t end)
int PyUnicodeTranslateError_SetEnd (PyObject *exc, Py_ssize_t end)
     Set the end attribute of the given exception object to end. Return 0 on success, -1 on failure.
PyObject* PyUnicodeDecodeError GetReason (PyObject *exc)
PyObject* PyUnicodeEncodeError_GetReason (PyObject *exc)
PyObject* PyUnicodeTranslateError GetReason (PyObject *exc)
     Return value: New reference. Return the reason attribute of the given exception object.
int PyUnicodeDecodeError_SetReason (PyObject *exc, const char *reason)
int PyUnicodeError SetReason (PyObject *exc, const char *reason)
int PyUnicodeTranslateError_SetReason (PyObject *exc, const char *reason)
     Set the reason attribute of the given exception object to reason. Return 0 on success, -1 on failure.
```

# 5.9 Recursion Control

These two functions provide a way to perform safe recursive calls at the C level, both in the core and in extension modules. They are needed if the recursive code does not necessarily invoke Python code (which tracks its recursion depth automatically).

```
int Py_EnterRecursiveCall (const char *where)
```

Marks a point where a recursive C-level call is about to be performed.

If  $USE\_STACKCHECK$  is defined, this function checks if the OS stack overflowed using  $PyOS\_CheckStack$  (). In this is the case, it sets a MemoryError and returns a nonzero value.

The function then checks if the recursion limit is reached. If this is the case, a RecursionError is set and a nonzero value is returned. Otherwise, zero is returned.

where should be a string such as " in instance check" to be concatenated to the RecursionError message caused by the recursion depth limit.

```
void Py_LeaveRecursiveCall()
```

Ends a Py\_EnterRecursiveCall(). Must be called once for each successful invocation of Py EnterRecursiveCall().

Properly implementing  $tp\_repr$  for container types requires special recursion handling. In addition to protecting the stack,  $tp\_repr$  also needs to track objects to prevent cycles. The following two functions facilitate this functionality. Effectively, these are the C equivalent to reprlib.recursive\\_repr().

5.9. Recursion Control 31

#### int Py\_ReprEnter (PyObject \*object)

Called at the beginning of the  $tp\_repr$  implementation to detect cycles.

If the object has already been processed, the function returns a positive integer. In that case the  $tp\_repr$  implementation should return a string object indicating a cycle. As examples, dict objects return  $\{\ldots\}$  and list objects return  $[\ldots]$ .

The function will return a negative integer if the recursion limit is reached. In that case the  $tp\_repr$  implementation should typically return NULL.

Otherwise, the function returns zero and the  $tp\_repr$  implementation can continue normally.

#### void Py\_ReprLeave (PyObject \*object)

Ends a Py\_ReprEnter(). Must be called once for each invocation of Py\_ReprEnter() that returns zero.

# 5.10 Standard Exceptions

All standard Python exceptions are available as global variables whose names are  $PyExc_$  followed by the Python exception name. These have the type  $PyObject^*$ ; they are all class objects. For completeness, here are all the variables:

C Name	Python Name	Notes
PyExc_BaseException	BaseException	(1)
PyExc_Exception	Exception	(1)
PyExc_ArithmeticError	ArithmeticError	(1)
PyExc_AssertionError	AssertionError	
PyExc_AttributeError	AttributeError	
PyExc_BlockingIOError	BlockingIOError	
PyExc_BrokenPipeError	BrokenPipeError	
PyExc_BufferError	BufferError	
PyExc_ChildProcessError	ChildProcessError	
PyExc_ConnectionAbortedError	ConnectionAbortedError	
PyExc_ConnectionError	ConnectionError	
PyExc_ConnectionRefusedError	ConnectionRefusedError	
PyExc_ConnectionResetError	ConnectionResetError	
PyExc_EOFError	EOFError	
PyExc_FileExistsError	FileExistsError	
PyExc_FileNotFoundError	FileNotFoundError	
PyExc_FloatingPointError	FloatingPointError	
PyExc_GeneratorExit	GeneratorExit	
PyExc_ImportError	ImportError	
PyExc_IndentationError	IndentationError	
PyExc_IndexError	IndexError	
PyExc_InterruptedError	InterruptedError	
PyExc_IsADirectoryError	IsADirectoryError	
PyExc_KeyError	KeyError	
PyExc_KeyboardInterrupt	KeyboardInterrupt	
PyExc_LookupError	LookupError	(1)
PyExc_MemoryError	MemoryError	
PyExc_ModuleNotFoundError	ModuleNotFoundError	
PyExc_NameError	NameError	
PyExc_NotADirectoryError	NotADirectoryError	
PyExc_NotImplementedError	NotImplementedError	

Continued on next page

C Name Python Name Notes (1) PyExc\_OSError OSError PyExc\_OverflowError OverflowError PyExc\_PermissionError PermissionError PyExc\_ProcessLookupError ProcessLookupError RecursionError PyExc\_RecursionError (2) PyExc\_ReferenceError ReferenceError PyExc\_RuntimeError RuntimeError PyExc\_StopAsyncIteration StopAsyncIteration PyExc\_StopIteration StopIteration PyExc\_SyntaxError SyntaxError PyExc\_SystemError SystemError PyExc\_SystemExit SystemExit PyExc TabError TabError PyExc\_TimeoutError TimeoutError PyExc\_TypeError TypeError PyExc UnboundLocalError UnboundLocalError PyExc\_UnicodeDecodeError UnicodeDecodeError

Table 1 - continued from previous page

New in version 3.3: PyExc\_BlockingIOError, PyExc\_BrokenPipeError, PyExc\_ChildProcessError, PyExc\_ConnectionError, PyExc\_ConnectionAbortedError, PyExc\_ConnectionRefusedError, PyExc\_ConnectionResetError, PyExc\_FileExistsError, PyExc\_FileNotFoundError, PyExc\_InterruptedError, PyExc\_IsADirectoryError, PyExc\_NotADirectoryError, PyExc\_PermissionError, PyExc\_ProcessLookupError and PyExc\_TimeoutError were introduced following PEP 3151.

UnicodeEncodeError

ZeroDivisionError

UnicodeTranslateError

UnicodeError

ValueError

New in version 3.5: PyExc\_StopAsyncIteration and PyExc\_RecursionError.

New in version 3.6: PyExc\_ModuleNotFoundError.

PyExc\_UnicodeEncodeError

PyExc\_ZeroDivisionError

PyExc UnicodeTranslateError

PyExc\_UnicodeError

PyExc\_ValueError

These are compatibility aliases to PyExc\_OSError:

C Name	Notes
PyExc_EnvironmentError	
PyExc_IOError	
PyExc_WindowsError	(3)

Changed in version 3.3: These aliases used to be separate exception types.

#### Notes:

- (1) This is a base class for other standard exceptions.
- (2) This is the same as weakref.ReferenceError.
- (3) Only defined on Windows; protect code that uses this by testing that the preprocessor macro MS\_WINDOWS is defined.

# **5.11 Standard Warning Categories**

All standard Python warning categories are available as global variables whose names are  $PyExc_followed$  by the Python exception name. These have the type PyObject\*; they are all class objects. For completeness, here are all the variables:

C Name	Python Name	Notes
PyExc_Warning	Warning	(1)
PyExc_BytesWarning	BytesWarning	
PyExc_DeprecationWarning	DeprecationWarning	
PyExc_FutureWarning	FutureWarning	
PyExc_ImportWarning	ImportWarning	
PyExc_PendingDeprecationWarning	PendingDeprecationWarning	
PyExc_ResourceWarning	ResourceWarning	
PyExc_RuntimeWarning	RuntimeWarning	
PyExc_SyntaxWarning	SyntaxWarning	
PyExc_UnicodeWarning	UnicodeWarning	
PyExc_UserWarning	UserWarning	

New in version 3.2: PyExc\_ResourceWarning.

#### Notes:

(1) This is a base class for other standard warning categories.

# **UTILITIES**

The functions in this chapter perform various utility tasks, ranging from helping C code be more portable across platforms, using Python modules from C, and parsing function arguments and constructing Python values from C values.

# 6.1 Operating System Utilities

#### PyObject\* PyOS\_FSPath (PyObject \*path)

Return value: New reference. Return the file system representation for path. If the object is a str or bytes object, then its reference count is incremented. If the object implements the os.PathLike interface, then \_\_fspath\_\_\_() is returned as long as it is a str or bytes object. Otherwise TypeError is raised and NULL is returned.

New in version 3.6.

#### int **Py\_FdIsInteractive** (FILE \*fp, const char \*filename)

Return true (nonzero) if the standard I/O file fp with name filename is deemed interactive. This is the case for files for which isatty (fileno (fp)) is true. If the global flag  $Py\_InteractiveFlag$  is true, this function also returns true if the filename pointer is NULL or if the name is equal to one of the strings '<stdin>' or '???'.

#### void PyOS\_BeforeFork()

Function to prepare some internal state before a process fork. This should be called before calling fork () or any similar function that clones the current process. Only available on systems where fork () is defined.

New in version 3.7.

#### void PyOS\_AfterFork\_Parent()

Function to update some internal state after a process fork. This should be called from the parent process after calling fork () or any similar function that clones the current process, regardless of whether process cloning was successful. Only available on systems where fork () is defined.

New in version 3.7.

#### void PyOS AfterFork Child()

Function to update internal interpreter state after a process fork. This must be called from the child process after calling fork(), or any similar function that clones the current process, if there is any chance the process will call back into the Python interpreter. Only available on systems where fork() is defined.

New in version 3.7.

#### See also:

os.register\_at\_fork() allows registering custom Python functions to be called by PyOS\_BeforeFork(), PyOS\_AfterFork\_Parent() and PyOS\_AfterFork\_Child().

#### void PyOS AfterFork()

Function to update some internal state after a process fork; this should be called in the new process if the Python interpreter will continue to be used. If a new executable is loaded into the new process, this function does not need to be called.

Deprecated since version 3.7: This function is superseded by PyOS\_AfterFork\_Child().

#### int PyOS CheckStack()

Return true when the interpreter runs out of stack space. This is a reliable check, but is only available when USE\_STACKCHECK is defined (currently on Windows using the Microsoft Visual C++ compiler). USE\_STACKCHECK will be defined automatically; you should never change the definition in your own code.

#### PyOS\_sighandler\_t PyOS\_getsig (int i)

Return the current signal handler for signal *i*. This is a thin wrapper around either signation () or signal (). Do not call those functions directly! PyOS\_sighandler\_t is a typedef alias for void (\*) (int).

#### PyOS\_sighandler\_t PyOS\_setsig (int i, PyOS\_sighandler\_t h)

Set the signal handler for signal i to be h; return the old signal handler. This is a thin wrapper around either signation() or signal(). Do not call those functions directly! PyOS\_sighandler\_t is a typedef alias for void (\*) (int).

#### wchar\_t\* Py\_DecodeLocale (const char\* arg, size\_t \*size)

Decode a byte string from the locale encoding with the surrogateescape error handler: undecodable bytes are decoded as characters in range U+DC80..U+DCFF. If a byte sequence can be decoded as a surrogate character, escape the bytes using the surrogateescape error handler instead of decoding them.

Encoding, highest priority to lowest priority:

- UTF-8 on macOS, Android, and VxWorks;
- UTF-8 on Windows if Py\_LegacyWindowsFSEncodingFlag is zero;
- UTF-8 if the Python UTF-8 mode is enabled;
- ASCII if the LC\_CTYPE locale is "C", nl\_langinfo (CODESET) returns the ASCII encoding (or an alias), and mbstowcs () and wcstombs () functions uses the ISO-8859-1 encoding.
- the current locale encoding.

Return a pointer to a newly allocated wide character string, use <code>PyMem\_RawFree()</code> to free the memory. If size is not <code>NULL</code>, write the number of wide characters excluding the null character into <code>\*size</code>

Return NULL on decoding error or memory allocation error. If size is not NULL, \*size is set to (size\_t) -1 on memory error or set to (size\_t) -2 on decoding error.

Decoding errors should never happen, unless there is a bug in the C library.

Use the Py EncodeLocale () function to encode the character string back to a byte string.

#### See also:

The PyUnicode\_DecodeFSDefaultAndSize() and PyUnicode\_DecodeLocaleAndSize() functions.

New in version 3.5.

Changed in version 3.7: The function now uses the UTF-8 encoding in the UTF-8 mode.

Changed in version 3.8: The function now uses the UTF-8 encoding on Windows if Py\_LegacyWindowsFSEncodingFlag is zero;

## char\* Py\_EncodeLocale (const wchar\_t \*text, size\_t \*error\_pos)

Encode a wide character string to the locale encoding with the surrogateescape error handler: surrogate characters in the range U+DC80..U+DCFF are converted to bytes 0x80..0xFF.

36 Chapter 6. Utilities

Encoding, highest priority to lowest priority:

- UTF-8 on macOS, Android, and VxWorks;
- UTF-8 on Windows if Py\_LegacyWindowsFSEncodingFlag is zero;
- UTF-8 if the Python UTF-8 mode is enabled;
- ASCII if the LC\_CTYPE locale is "C", nl\_langinfo (CODESET) returns the ASCII encoding (or an alias), and mbstowcs () and wcstombs () functions uses the ISO-8859-1 encoding.
- the current locale encoding.

The function uses the UTF-8 encoding in the Python UTF-8 mode.

Return a pointer to a newly allocated byte string, use PyMem\_Free() to free the memory. Return NULL on encoding error or memory allocation error

If error\_pos is not NULL, \*error\_pos is set to (size\_t)-1 on success, or set to the index of the invalid character on encoding error.

Use the Py\_DecodeLocale() function to decode the bytes string back to a wide character string.

#### See also:

The PyUnicode\_EncodeFSDefault () and PyUnicode\_EncodeLocale () functions.

New in version 3.5.

Changed in version 3.7: The function now uses the UTF-8 encoding in the UTF-8 mode.

Changed in version 3.8: The function now uses the UTF-8 encoding on Windows if Py LegacyWindowsFSEncodingFlag is zero;

# 6.2 System Functions

These are utility functions that make functionality from the sys module accessible to C code. They all work with the current interpreter thread's sys module's dict, which is contained in the internal thread state structure.

```
PyObject *PySys_GetObject (const char *name)
```

Return value: Borrowed reference. Return the object name from the sys module or NULL if it does not exist, without setting an exception.

```
int PySys_SetObject (const char *name, PyObject *v)
```

Set *name* in the sys module to v unless v is NULL, in which case *name* is deleted from the sys module. Returns 0 on success, -1 on error.

# void PySys\_ResetWarnOptions()

Reset sys.warnoptions to an empty list. This function may be called prior to Py\_Initialize().

#### void PySys\_AddWarnOption (const wchar\_t \*s)

Append s to sys.warnoptions. This function must be called prior to  $Py\_Initialize()$  in order to affect the warnings filter list.

#### void PySys\_AddWarnOptionUnicode (PyObject \*unicode)

Append unicode to sys.warnoptions.

Note: this function is not currently usable from outside the CPython implementation, as it must be called prior to the implicit import of warnings in Py\_Initialize() to be effective, but can't be called until enough of the runtime has been initialized to permit the creation of Unicode objects.

#### void PySys\_SetPath (const wchar\_t \*path)

Set sys.path to a list object of paths found in *path* which should be a list of paths separated with the platform's search path delimiter (: on Unix,; on Windows).

#### void PySys\_WriteStdout (const char \*format, ...)

Write the output string described by *format* to sys.stdout. No exceptions are raised, even if truncation occurs (see below).

format should limit the total size of the formatted output string to 1000 bytes or less – after 1000 bytes, the output string is truncated. In particular, this means that no unrestricted "%s" formats should occur; these should be limited using "%.<N>s" where <N> is a decimal number calculated so that <N> plus the maximum size of other formatted text does not exceed 1000 bytes. Also watch out for "%f", which can print hundreds of digits for very large numbers.

If a problem occurs, or sys.stdout is unset, the formatted message is written to the real (C level) stdout.

#### void PySys\_WriteStderr (const char \*format, ...)

As PySys\_WriteStdout(), but write to sys.stderr or stderr instead.

#### void PySys\_FormatStdout (const char \*format, ...)

Function similar to PySys\_WriteStdout() but format the message using PyUnicode\_FromFormatV() and don't truncate the message to an arbitrary length.

New in version 3.2.

### void PySys\_FormatStderr (const char \*format, ...)

As PySys\_FormatStdout(), but write to sys.stderr or stderr instead.

New in version 3.2.

#### void PySys AddXOption (const wchar t \*s)

Parse s as a set of -X options and add them to the current options mapping as returned by  $PySys\_GetXOptions()$ . This function may be called prior to  $Py\_Initialize()$ .

New in version 3.2.

#### PyObject \*PySys\_GetXOptions()

*Return value: Borrowed reference.* Return the current dictionary of -X options, similarly to sys.\_xoptions. On error, *NULL* is returned and an exception is set.

New in version 3.2.

#### int PySys\_Audit (const char \*event, const char \*format, ...)

Raises an auditing event with any active hooks. Returns zero for success and non-zero with an exception set on failure.

If any hooks have been added, *format* and other arguments will be used to construct a tuple to pass. Apart from N, the same format characters as used in  $Py\_BuildValue()$  are available. If the built value is not a tuple, it will be added into a single-element tuple. (The N format option consumes a reference, but since there is no way to know whether arguments to this function will be consumed, using it may cause reference leaks.)

sys.audit() performs the same function from Python code.

New in version 3.8.

# int PySys\_AddAuditHook (Py\_AuditHookFunction hook, void \*userData)

Adds to the collection of active auditing hooks. Returns zero for success and non-zero on failure. If the runtime has been initialized, also sets an error on failure. Hooks added through this API are called for all interpreters created by the runtime.

This function is safe to call before  $Py_Initialize()$ . When called after runtime initialization, existing audit hooks are notified and may silently abort the operation by raising an error subclassed from Exception (other errors will not be silenced).

The hook function is of type int (\*) (const char \*event, PyObject \*args, void \*userData), where args is guaranteed to be a PyTupleObject. The hook function is always called with the GIL held by the Python interpreter that raised the event.

The *userData* pointer is passed into the hook function. Since hook functions may be called from different runtimes, this pointer should not refer directly to Python state.

See PEP 578 for a detailed description of auditing. Functions in the runtime and standard library that raise events include the details in each function's documentation.

New in version 3.8.

# **6.3 Process Control**

#### void Py FatalError (const char \*message)

Print a fatal error message and kill the process. No cleanup is performed. This function should only be invoked when a condition is detected that would make it dangerous to continue using the Python interpreter; e.g., when the object administration appears to be corrupted. On Unix, the standard C library function abort () is called which will attempt to produce a core file.

#### void Py\_Exit (int status)

Exit the current process. This calls  $Py\_FinalizeEx()$  and then calls the standard C library function exit (status). If  $Py\_FinalizeEx()$  indicates an error, the exit status is set to 120.

Changed in version 3.6: Errors from finalization no longer ignored.

#### int Py\_AtExit (void (\*func)())

Register a cleanup function to be called by  $Py\_FinalizeEx()$ . The cleanup function will be called with no arguments and should return no value. At most 32 cleanup functions can be registered. When the registration is successful,  $Py\_AtExit()$  returns 0; on failure, it returns -1. The cleanup function registered last is called first. Each cleanup function will be called at most once. Since Python's internal finalization will have completed before the cleanup function, no Python APIs should be called by *func*.

# 6.4 Importing Modules

#### PyObject\* PyImport\_ImportModule (const char \*name)

Return value: New reference. This is a simplified interface to PyImport\_ImportModuleEx() below, leaving the globals and locals arguments set to NULL and level set to 0. When the name argument contains a dot (when it specifies a submodule of a package), the fromlist argument is set to the list ['\*'] so that the return value is the named module rather than the top-level package containing it as would otherwise be the case. (Unfortunately, this has an additional side effect when name in fact specifies a subpackage instead of a submodule: the submodules specified in the package's \_\_all\_\_ variable are loaded.) Return a new reference to the imported module, or NULL with an exception set on failure. A failing import of a module doesn't leave the module in sys.modules.

This function always uses absolute imports.

#### PyObject\* PyImport\_ImportModuleNoBlock (const char \*name)

Return value: New reference. This function is a deprecated alias of PyImport\_ImportModule().

Changed in version 3.3: This function used to fail immediately when the import lock was held by another thread. In Python 3.3 though, the locking scheme switched to per-module locks for most purposes, so this function's special behaviour isn't needed anymore.

6.3. Process Control 39

# PyObject\* PyImport\_ImportModuleEx (const char \*name, PyObject \*globals, PyObject \*locals, PyObject \*fromlist)

*Return value: New reference.* Import a module. This is best described by referring to the built-in Python function \_\_import\_\_().

The return value is a new reference to the imported module or top-level package, or *NULL* with an exception set on failure. Like for \_\_import\_\_(), the return value when a submodule of a package was requested is normally the top-level package, unless a non-empty *fromlist* was given.

Failing imports remove incomplete module objects, like with PyImport\_ImportModule().

### PyObject\* PyImport\_ImportModuleLevelObject (PyObject \*name, PyObject \*globals, PyObject \*locals, PyObject \*fromlist, int level)

Return value: New reference. Import a module. This is best described by referring to the built-in Python function \_\_import\_\_\_(), as the standard \_\_import\_\_\_() function calls this function directly.

The return value is a new reference to the imported module or top-level package, or *NULL* with an exception set on failure. Like for \_\_import\_\_(), the return value when a submodule of a package was requested is normally the top-level package, unless a non-empty *fromlist* was given.

New in version 3.3.

# PyObject\* PyImport\_ImportModuleLevel (const char \*name, PyObject \*globals, PyObject \*locals, PyObject \*fromlist, int level)

Return value: New reference. Similar to PyImport\_ImportModuleLevelObject(), but the name is a UTF-8 encoded string instead of a Unicode object.

Changed in version 3.3: Negative values for *level* are no longer accepted.

#### PyObject\* PyImport\_Import (PyObject \*name)

Return value: New reference. This is a higher-level interface that calls the current "import hook function" (with an explicit level of 0, meaning absolute import). It invokes the \_\_import\_\_ () function from the \_\_builtins\_\_ of the current globals. This means that the import is done using whatever import hooks are installed in the current environment.

This function always uses absolute imports.

#### PyObject\* PyImport\_ReloadModule (PyObject \*m)

*Return value: New reference.* Reload a module. Return a new reference to the reloaded module, or *NULL* with an exception set on failure (the module still exists in this case).

#### PyObject\* PyImport\_AddModuleObject (PyObject \*name)

Return value: Borrowed reference. Return the module object corresponding to a module name. The *name* argument may be of the form package.module. First check the modules dictionary if there's one there, and if not, create a new one and insert it in the modules dictionary. Return *NULL* with an exception set on failure.

**Note:** This function does not load or import the module; if the module wasn't already loaded, you will get an empty module object. Use <code>PyImport\_ImportModule()</code> or one of its variants to import a module. Package structures implied by a dotted name for *name* are not created if not already present.

New in version 3.3.

#### *PyObject\** **PyImport AddModule** (const char \*name)

Return value: Borrowed reference. Similar to PyImport\_AddModuleObject(), but the name is a UTF-8 encoded string instead of a Unicode object.

### PyObject\* PyImport\_ExecCodeModule (const char \*name, PyObject \*co)

Return value: New reference. Given a module name (possibly of the form package.module) and a code object read from a Python bytecode file or obtained from the built-in function compile(), load the module. Return a new reference to the module object, or NULL with an exception set if an error occurred. name

40 Chapter 6. Utilities

is removed from sys.modules in error cases, even if *name* was already in sys.modules on entry to  $PyImport\_ExecCodeModule()$ . Leaving incompletely initialized modules in sys.modules is dangerous, as imports of such modules have no way to know that the module object is an unknown (and probably damaged with respect to the module author's intents) state.

The module's \_\_spec\_\_ and \_\_loader\_\_ will be set, if not set already, with the appropriate values. The spec's loader will be set to the module's \_\_loader\_\_ (if set) and to an instance of SourceFileLoader otherwise.

The module's \_\_file\_\_ attribute will be set to the code object's co\_filename. If applicable, \_\_cached\_\_ will also be set.

This function will reload the module if it was already imported. See <code>PyImport\_ReloadModule()</code> for the intended way to reload a module.

If *name* points to a dotted name of the form package.module, any package structures not already created will still not be created.

See also PyImport\_ExecCodeModuleEx() and PyImport\_ExecCodeModuleWithPathnames().

#### PyObject\* PyImport\_ExecCodeModuleEx (const char \*name, PyObject \*co, const char \*pathname)

Return value: New reference. Like PyImport\_ExecCodeModule(), but the \_\_file\_\_ attribute of the module object is set to pathname if it is non-NULL.

See also PyImport ExecCodeModuleWithPathnames().

# PyObject\* PyImport\_ExecCodeModuleObject (PyObject \*name, PyObject \*co, PyObject \*pathname, PyObject \*cpathname)

Return value: New reference. Like PyImport\_ExecCodeModuleEx(), but the \_\_cached\_\_ attribute of the module object is set to cpathname if it is non-NULL. Of the three functions, this is the preferred one to use.

New in version 3.3.

# PyObject\* PyImport\_ExecCodeModuleWithPathnames (const char \*name, PyObject \*co, const char \*pathname, const char \*cpathname)

Return value: New reference. Like PyImport\_ExecCodeModuleObject(), but name, pathname and cpathname are UTF-8 encoded strings. Attempts are also made to figure out what the value for pathname should be from cpathname if the former is set to NULL.

New in version 3.2.

Changed in version 3.3: Uses imp.source\_from\_cache() in calculating the source path if only the bytecode path is provided.

#### long PyImport\_GetMagicNumber()

Return the magic number for Python bytecode files (a.k.a. .pyc file). The magic number should be present in the first four bytes of the bytecode file, in little-endian byte order. Returns -1 on error.

Changed in version 3.3: Return value of -1 upon failure.

#### const char \* PyImport\_GetMagicTag()

Return the magic tag string for PEP 3147 format Python bytecode file names. Keep in mind that the value at sys.implementation.cache\_tag is authoritative and should be used instead of this function.

New in version 3.2.

#### PyObject\* PyImport\_GetModuleDict()

Return value: Borrowed reference. Return the dictionary used for the module administration (a.k.a. sys.modules). Note that this is a per-interpreter variable.

#### PyObject\* PyImport\_GetModule (PyObject \*name)

*Return value: New reference.* Return the already imported module with the given name. If the module has not been imported yet then returns NULL but does not set an error. Returns NULL and sets an error if the lookup failed.

New in version 3.7.

#### PyObject\* PyImport\_GetImporter (PyObject \*path)

Return value: New reference. Return a finder object for a sys.path/pkg.\_\_path\_\_ item path, possibly by fetching it from the sys.path\_importer\_cache dict. If it wasn't yet cached, traverse sys.path\_hooks until a hook is found that can handle the path item. Return None if no hook could; this tells our caller that the path based finder could not find a finder for this path item. Cache the result in sys.path\_importer\_cache. Return a new reference to the finder object.

#### void \_PyImport\_Init()

Initialize the import mechanism. For internal use only.

#### void PyImport\_Cleanup()

Empty the module table. For internal use only.

#### void \_PyImport\_Fini()

Finalize the import mechanism. For internal use only.

# int PyImport\_ImportFrozenModuleObject (PyObject \*name)

Return value: New reference. Load a frozen module named name. Return 1 for success, 0 if the module is not found, and -1 with an exception set if the initialization failed. To access the imported module on a successful load, use PyImport\_ImportModule(). (Note the misnomer — this function would reload the module if it was already imported.)

New in version 3.3.

Changed in version 3.4: The \_\_\_file\_\_ attribute is no longer set on the module.

#### int PyImport\_ImportFrozenModule (const char \*name)

Similar to PyImport\_ImportFrozenModuleObject (), but the name is a UTF-8 encoded string instead of a Unicode object.

#### struct **\_frozen**

This is the structure type definition for frozen module descriptors, as generated by the **freeze** utility (see Tools/freeze/ in the Python source distribution). Its definition, found in Include/import.h, is:

```
struct _frozen {
   const char *name;
   const unsigned char *code;
   int size;
};
```

#### const struct \_frozen\* PyImport\_FrozenModules

This pointer is initialized to point to an array of struct \_frozen records, terminated by one whose members are all *NULL* or zero. When a frozen module is imported, it is searched in this table. Third-party code could play tricks with this to provide a dynamically created collection of frozen modules.

# int PyImport\_AppendInittab (const char \*name, PyObject\* (\*initfunc)(void))

Add a single module to the existing table of built-in modules. This is a convenience wrapper around  $PyImport\_ExtendInittab()$ , returning -1 if the table could not be extended. The new module can be imported by the name *name*, and uses the function *initfunc* as the initialization function called on the first attempted import. This should be called before  $Py\_Initialize()$ .

#### struct \_inittab

Structure describing a single entry in the list of built-in modules. Each of these structures gives the name and initialization function for a module built into the interpreter. The name is an ASCII encoded string. Programs which embed Python may use an array of these structures in conjunction with <code>PyImport\_ExtendInittab()</code> to provide additional built-in modules. The structure is defined in <code>Include/import.h</code> as:

42 Chapter 6. Utilities

(continued from previous page)

```
PyObject* (*initfunc)(void);
};
```

#### int PyImport\_ExtendInittab (struct \_inittab \*newtab)

Add a collection of modules to the table of built-in modules. The *newtab* array must end with a sentinel entry which contains *NULL* for the name field; failure to provide the sentinel value can result in a memory fault. Returns 0 on success or -1 if insufficient memory could be allocated to extend the internal table. In the event of failure, no modules are added to the internal table. This should be called before *Py\_Initialize()*.

# 6.5 Data marshalling support

These routines allow C code to work with serialized objects using the same data format as the marshal module. There are functions to write data into the serialization format, and additional functions that can be used to read the data back. Files used to store marshalled data must be opened in binary mode.

Numeric values are stored with the least significant byte first.

The module supports two versions of the data format: version 0 is the historical version, version 1 shares interned strings in the file, and upon unmarshalling. Version 2 uses a binary format for floating point numbers. *Py\_MARSHAL\_VERSION* indicates the current file format (currently 2).

#### void PyMarshal\_WriteLongToFile (long value, FILE \*file, int version)

Marshal a long integer, *value*, to *file*. This will only write the least-significant 32 bits of *value*; regardless of the size of the native long type. *version* indicates the file format.

#### void PyMarshal\_WriteObjectToFile (PyObject \*value, FILE \*file, int version)

Marshal a Python object, value, to file. version indicates the file format.

#### PyObject\* PyMarshal\_WriteObjectToString (PyObject \*value, int version)

Return value: New reference. Return a bytes object containing the marshalled representation of value. version indicates the file format.

The following functions allow marshalled values to be read back in.

#### long PyMarshal ReadLongFromFile (FILE \*file)

Return a C long from the data stream in a FILE\* opened for reading. Only a 32-bit value can be read in using this function, regardless of the native size of long.

On error, sets the appropriate exception (EOFError) and returns -1.

#### int PyMarshal\_ReadShortFromFile (FILE \*file)

Return a C short from the data stream in a FILE\* opened for reading. Only a 16-bit value can be read in using this function, regardless of the native size of short.

On error, sets the appropriate exception (EOFError) and returns -1.

#### PyObject\* PyMarshal\_ReadObjectFromFile (FILE \*file)

Return value: New reference. Return a Python object from the data stream in a FILE\* opened for reading.

On error, sets the appropriate exception (EOFError, ValueError or TypeError) and returns NULL.

## PyObject\* PyMarshal\_ReadLastObjectFromFile (FILE \*file)

Return value: New reference. Return a Python object from the data stream in a FILE\* opened for reading. Unlike PyMarshal\_ReadObjectFromFile(), this function assumes that no further objects will be read from the file, allowing it to aggressively load file data into memory so that the de-serialization can operate from data in memory rather than reading a byte at a time from the file. Only use these variant if you are certain that you won't be reading anything else from the file.

On error, sets the appropriate exception (EOFError, ValueError or TypeError) and returns NULL.

PyObject\* PyMarshal\_ReadObjectFromString (const char \*data, Py\_ssize\_t len)

Return value: New reference. Return a Python object from the data stream in a byte buffer containing len bytes pointed to by data.

On error, sets the appropriate exception (EOFError, ValueError or TypeError) and returns NULL.

# 6.6 Parsing arguments and building values

These functions are useful when creating your own extensions functions and methods. Additional information and examples are available in extending-index.

The first three of these functions described,  $PyArg\_ParseTuple()$ ,  $PyArg\_ParseTupleAndKeywords()$ , and  $PyArg\_Parse()$ , all use *format strings* which are used to tell the function about the expected arguments. The format strings use the same syntax for each of these functions.

# 6.6.1 Parsing arguments

A format string consists of zero or more "format units." A format unit describes one Python object; it is usually a single character or a parenthesized sequence of format units. With a few exceptions, a format unit that is not a parenthesized sequence normally corresponds to a single address argument to these functions. In the following description, the quoted form is the format unit; the entry in (round) parentheses is the Python object type that matches the format unit; and the entry in [square] brackets is the type of the C variable(s) whose address should be passed.

# Strings and buffers

These formats allow accessing an object as a contiguous chunk of memory. You don't have to provide raw storage for the returned unicode or bytes area.

In general, when a format sets a pointer to a buffer, the buffer is managed by the corresponding Python object, and the buffer shares the lifetime of this object. You won't have to release any memory yourself. The only exceptions are es, es#, et and et#.

However, when a <code>Py\_buffer</code> structure gets filled, the underlying buffer is locked so that the caller can subsequently use the buffer even inside a <code>Py\_BEGIN\_ALLOW\_THREADS</code> block without the risk of mutable data being resized or destroyed. As a result, you have to call <code>PyBuffer\_Release()</code> after you have finished processing the data (or in any early abort case).

Unless otherwise stated, buffers are not NUL-terminated.

Some formats require a read-only *bytes-like object*, and set a pointer instead of a buffer structure. They work by checking that the object's *PyBufferProcs.bf\_releasebuffer* field is *NULL*, which disallows mutable objects such as bytearray.

**Note:** For all # variants of formats (s#, y#, etc.), the type of the length argument (int or Py\_ssize\_t) is controlled by defining the macro PY\_SSIZE\_T\_CLEAN before including Python.h. If the macro was defined, length is a Py\_ssize\_t rather than an int. This behavior will change in a future Python version to only support Py\_ssize\_t and drop int support. It is best to always define PY\_SSIZE\_T\_CLEAN.

**s** (**str**) [**const char \***] Convert a Unicode object to a C pointer to a character string. A pointer to an existing string is stored in the character pointer variable whose address you pass. The C string is NUL-terminated. The Python

string must not contain embedded null code points; if it does, a ValueError exception is raised. Unicode objects are converted to C strings using 'utf-8' encoding. If this conversion fails, a UnicodeError is raised.

**Note:** This format does not accept *bytes-like objects*. If you want to accept filesystem paths and convert them to C character strings, it is preferable to use the O& format with PyUnicode\_FSConverter() as converter.

Changed in version 3.5: Previously, TypeError was raised when embedded null code points were encountered in the Python string.

- **s\*** (**str** or *bytes-like object*) [**Py\_buffer**] This format accepts Unicode objects as well as bytes-like objects. It fills a *Py\_buffer* structure provided by the caller. In this case the resulting C string may contain embedded NUL bytes. Unicode objects are converted to C strings using 'utf-8' encoding.
- s# (str, read-only bytes-like object) [const char \*, int or Py\_ssize\_t] Like s\*, except that it doesn't accept mutable objects. The result is stored into two C variables, the first one a pointer to a C string, the second one its length. The string may contain embedded null bytes. Unicode objects are converted to C strings using 'utf-8' encoding.
- z (str or None) [const char \*] Like s, but the Python object may also be None, in which case the C pointer is set to NULL.
- **z\*** (**str**, *bytes-like object* **or None**) [**Py\_buffer**] Like s\*, but the Python object may also be None, in which case the buf member of the Py\_buffer structure is set to *NULL*.
- z# (str, read-only bytes-like object or None) [const char \*, int] Like s#, but the Python object may also be None, in which case the C pointer is set to NULL.
- y (read-only bytes-like object) [const char \*] This format converts a bytes-like object to a C pointer to a character string; it does not accept Unicode objects. The bytes buffer must not contain embedded null bytes; if it does, a ValueError exception is raised.
  - Changed in version 3.5: Previously, TypeError was raised when embedded null bytes were encountered in the bytes buffer.
- y\* (bytes-like object) [Py\_buffer] This variant on s\* doesn't accept Unicode objects, only bytes-like objects. This is the recommended way to accept binary data.
- **y#** (**read-only** *bytes-like object*) [**const char \*, int**] This variant on s# doesn't accept Unicode objects, only bytes-like objects.
- **S (bytes)** [**PyBytesObject \***] Requires that the Python object is a bytes object, without attempting any conversion. Raises TypeError if the object is not a bytes object. The C variable may also be declared as PyObject\*.
- Y (bytearray) [PyByteArrayObject \*] Requires that the Python object is a bytearray object, without attempting any conversion. Raises TypeError if the object is not a bytearray object. The C variable may also be declared as PyObject\*.
- u (str) [const Py\_UNICODE \*] Convert a Python Unicode object to a C pointer to a NUL-terminated buffer of Unicode characters. You must pass the address of a Py\_UNICODE pointer variable, which will be filled with the pointer to an existing Unicode buffer. Please note that the width of a Py\_UNICODE character depends on compilation options (it is either 16 or 32 bits). The Python string must not contain embedded null code points; if it does, a ValueError exception is raised.

Changed in version 3.5: Previously, TypeError was raised when embedded null code points were encountered in the Python string.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py\_UNICODE API; please migrate to using PyUnicode\_AsWideCharString().

**u#** (str) [const Py\_UNICODE \*, int] This variant on u stores into two C variables, the first one a pointer to a Unicode data buffer, the second one its length. This variant allows null code points.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py\_UNICODE API; please migrate to using PyUnicode\_AsWideCharString().

**Z** (str or None) [const Py\_UNICODE \*] Like u, but the Python object may also be None, in which case the Py\_UNICODE pointer is set to NULL.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style *Py\_UNICODE* API; please migrate to using *PyUnicode\_AsWideCharString()*.

**Z#** (str or None) [const Py\_UNICODE \*, int] Like u#, but the Python object may also be None, in which case the Py\_UNICODE pointer is set to NULL.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style *Py\_UNICODE* API; please migrate to using *PyUnicode\_AsWideCharString()*.

- U (str) [PyObject \*] Requires that the Python object is a Unicode object, without attempting any conversion. Raises TypeError if the object is not a Unicode object. The C variable may also be declared as PyObject \*.
- w\* (read-write bytes-like object) [Py\_buffer] This format accepts any object which implements the read-write buffer interface. It fills a Py\_buffer structure provided by the caller. The buffer may contain embedded null bytes. The caller have to call PyBuffer\_Release() when it is done with the buffer.
- **es** (**str**) [const char \*encoding, char \*\*buffer] This variant on s is used for encoding Unicode into a character buffer. It only works for encoded data without embedded NUL bytes.

This format requires two arguments. The first is only used as input, and must be a const char\* which points to the name of an encoding as a NUL-terminated string, or *NULL*, in which case 'utf-8' encoding is used. An exception is raised if the named encoding is not known to Python. The second argument must be a char\*\*; the value of the pointer it references will be set to a buffer with the contents of the argument text. The text will be encoded in the encoding specified by the first argument.

PyArg\_ParseTuple() will allocate a buffer of the needed size, copy the encoded data into this buffer and adjust \*buffer to reference the newly allocated storage. The caller is responsible for calling PyMem\_Free() to free the allocated buffer after use.

- et (str, bytes or bytearray) [const char \*encoding, char \*\*buffer] Same as es except that byte string objects are passed through without recoding them. Instead, the implementation assumes that the byte string object uses the encoding passed in as parameter.
- es# (str) [const char \*encoding, char \*\*buffer, int \*buffer\_length] This variant on s# is used for encoding Unicode into a character buffer. Unlike the es format, this variant allows input data which contains NUL characters.

It requires three arguments. The first is only used as input, and must be a const char\* which points to the name of an encoding as a NUL-terminated string, or *NULL*, in which case 'utf-8' encoding is used. An exception is raised if the named encoding is not known to Python. The second argument must be a char\*\*; the value of the pointer it references will be set to a buffer with the contents of the argument text. The text will be encoded in the encoding specified by the first argument. The third argument must be a pointer to an integer; the referenced integer will be set to the number of bytes in the output buffer.

There are two modes of operation:

If \*buffer points a NULL pointer, the function will allocate a buffer of the needed size, copy the encoded data into this buffer and set \*buffer to reference the newly allocated storage. The caller is responsible for calling PyMem\_Free() to free the allocated buffer after usage.

If \*buffer points to a non-NULL pointer (an already allocated buffer), PyArg\_ParseTuple() will use this location as the buffer and interpret the initial value of \*buffer\_length as the buffer size. It will then copy the encoded data into the buffer and NUL-terminate it. If the buffer is not large enough, a ValueError will be set.

46 Chapter 6. Utilities

In both cases, \*buffer\_length is set to the length of the encoded data without the trailing NUL byte.

et# (str, bytes or bytearray) [const char \*encoding, char \*\*buffer, int \*buffer\_length] Same as es# except that byte string objects are passed through without recoding them. Instead, the implementation assumes that the byte string object uses the encoding passed in as parameter.

#### **Numbers**

- **b** (int) [unsigned char] Convert a nonnegative Python integer to an unsigned tiny int, stored in a C unsigned char.
- **B** (int) [unsigned char] Convert a Python integer to a tiny int without overflow checking, stored in a C unsigned char.
- h (int) [short int] Convert a Python integer to a C short int.
- H (int) [unsigned short int] Convert a Python integer to a C unsigned short int, without overflow checking.
- i (int) [int] Convert a Python integer to a plain C int.
- I (int) [unsigned int] Convert a Python integer to a C unsigned int, without overflow checking.
- 1 (int) [long int] Convert a Python integer to a C long int.
- k (int) [unsigned long] Convert a Python integer to a C unsigned long without overflow checking.
- L(int)[long long] Convert a Python integer to a Clong long.
- K (int) [unsigned long long] Convert a Python integer to a C unsigned long long without overflow checking.
- n (int) [Py\_ssize\_t] Convert a Python integer to a C Py\_ssize\_t.
- c (bytes or bytearray of length 1) [char] Convert a Python byte, represented as a bytes or bytearray object of length 1, to a C char.

Changed in version 3.3: Allow bytearray objects.

- C (str of length 1) [int] Convert a Python character, represented as a str object of length 1, to a C int.
- **f (float)** [float] Convert a Python floating point number to a C float.
- d (float) [double] Convert a Python floating point number to a C double.
- D (complex) [Py\_complex] Convert a Python complex number to a C Py\_complex structure.

#### Other objects

- O (object) [PyObject \*] Store a Python object (without any conversion) in a C object pointer. The C program thus receives the actual object that was passed. The object's reference count is not increased. The pointer stored is not *NULL*.
- O! (object) [typeobject, PyObject \*] Store a Python object in a C object pointer. This is similar to 0, but takes two C arguments: the first is the address of a Python type object, the second is the address of the C variable (of type PyObject\*) into which the object pointer is stored. If the Python object does not have the required type, TypeError is raised.
- **O&** (object) [converter, anything] Convert a Python object to a C variable through a converter function. This takes two arguments: the first is a function, the second is the address of a C variable (of arbitrary type), converted to void \*. The converter function in turn is called as follows:

```
status = converter(object, address);
```

where *object* is the Python object to be converted and *address* is the void\* argument that was passed to the *PyArg\_Parse\**() function. The returned *status* should be 1 for a successful conversion and 0 if the conversion has failed. When the conversion fails, the *converter* function should raise an exception and leave the content of *address* unmodified.

If the *converter* returns Py\_CLEANUP\_SUPPORTED, it may get called a second time if the argument parsing eventually fails, giving the converter a chance to release any memory that it had already allocated. In this second call, the *object* parameter will be NULL; *address* will have the same value as in the original call.

Changed in version 3.1: Py\_CLEANUP\_SUPPORTED was added.

**p (bool) [int]** Tests the value passed in for truth (a boolean **pr**edicate) and converts the result to its equivalent C true/false integer value. Sets the int to 1 if the expression was true and 0 if it was false. This accepts any valid Python value. See truth for more information about how Python tests values for truth.

New in version 3.3.

(items) (tuple) [matching-items] The object must be a Python sequence whose length is the number of format units in items. The C arguments must correspond to the individual format units in items. Format units for sequences may be nested.

It is possible to pass "long" integers (integers whose value exceeds the platform's LONG\_MAX) however no proper range checking is done — the most significant bits are silently truncated when the receiving field is too small to receive the value (actually, the semantics are inherited from downcasts in C — your mileage may vary).

A few other characters have a meaning in a format string. These may not occur inside nested parentheses. They are:

- Indicates that the remaining arguments in the Python argument list are optional. The C variables corresponding to optional arguments should be initialized to their default value when an optional argument is not specified, <code>PyArg\_ParseTuple()</code> does not touch the contents of the corresponding C variable(s).
- \$ PyArg\_ParseTupleAndKeywords() only: Indicates that the remaining arguments in the Python argument list are keyword-only. Currently, all keyword-only arguments must also be optional arguments, so | must always be specified before \$ in the format string.

New in version 3.3.

- : The list of format units ends here; the string after the colon is used as the function name in error messages (the "associated value" of the exception that PyArg\_ParseTuple() raises).
- ; The list of format units ends here; the string after the semicolon is used as the error message *instead* of the default error message. : and ; mutually exclude each other.

Note that any Python object references which are provided to the caller are *borrowed* references; do not decrement their reference count!

Additional arguments passed to these functions must be addresses of variables whose type is determined by the format string; these are used to store values from the input tuple. There are a few cases, as described in the list of format units above, where these parameters are used as input values; they should match what is specified for the corresponding format unit in that case.

For the conversion to succeed, the *arg* object must match the format and the format must be exhausted. On success, the *PyArg\_Parse\*()* functions return true, otherwise they return false and raise an appropriate exception. When the *PyArg\_Parse\*()* functions fail due to conversion failure in one of the format units, the variables at the addresses corresponding to that and the following format units are left untouched.

#### **API Functions**

```
int PyArg_ParseTuple (PyObject *args, const char *format, ...)
```

Parse the parameters of a function that takes only positional parameters into local variables. Returns true on success; on failure, it returns false and raises the appropriate exception.

```
int PyArq VaParse (PyObject *args, const char *format, va list vargs)
```

Identical to PyArg\_ParseTuple(), except that it accepts a va\_list rather than a variable number of arguments.

```
int PyArg_ParseTupleAndKeywords (PyObject *args, PyObject *kw, const char *format, char *keywords[], ...)
```

Parse the parameters of a function that takes both positional and keyword parameters into local variables. The *keywords* argument is a *NULL*-terminated array of keyword parameter names. Empty names denote *positional-only parameters*. Returns true on success; on failure, it returns false and raises the appropriate exception.

Changed in version 3.6: Added support for positional-only parameters.

```
int PyArg_VaParseTupleAndKeywords (PyObject *args, PyObject *kw, const char *format, char *key-words[], va_list vargs)
```

Identical to PyArg\_ParseTupleAndKeywords (), except that it accepts a va\_list rather than a variable number of arguments.

#### int PyArg\_ValidateKeywordArguments (PyObject \*)

Ensure that the keys in the keywords argument dictionary are strings. This is only needed if PyArg ParseTupleAndKeywords () is not used, since the latter already does this check.

New in version 3.2.

```
int PyArg_Parse (PyObject *args, const char *format, ...)
```

Function used to deconstruct the argument lists of "old-style" functions — these are functions which use the METH\_OLDARGS parameter parsing method, which has been removed in Python 3. This is not recommended for use in parameter parsing in new code, and most code in the standard interpreter has been modified to no longer use this for that purpose. It does remain a convenient way to decompose other tuples, however, and may continue to be used for that purpose.

```
int PyArg_UnpackTuple (PyObject *args, const char *name, Py_ssize_t min, Py_ssize_t max, ...)
```

A simpler form of parameter retrieval which does not use a format string to specify the types of the arguments. Functions which use this method to retrieve their parameters should be declared as  $METH\_VARARGS$  in function or method tables. The tuple containing the actual parameters should be passed as args; it must actually be a tuple. The length of the tuple must be at least min and no more than max; min and max may be equal. Additional arguments must be passed to the function, each of which should be a pointer to a PyObject\* variable; these will be filled in with the values from args; they will contain borrowed references. The variables which correspond to optional parameters not given by args will not be filled in; these should be initialized by the caller. This function returns true on success and false if args is not a tuple or contains the wrong number of elements; an exception will be set if there was a failure.

This is an example of the use of this function, taken from the sources for the \_weakref helper module for weak references:

```
static PyObject *
weakref_ref(PyObject *self, PyObject *args)
{
    PyObject *object;
    PyObject *callback = NULL;
    PyObject *result = NULL;

    if (PyArg_UnpackTuple(args, "ref", 1, 2, &object, &callback)) {
        result = PyWeakref_NewRef(object, callback);
    }
    return result;
}
```

The call to  $PyArg\_UnpackTuple()$  in this example is entirely equivalent to this call to  $PyArg\_ParseTuple()$ :

```
PyArg_ParseTuple(args, "0|0:ref", &object, &callback)
```

# 6.6.2 Building values

```
PyObject* Py_BuildValue (const char *format, ...)
```

Return value: New reference. Create a new value based on a format string similar to those accepted by the PyArg\_Parse\*() family of functions and a sequence of values. Returns the value or NULL in the case of an error; an exception will be raised if NULL is returned.

Py\_BuildValue() does not always build a tuple. It builds a tuple only if its format string contains two or more format units. If the format string is empty, it returns None; if it contains exactly one format unit, it returns whatever object is described by that format unit. To force it to return a tuple of size 0 or one, parenthesize the format string.

When memory buffers are passed as parameters to supply data to build objects, as for the s and s# formats, the required data is copied. Buffers provided by the caller are never referenced by the objects created by  $Py\_BuildValue()$ . In other words, if your code invokes malloc() and passes the allocated memory to  $Py\_BuildValue()$ , your code is responsible for calling free() for that memory once  $Py\_BuildValue()$  returns.

In the following description, the quoted form is the format unit; the entry in (round) parentheses is the Python object type that the format unit will return; and the entry in [square] brackets is the type of the C value(s) to be passed.

The characters space, tab, colon and comma are ignored in format strings (but not within format units such as s#). This can be used to make long format strings a tad more readable.

- s (str or None) [const char\*] Convert a null-terminated C string to a Python str object using 'utf-8' encoding. If the C string pointer is *NULL*, None is used.
- **s#** (**str or None**) [const char \*, int] Convert a C string and its length to a Python str object using 'utf-8' encoding. If the C string pointer is *NULL*, the length is ignored and None is returned.
- y (bytes) [const char \*] This converts a C string to a Python bytes object. If the C string pointer is *NULL*, None is returned.
- **y#** (bytes) [const char \*, int] This converts a C string and its lengths to a Python object. If the C string pointer is *NULL*, None is returned.
- z (str or None) [const char \*] Same as s.
- z# (str or None) [const char \*, int] Same as s#.
- u (str) [const wchar\_t \*] Convert a null-terminated wchar\_t buffer of Unicode (UTF-16 or UCS-4) data to a Python Unicode object. If the Unicode buffer pointer is *NULL*, None is returned.
- u# (str) [const wchar\_t \*, int] Convert a Unicode (UTF-16 or UCS-4) data buffer and its length to a Python Unicode object. If the Unicode buffer pointer is *NULL*, the length is ignored and None is returned.
- U (str or None) [const char \*] Same as s.
- U# (str or None) [const char \*, int] Same as s#.
- i (int) [int] Convert a plain C int to a Python integer object.
- **b** (int) [char] Convert a plain C char to a Python integer object.
- h (int) [short int] Convert a plain C short int to a Python integer object.
- 1 (int) [long int] Convert a Clong int to a Python integer object.
- B(int)[unsigned char] Convert a Cunsigned char to a Python integer object.

50 Chapter 6. Utilities

- H (int) [unsigned short int] Convert a C unsigned short int to a Python integer object.
- I (int) [unsigned int] Convert a C unsigned int to a Python integer object.
- k (int) [unsigned long] Convert a C unsigned long to a Python integer object.
- L (int) [long long] Convert a C long long to a Python integer object.
- K (int) [unsigned long long] Convert a C unsigned long long to a Python integer object.
- n (int) [Py ssize t] Convert a C Py ssize t to a Python integer.
- c (bytes of length 1) [char] Convert a C int representing a byte to a Python bytes object of length 1.
- C (str of length 1) [int] Convert a C int representing a character to Python str object of length 1.
- d (float) [double] Convert a C double to a Python floating point number.
- **f** (**float**) [**float**] Convert a C float to a Python floating point number.
- D (complex) [Py\_complex \*] Convert a C Py\_complex structure to a Python complex number.
- O (object) [PyObject \*] Pass a Python object untouched (except for its reference count, which is incremented by one). If the object passed in is a *NULL* pointer, it is assumed that this was caused because the call producing the argument found an error and set an exception. Therefore, *Py\_BuildValue()* will return *NULL* but won't raise an exception. If no exception has been raised yet, SystemError is set.
- **S** (object) [PyObject \*] Same as O.
- **N** (object) [PyObject \*] Same as O, except it doesn't increment the reference count on the object. Useful when the object is created by a call to an object constructor in the argument list.
- **O&** (object) [converter, anything] Convert anything to a Python object through a converter function. The function is called with anything (which should be compatible with void \*) as its argument and should return a "new" Python object, or NULL if an error occurred.
- (items) (tuple) [matching-items] Convert a sequence of C values to a Python tuple with the same number of items.
- [items] (list) [matching-items] Convert a sequence of C values to a Python list with the same number of items.
- **{items}** (dict) [matching-items] Convert a sequence of C values to a Python dictionary. Each pair of consecutive C values adds one item to the dictionary, serving as key and value, respectively.

If there is an error in the format string, the SystemError exception is set and NULL returned.

PyObject\* Py\_VaBuildValue (const char \*format, va\_list vargs)

Return value: New reference. Identical to Py\_BuildValue(), except that it accepts a va\_list rather than a variable number of arguments.

# 6.7 String conversion and formatting

Functions for number conversion and formatted string output.

int PyOS\_snprintf (char \*str, size\_t size, const char \*format, ...)

Output not more than *size* bytes to *str* according to the format string *format* and the extra arguments. See the Unix man page *snprintf(2)*.

int **PyOS\_vsnprintf** (char \*str, size\_t size, const char \*format, va\_list va)

Output not more than size bytes to str according to the format string format and the variable argument list va. Unix man page vsnprintf(2).

PyOS\_snprintf() and PyOS\_vsnprintf() wrap the Standard C library functions snprintf() and vsnprintf(). Their purpose is to guarantee consistent behavior in corner cases, which the Standard C functions do not.

The wrappers ensure that  $str^*[*size-1]$  is always '\0' upon return. They never write more than size bytes (including the trailing '\0') into str. Both functions require that str != NULL, size > 0 and format != NULL.

If the platform doesn't have vsnprintf() and the buffer size needed to avoid truncation exceeds *size* by more than 512 bytes, Python aborts with a *Py\_FatalError*.

The return value (rv) for these functions should be interpreted as follows:

- When 0 <= rv < size, the output conversion was successful and rv characters were written to str (excluding the trailing '\0' byte at str\*[\*rv]).
- When rv >= size, the output conversion was truncated and a buffer with rv + 1 bytes would have been needed to succeed. str\*[\*size-1] is '\0' in this case.
- When rv < 0, "something bad happened." str\*[\*size-1] is '\0' in this case too, but the rest of str is undefined. The exact cause of the error depends on the underlying platform.

The following functions provide locale-independent string to number conversions.

```
double PyOS_string_to_double (const char *s, char **endptr, PyObject *overflow_exception)
```

Convert a string s to a double, raising a Python exception on failure. The set of accepted strings corresponds to the set of strings accepted by Python's float () constructor, except that s must not have leading or trailing whitespace. The conversion is independent of the current locale.

If endptr is NULL, convert the whole string. Raise ValueError and return -1.0 if the string is not a valid representation of a floating-point number.

If endptr is not NULL, convert as much of the string as possible and set \*endptr to point to the first unconverted character. If no initial segment of the string is the valid representation of a floating-point number, set \*endptr to point to the beginning of the string, raise ValueError, and return -1.0.

If s represents a value that is too large to store in a float (for example, "1e500" is such a string on many platforms) then if overflow\_exception is NULL return Py\_HUGE\_VAL (with an appropriate sign) and don't set any exception. Otherwise, overflow\_exception must point to a Python exception object; raise that exception and return -1.0. In both cases, set \*endptr to point to the first character after the converted value.

If any other error occurs during the conversion (for example an out-of-memory error), set the appropriate Python exception and return -1.0.

New in version 3.1.

char\* PyOS\_double\_to\_string (double *val*, char *format\_code*, int *precision*, int *flags*, int \**ptype*)

Convert a double *val* to a string using supplied *format\_code*, *precision*, and *flags*.

format\_code must be one of 'e', 'E', 'f', 'F', 'g', 'G' or 'r'. For 'r', the supplied precision must be 0 and is ignored. The 'r' format code specifies the standard repr() format.

flags can be zero or more of the values Py\_DTSF\_SIGN, Py\_DTSF\_ADD\_DOT\_0, or Py\_DTSF\_ALT, or-ed to-gether:

- Py\_DTSF\_SIGN means to always precede the returned string with a sign character, even if val is non-negative.
- Py\_DTSF\_ADD\_DOT\_0 means to ensure that the returned string will not look like an integer.
- *Py\_DTSF\_ALT* means to apply "alternate" formatting rules. See the documentation for the *PyOS\_snprintf()* '#' specifier for details.

If *ptype* is non-NULL, then the value it points to will be set to one of *Py\_DTST\_FINITE*, *Py\_DTST\_INFINITE*, or *Py\_DTST\_NAN*, signifying that *val* is a finite number, an infinite number, or not a number, respectively.

52 Chapter 6. Utilities

The return value is a pointer to *buffer* with the converted string or *NULL* if the conversion failed. The caller is responsible for freeing the returned string by calling  $PyMem\ Free()$ .

New in version 3.1.

#### int PyOS stricmp (const char \*s1, const char \*s2)

Case insensitive comparison of strings. The function works almost identically to stromp () except that it ignores the case.

#### int **PyOS\_strnicmp** (const char \*s1, const char \*s2, Py\_ssize\_t size)

Case insensitive comparison of strings. The function works almost identically to strncmp() except that it ignores the case.

# 6.8 Reflection

# PyObject\* PyEval\_GetBuiltins()

Return value: Borrowed reference. Return a dictionary of the builtins in the current execution frame, or the interpreter of the thread state if no frame is currently executing.

#### PyObject\* PyEval\_GetLocals()

*Return value: Borrowed reference.* Return a dictionary of the local variables in the current execution frame, or *NULL* if no frame is currently executing.

#### PyObject\* PyEval\_GetGlobals()

*Return value: Borrowed reference.* Return a dictionary of the global variables in the current execution frame, or *NULL* if no frame is currently executing.

#### PyFrameObject\* PyEval GetFrame()

*Return value: Borrowed reference.* Return the current thread state's frame, which is *NULL* if no frame is currently executing.

# int PyFrame\_GetLineNumber (PyFrameObject \*frame)

Return the line number that *frame* is currently executing.

#### const char\* PyEval GetFuncName (PyObject \*func)

Return the name of *func* if it is a function, class or instance object, else the name of *func*s type.

#### const char\* PyEval\_GetFuncDesc (PyObject \*func)

Return a description string, depending on the type of *func*. Return values include "()" for functions and methods, "constructor", "instance", and "object". Concatenated with the result of <code>PyEval\_GetFuncName()</code>, the result will be a description of *func*.

# 6.9 Codec registry and support functions

#### int PyCodec\_Register (PyObject \*search\_function)

Register a new codec search function.

As side effect, this tries to load the encodings package, if not yet done, to make sure that it is always first in the list of search functions.

#### int PyCodec\_KnownEncoding (const char \*encoding)

Return 1 or 0 depending on whether there is a registered codec for the given *encoding*. This function always succeeds.

#### PyObject\* PyCodec\_Encode (PyObject \*object, const char \*encoding, const char \*errors)

Return value: New reference. Generic codec based encoding API.

6.8. Reflection 53

*object* is passed through the encoder function found for the given *encoding* using the error handling method defined by *errors*. *errors* may be *NULL* to use the default method defined for the codec. Raises a LookupError if no encoder can be found.

PyObject\* PyCodec\_Decode (PyObject \*object, const char \*encoding, const char \*errors)

Return value: New reference. Generic codec based decoding API.

*object* is passed through the decoder function found for the given *encoding* using the error handling method defined by *errors*. *errors* may be *NULL* to use the default method defined for the codec. Raises a LookupError if no encoder can be found.

# 6.9.1 Codec lookup API

In the following functions, the *encoding* string is looked up converted to all lower-case characters, which makes encodings looked up through this mechanism effectively case-insensitive. If no codec is found, a KeyError is set and *NULL* returned.

PyObject\* PyCodec\_Encoder (const char \*encoding)

Return value: New reference. Get an encoder function for the given encoding.

PyObject\* PyCodec\_Decoder (const char \*encoding)

Return value: New reference. Get a decoder function for the given encoding.

PyObject\* PyCodec\_IncrementalEncoder (const char \*encoding, const char \*errors)

Return value: New reference. Get an IncrementalEncoder object for the given encoding.

PyObject\* PyCodec\_IncrementalDecoder (const char \*encoding, const char \*errors)

Return value: New reference. Get an IncrementalDecoder object for the given encoding.

PyObject\* PyCodec\_StreamReader (const char \*encoding, PyObject \*stream, const char \*errors)

Return value: New reference. Get a StreamReader factory function for the given encoding.

PyObject\* PyCodec\_StreamWriter (const char \*encoding, PyObject \*stream, const char \*errors)

Return value: New reference. Get a StreamWriter factory function for the given encoding.

# 6.9.2 Registry API for Unicode encoding error handlers

int PyCodec\_RegisterError (const char \*name, PyObject \*error)

Register the error handling callback function *error* under the given *name*. This callback function will be called by a codec when it encounters unencodable characters/undecodable bytes and *name* is specified as the error parameter in the call to the encode/decode function.

The callback gets a single argument, an instance of UnicodeEncodeError, UnicodeDecodeError or UnicodeTranslateError that holds information about the problematic sequence of characters or bytes and their offset in the original string (see *Unicode Exception Objects* for functions to extract this information). The callback must either raise the given exception, or return a two-item tuple containing the replacement for the problematic sequence, and an integer giving the offset in the original string at which encoding/decoding should be resumed.

Return 0 on success, -1 on error.

PyObject\* PyCodec\_LookupError (const char \*name)

*Return value: New reference.* Lookup the error handling callback function registered under *name.* As a special case *NULL* can be passed, in which case the error handling callback for "strict" will be returned.

PyObject\* PyCodec\_StrictErrors (PyObject \*exc)

Return value: Always NULL. Raise exc as an exception.

PyObject\* PyCodec\_IgnoreErrors (PyObject \*exc)

Return value: New reference. Ignore the unicode error, skipping the faulty input.

#### PyObject\* PyCodec\_ReplaceErrors (PyObject \*exc)

Return value: New reference. Replace the unicode encode error with? or U+FFFD.

#### PyObject\* PyCodec\_XMLCharRefReplaceErrors (PyObject \*exc)

Return value: New reference. Replace the unicode encode error with XML character references.

## PyObject\* PyCodec\_BackslashReplaceErrors (PyObject \*exc)

Return value: New reference. Replace the unicode encode error with backslash escapes (\x, \u and \U).

#### PyObject\* PyCodec\_NameReplaceErrors (PyObject \*exc)

*Return value: New reference.* Replace the unicode encode error with \N{...} escapes.

New in version 3.5.

56 Chapter 6. Utilities

# ABSTRACT OBJECTS LAYER

The functions in this chapter interact with Python objects regardless of their type, or with wide classes of object types (e.g. all numerical types, or all sequence types). When used on object types for which they do not apply, they will raise a Python exception.

It is not possible to use these functions on objects that are not properly initialized, such as a list object that has been created by  $PyList_New()$ , but whose items have not been set to some non-NULL value yet.

# 7.1 Object Protocol

#### PyObject\* Py\_NotImplemented

The NotImplemented singleton, used to signal that an operation is not implemented for the given type combination.

#### Py RETURN NOTIMPLEMENTED

Properly handle returning Py\_NotImplemented from within a C function (that is, increment the reference count of NotImplemented and return it).

#### int PyObject\_Print (PyObject \*o, FILE \*fp, int flags)

Print an object o, on file fp. Returns -1 on error. The flags argument is used to enable certain printing options. The only option currently supported is Py\_PRINT\_RAW; if given, the str() of the object is written instead of the repr().

#### int PyObject HasAttr (PyObject \*o, PyObject \*attr name)

Returns 1 if o has the attribute  $attr\_name$ , and 0 otherwise. This is equivalent to the Python expression has attr(o, attr name). This function always succeeds.

Note that exceptions which occur while calling \_\_getattr\_\_() and \_\_getattribute\_\_() methods will get suppressed. To get error reporting use PyObject\_GetAttr() instead.

#### int PyObject\_HasAttrString (PyObject \*o, const char \*attr\_name)

Returns 1 if o has the attribute  $attr\_name$ , and 0 otherwise. This is equivalent to the Python expression hasattr(o, attr\\_name). This function always succeeds.

Note that exceptions which occur while calling  $\_\_getattr\_\_()$  and  $\_\_getattribute\_\_()$  methods and creating a temporary string object will get suppressed. To get error reporting use  $PyObject\_GetAttrString()$  instead.

#### PyObject\* PyObject\_GetAttr (PyObject \*o, PyObject \*attr\_name)

*Return value: New reference.* Retrieve an attribute named *attr\_name* from object *o*. Returns the attribute value on success, or *NULL* on failure. This is the equivalent of the Python expression o.attr\_name.

# PyObject\* PyObject\_GetAttrString (PyObject \*o, const char \*attr\_name)

*Return value: New reference.* Retrieve an attribute named *attr\_name* from object *o*. Returns the attribute value on success, or *NULL* on failure. This is the equivalent of the Python expression o .attr\_name.

#### PyObject\* PyObject\_GenericGetAttr (PyObject \*o, PyObject \*name)

Return value: New reference. Generic attribute getter function that is meant to be put into a type object's tp\_getattro slot. It looks for a descriptor in the dictionary of classes in the object's MRO as well as an attribute in the object's \_\_dict\_\_ (if present). As outlined in descriptors, data descriptors take preference over instance attributes, while non-data descriptors don't. Otherwise, an AttributeError is raised.

#### int PyObject\_SetAttr (PyObject \*o, PyObject \*attr\_name, PyObject \*v)

Set the value of the attribute named  $attr\_name$ , for object o, to the value v. Raise an exception and return -1 on failure; return 0 on success. This is the equivalent of the Python statement o .attr name = v.

If v is *NULL*, the attribute is deleted, however this feature is deprecated in favour of using  $PyObject\_DelAttr()$ .

# int PyObject\_SetAttrString (PyObject \*o, const char \*attr\_name, PyObject \*v)

Set the value of the attribute named  $attr\_name$ , for object o, to the value v. Raise an exception and return -1 on failure; return 0 on success. This is the equivalent of the Python statement  $o.attr\_name = v$ .

If v is *NULL*, the attribute is deleted, however this feature is deprecated in favour of using  $PyObject\_DelAttrString()$ .

#### int PyObject\_GenericSetAttr (PyObject \*o, PyObject \*name, PyObject \*value)

Generic attribute setter and deleter function that is meant to be put into a type object's tp\_setattro slot. It looks for a data descriptor in the dictionary of classes in the object's MRO, and if found it takes preference over setting or deleting the attribute in the instance dictionary. Otherwise, the attribute is set or deleted in the object's \_\_\_dict\_\_ (if present). On success, 0 is returned, otherwise an AttributeError is raised and -1 is returned.

#### int PyObject\_DelAttr (PyObject \*o, PyObject \*attr\_name)

Delete attribute named  $attr_name$ , for object o. Returns -1 on failure. This is the equivalent of the Python statement del o.attr\_name.

#### int PyObject\_DelAttrString (*PyObject \*o*, const char \*attr\_name)

Delete attribute named  $attr\_name$ , for object o. Returns -1 on failure. This is the equivalent of the Python statement del o.attr\\_name.

## PyObject\* PyObject\_GenericGetDict (PyObject \*o, void \*context)

*Return value: New reference.* A generic implementation for the getter of a \_\_\_dict\_\_\_ descriptor. It creates the dictionary if necessary.

New in version 3.3.

#### int PyObject\_GenericSetDict (PyObject \*o, void \*context)

A generic implementation for the setter of a \_\_dict\_\_ descriptor. This implementation does not allow the dictionary to be deleted.

New in version 3.3.

#### PyObject\* PyObject RichCompare (PyObject \*o1, PyObject \*o2, int opid)

Return value: New reference. Compare the values of o1 and o2 using the operation specified by opid, which must be one of Py\_LT, Py\_LE, Py\_EQ, Py\_NE, Py\_GT, or Py\_GE, corresponding to <, <=, ==, !=, >, or >= respectively. This is the equivalent of the Python expression o1 op o2, where op is the operator corresponding to opid. Returns the value of the comparison on success, or NULL on failure.

# int PyObject\_RichCompareBool (PyObject \*o1, PyObject \*o2, int opid)

Compare the values of o1 and o2 using the operation specified by opid, which must be one of Py\_LT, Py\_LE, Py\_EQ, Py\_NE, Py\_GT, or Py\_GE, corresponding to <, <=, ==, !=, >, or >= respectively. Returns -1 on error, 0 if the result is false, 1 otherwise. This is the equivalent of the Python expression o1 op o2, where op is the operator corresponding to opid.

Note: If o1 and o2 are the same object, PyObject RichCompareBool () will always return 1 for Py EQ and 0

for Py\_NE.

#### PyObject\* PyObject\_Repr (PyObject \*o)

Return value: New reference. Compute a string representation of object o. Returns the string representation on success, NULL on failure. This is the equivalent of the Python expression repr(0). Called by the repr() built-in function.

Changed in version 3.4: This function now includes a debug assertion to help ensure that it does not silently discard an active exception.

#### PyObject\* PyObject\_ASCII (PyObject \*o)

Return value: New reference. As  $PyObject\_Repr()$ , compute a string representation of object o, but escape the non-ASCII characters in the string returned by  $PyObject\_Repr()$  with  $\x$ ,  $\u$  or  $\u$  escapes. This generates a string similar to that returned by  $PyObject\_Repr()$  in Python 2. Called by the ascii() built-in function.

#### PyObject\* PyObject\_Str (PyObject \*o)

Return value: New reference. Compute a string representation of object o. Returns the string representation on success, NULL on failure. This is the equivalent of the Python expression str(0). Called by the str() built-in function and, therefore, by the print() function.

Changed in version 3.4: This function now includes a debug assertion to help ensure that it does not silently discard an active exception.

#### PyObject\* PyObject\_Bytes (PyObject \*o)

Return value: New reference. Compute a bytes representation of object o. NULL is returned on failure and a bytes object on success. This is equivalent to the Python expression bytes (o), when o is not an integer. Unlike bytes (o), a TypeError is raised when o is an integer instead of a zero-initialized bytes object.

#### int PyObject\_IsSubclass (PyObject \*derived, PyObject \*cls)

Return 1 if the class *derived* is identical to or derived from the class *cls*, otherwise return 0. In case of an error, return -1.

If *cls* is a tuple, the check will be done against every entry in *cls*. The result will be 1 when at least one of the checks returns 1, otherwise it will be 0.

If *cls* has a \_\_subclasscheck\_\_() method, it will be called to determine the subclass status as described in **PEP 3119**. Otherwise, *derived* is a subclass of *cls* if it is a direct or indirect subclass, i.e. contained in cls. \_\_mro\_\_.

Normally only class objects, i.e. instances of type or a derived class, are considered classes. However, objects can override this by having a bases attribute (which must be a tuple of base classes).

#### int PyObject\_IsInstance (PyObject \*inst, PyObject \*cls)

Return 1 if *inst* is an instance of the class cls or a subclass of cls, or 0 if not. On error, returns -1 and sets an exception.

If cls is a tuple, the check will be done against every entry in cls. The result will be 1 when at least one of the checks returns 1, otherwise it will be 0.

If *cls* has a \_\_instancecheck\_\_() method, it will be called to determine the subclass status as described in **PEP 3119**. Otherwise, *inst* is an instance of *cls* if its class is a subclass of *cls*.

An instance *inst* can override what is considered its class by having a \_\_class\_\_ attribute.

An object *cls* can override if it is considered a class, and what its base classes are, by having a \_\_bases\_\_ attribute (which must be a tuple of base classes).

### int PyCallable\_Check (PyObject \*o)

Determine if the object o is callable. Return 1 if the object is callable and 0 otherwise. This function always succeeds.

#### PyObject\* PyObject\_Call (PyObject \*callable, PyObject \*args, PyObject \*kwargs)

*Return value: New reference.* Call a callable Python object *callable*, with arguments given by the tuple *args*, and named arguments given by the dictionary *kwargs*.

args must not be NULL, use an empty tuple if no arguments are needed. If no named arguments are needed, kwargs can be NULL.

Return the result of the call on success, or raise an exception and return NULL on failure.

This is the equivalent of the Python expression: callable (\*args, \*\*kwargs).

#### PyObject\* PyObject\_CallObject (PyObject \*callable, PyObject \*args)

*Return value: New reference.* Call a callable Python object *callable*, with arguments given by the tuple *args*. If no arguments are needed, then *args* can be *NULL*.

Return the result of the call on success, or raise an exception and return NULL on failure.

This is the equivalent of the Python expression: callable (\*args).

## PyObject\* PyObject\_CallFunction (PyObject \*callable, const char \*format, ...)

Return value: New reference. Call a callable Python object callable, with a variable number of C arguments. The C arguments are described using a Py\_BuildValue() style format string. The format can be NULL, indicating that no arguments are provided.

Return the result of the call on success, or raise an exception and return NULL on failure.

This is the equivalent of the Python expression: callable(\*args).

Note that if you only pass PyObject \*args, PyObject\_CallFunctionObjArgs() is a faster alternative.

Changed in version 3.4: The type of *format* was changed from char \*.

#### PyObject\* PyObject\_CallMethod (PyObject \*obj, const char \*name, const char \*format, ...)

*Return value: New reference.* Call the method named *name* of object *obj* with a variable number of C arguments. The C arguments are described by a *Py\_BuildValue()* format string that should produce a tuple.

The format can be NULL, indicating that no arguments are provided.

Return the result of the call on success, or raise an exception and return NULL on failure.

This is the equivalent of the Python expression: obj.name(arg1, arg2, ...).

Note that if you only pass PyObject \* args, PyObject\_CallMethodObjArgs() is a faster alternative.

Changed in version 3.4: The types of *name* and *format* were changed from char \*.

#### PyObject\* PyObject\_CallFunctionObjArgs (PyObject \*callable, ..., NULL)

*Return value: New reference.* Call a callable Python object *callable*, with a variable number of *PyObject\** arguments. The arguments are provided as a variable number of parameters followed by *NULL*.

Return the result of the call on success, or raise an exception and return NULL on failure.

This is the equivalent of the Python expression: callable (arg1, arg2, ...).

### PyObject\* PyObject\_CallMethodObjArgs (PyObject \*obj, PyObject \*name, ..., NULL)

Return value: New reference. Calls a method of the Python object obj, where the name of the method is given as a Python string object in name. It is called with a variable number of PyObject\* arguments. The arguments are provided as a variable number of parameters followed by NULL.

Return the result of the call on success, or raise an exception and return NULL on failure.

```
PyObject* _PyObject *const *args, size_t nargsf, PyObject *kw-
```

names)

Call a callable Python object callable, using vectorcall if possible.

args is a C array with the positional arguments.

nargsf is the number of positional arguments plus optionally the flag PY\_VECTORCALL\_ARGUMENTS\_OFFSET (see below). To get actual number of arguments, use PyVectorcall NARGS (nargsf).

kwnames can be either NULL (no keyword arguments) or a tuple of keyword names. In the latter case, the values of the keyword arguments are stored in *args* after the positional arguments. The number of keyword arguments does not influence *nargsf*.

kwnames must contain only objects of type str (not a subclass), and all keys must be unique.

Return the result of the call on success, or raise an exception and return NULL on failure.

This uses the vectorcall protocol if the callable supports it; otherwise, the arguments are converted to use  $tp_call$ .

**Note:** This function is provisional and expected to become public in Python 3.9, with a different name and, possibly, changed semantics. If you use the function, plan for updating your code for Python 3.9.

New in version 3.8.

#### PY\_VECTORCALL\_ARGUMENTS\_OFFSET

If set in a vectorcall *nargsf* argument, the callee is allowed to temporarily change args[-1]. In other words, *args* points to argument 1 (not 0) in the allocated vector. The callee must restore the value of args[-1] before returning.

Whenever they can do so cheaply (without additional allocation), callers are encouraged to use PY\_VECTORCALL\_ARGUMENTS\_OFFSET. Doing so will allow callables such as bound methods to make their onward calls (which include a prepended *self* argument) cheaply.

New in version 3.8.

#### Py\_ssize\_t PyVectorcall\_NARGS (size\_t nargsf)

Given a vectorcall *nargsf* argument, return the actual number of arguments. Currently equivalent to nargsf & ~PY\_VECTORCALL\_ARGUMENTS\_OFFSET.

New in version 3.8.

# PyObject\*\_PyObject\_FastCallDict(PyObject \*callable, PyObject \*const \*args, size\_t nargsf, PyObject \*kwdict)

Same as \_PyObject\_Vectorcall() except that the keyword arguments are passed as a dictionary in *kwdict*. This may be *NULL* if there are no keyword arguments.

For callables supporting <code>vectorcal1</code>, the arguments are internally converted to the vectorcall convention. Therefore, this function adds some overhead compared to <code>\_PyObject\_Vectorcal1()</code>. It should only be used if the caller already has a dictionary ready to use.

**Note:** This function is provisional and expected to become public in Python 3.9, with a different name and, possibly, changed semantics. If you use the function, plan for updating your code for Python 3.9.

New in version 3.8.

#### Py\_hash\_t PyObject\_Hash (PyObject \*o)

Compute and return the hash value of an object o. On failure, return -1. This is the equivalent of the Python expression hash (o).

Changed in version 3.2: The return type is now Py\_hash\_t. This is a signed integer the same size as Py\_ssize\_t.

#### Py\_hash\_t PyObject\_HashNotImplemented (PyObject \*o)

Set a TypeError indicating that type (o) is not hashable and return -1. This function receives special treatment when stored in a tp\_hash slot, allowing a type to explicitly indicate to the interpreter that it is not hashable.

#### int PyObject IsTrue (PyObject \*o)

Returns 1 if the object o is considered to be true, and 0 otherwise. This is equivalent to the Python expression not not o. On failure, return -1.

#### int PyObject\_Not (PyObject \*o)

Returns 0 if the object o is considered to be true, and 1 otherwise. This is equivalent to the Python expression not o. On failure, return -1.

#### PyObject\* PyObject \*o)

Return value: New reference. When o is non-NULL, returns a type object corresponding to the object type of object o. On failure, raises SystemError and returns NULL. This is equivalent to the Python expression type (0). This function increments the reference count of the return value. There's really no reason to use this function instead of the common expression  $o->ob_type$ , which returns a pointer of type PyTypeObject\*, except when the incremented reference count is needed.

#### int PyObject\_TypeCheck (PyObject \*o, PyTypeObject \*type)

Return true if the object o is of type type or a subtype of type. Both parameters must be non-NULL.

```
Py_ssize_t PyObject_Size (PyObject *o)
```

#### Py\_ssize\_t PyObject\_Length (PyObject \*o)

Return the length of object o. If the object o provides either the sequence and mapping protocols, the sequence length is returned. On error, -1 is returned. This is the equivalent to the Python expression len(o).

## Py\_ssize\_t PyObject\_LengthHint (PyObject \*o, Py\_ssize\_t default)

Return an estimated length for the object o. First try to return its actual length, then an estimate using \_\_length\_hint\_\_(), and finally return the default value. On error return -1. This is the equivalent to the Python expression operator.length\_hint(o, default).

New in version 3.4.

#### PyObject\* PyObject\_GetItem (PyObject \*o, PyObject \*key)

*Return value: New reference.* Return element of o corresponding to the object key or NULL on failure. This is the equivalent of the Python expression o[key].

#### int PyObject\_SetItem (PyObject \*o, PyObject \*key, PyObject \*v)

Map the object key to the value v. Raise an exception and return -1 on failure; return 0 on success. This is the equivalent of the Python statement o[key] = v.

#### int PyObject\_DelItem (PyObject \*o, PyObject \*key)

Remove the mapping for the object *key* from the object o. Return -1 on failure. This is equivalent to the Python statement del o[key].

#### PyObject\* PyObject\_Dir (PyObject \*o)

Return value: New reference. This is equivalent to the Python expression dir(0), returning a (possibly empty) list of strings appropriate for the object argument, or NULL if there was an error. If the argument is NULL, this is like the Python dir(), returning the names of the current locals; in this case, if no execution frame is active then NULL is returned but PyErr\_Occurred() will return false.

### PyObject\* PyObject\_GetIter (PyObject \*o)

Return value: New reference. This is equivalent to the Python expression iter(0). It returns a new iterator for the object argument, or the object itself if the object is already an iterator. Raises TypeError and returns NULL if the object cannot be iterated.

# 7.2 Number Protocol

## int PyNumber\_Check (PyObject \*o)

Returns 1 if the object o provides numeric protocols, and false otherwise. This function always succeeds.

Changed in version 3.8: Returns 1 if o is an index integer.

#### PyObject\* PyNumber Add (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the result of adding o1 and o2, or NULL on failure. This is the equivalent of the Python expression o1 + o2.

#### PyObject\* PyNumber\_Subtract (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the result of subtracting o2 from o1, or NULL on failure. This is the equivalent of the Python expression o1 - o2.

## PyObject\* PyNumber\_Multiply (PyObject \*o1, PyObject \*o2)

*Return value: New reference.* Returns the result of multiplying o1 and o2, or *NULL* on failure. This is the equivalent of the Python expression o1 \* o2.

### PyObject\* PyNumber\_MatrixMultiply (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the result of matrix multiplication on o1 and o2, or NULL on failure. This is the equivalent of the Python expression o1 @ o2.

New in version 3.5.

#### PyObject\* PyNumber\_FloorDivide (PyObject \*o1, PyObject \*o2)

*Return value: New reference.* Return the floor of *o1* divided by *o2*, or *NULL* on failure. This is equivalent to the "classic" division of integers.

#### PyObject\* PyNumber\_TrueDivide (PyObject \*o1, PyObject \*o2)

Return value: New reference. Return a reasonable approximation for the mathematical value of o1 divided by o2, or NULL on failure. The return value is "approximate" because binary floating point numbers are approximate; it is not possible to represent all real numbers in base two. This function can return a floating point value when passed two integers.

#### PyObject\* PyNumber\_Remainder (PyObject \*o1, PyObject \*o2)

*Return value: New reference.* Returns the remainder of dividing o1 by o2, or NULL on failure. This is the equivalent of the Python expression o1 % o2.

#### PyObject\* PyNumber\_Divmod (PyObject \*o1, PyObject \*o2)

*Return value: New reference.* See the built-in function divmod(). Returns *NULL* on failure. This is the equivalent of the Python expression divmod(o1, o2).

#### PyObject\* PyNumber\_Power (PyObject \*o1, PyObject \*o2, PyObject \*o3)

Return value: New reference. See the built-in function pow(). Returns NULL on failure. This is the equivalent of the Python expression pow(o1, o2, o3), where o3 is optional. If o3 is to be ignored, pass  $Py\_None$  in its place (passing NULL for o3 would cause an illegal memory access).

#### PyObject\* PyNumber\_Negative (PyObject \*o)

Return value: New reference. Returns the negation of o on success, or NULL on failure. This is the equivalent of the Python expression  $-\circ$ .

#### PyObject\* PyNumber\_Positive (PyObject \*o)

Return value: New reference. Returns o on success, or NULL on failure. This is the equivalent of the Python expression  $+\circ$ .

# PyObject\* PyNumber\_Absolute (PyObject \*o)

*Return value: New reference.* Returns the absolute value of o, or *NULL* on failure. This is the equivalent of the Python expression abs (o).

#### PyObject\* PyNumber\_Invert (PyObject \*o)

*Return value: New reference.* Returns the bitwise negation of o on success, or *NULL* on failure. This is the equivalent of the Python expression  $\sim \circ$ .

## PyObject\* PyNumber\_Lshift (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the result of left shifting o1 by o2 on success, or NULL on failure. This is the

7.2. Number Protocol 63

equivalent of the Python expression 01 << 02.

#### PyObject\* PyNumber Rshift (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the result of right shifting o1 by o2 on success, or NULL on failure. This is the equivalent of the Python expression 01 >> 02.

#### PyObject\* PyNumber\_And (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the "bitwise and" of o1 and o2 on success and NULL on failure. This is the equivalent of the Python expression o1 & o2.

#### PyObject\* PyNumber\_Xor (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the "bitwise exclusive or" of o1 by o2 on success, or NULL on failure. This is the equivalent of the Python expression o1 oo o2.

### PyObject\* PyNumber\_Or (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the "bitwise or" of o1 and o2 on success, or NULL on failure. This is the equivalent of the Python expression  $o1 \mid o2$ .

#### PyObject\* PyNumber\_InPlaceAdd (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the result of adding o1 and o2, or NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement  $\circ 1 += \circ 2$ .

#### PyObject\* PyNumber\_InPlaceSubtract (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the result of subtracting o2 from o1, or NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement o1 = o2.

#### PyObject\* PyNumber\_InPlaceMultiply (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the result of multiplying o1 and o2, or NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement o1 \*= o2.

#### PyObject\* PyNumber\_InPlaceMatrixMultiply (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the result of matrix multiplication on o1 and o2, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 = o2.

New in version 3.5.

#### PyObject\* PyNumber\_InPlaceFloorDivide (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the mathematical floor of dividing o1 by o2, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 //= o2.

#### PyObject\* PyNumber\_InPlaceTrueDivide (PyObject \*o1, PyObject \*o2)

Return value: New reference. Return a reasonable approximation for the mathematical value of o1 divided by o2, or NULL on failure. The return value is "approximate" because binary floating point numbers are approximate; it is not possible to represent all real numbers in base two. This function can return a floating point value when passed two integers. The operation is done in-place when o1 supports it.

#### PyObject\* PyNumber InPlaceRemainder (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the remainder of dividing o1 by o2, or NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement o1 % = o2.

#### PyObject\* PyNumber\_InPlacePower (PyObject \*o1, PyObject \*o2, PyObject \*o3)

Return value: New reference. See the built-in function pow(). Returns NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement o1 \*\*= o2 when o3 is  $Py\_None$ , or an in-place variant of pow(o1, o2, o3) otherwise. If o3 is to be ignored, pass  $Py\_None$  in its place (passing NULL for o3 would cause an illegal memory access).

#### PyObject\* PyNumber\_InPlaceLshift (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the result of left shifting o1 by o2 on success, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 <<= o2.

#### PyObject\* PyNumber\_InPlaceRshift (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the result of right shifting o1 by o2 on success, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 >>= o2.

### PyObject\* PyNumber\_InPlaceAnd (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the "bitwise and" of ol and ol on success and NULL on failure. The operation is done in-place when ol supports it. This is the equivalent of the Python statement ol &=  $oldsymbol{o$ 

#### PyObject\* PyNumber InPlaceXor (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the "bitwise exclusive or" of o1 by o2 on success, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement  $o1 ^= o2$ .

#### PyObject\* PyNumber\_InPlaceOr (PyObject \*o1, PyObject \*o2)

Return value: New reference. Returns the "bitwise or" of o1 and o2 on success, or NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement o1 = o2.

#### PyObject\* PyNumber\_Long (PyObject \*o)

*Return value: New reference.* Returns the o converted to an integer object on success, or NULL on failure. This is the equivalent of the Python expression int (o).

#### PyObject\* PyNumber\_Float (PyObject \*o)

*Return value: New reference.* Returns the o converted to a float object on success, or NULL on failure. This is the equivalent of the Python expression float (o).

#### PyObject\* PyNumber\_Index (PyObject \*o)

*Return value: New reference.* Returns the *o* converted to a Python int on success or *NULL* with a TypeError exception raised on failure.

#### PyObject\* PyNumber\_ToBase (PyObject \*n, int base)

Return value: New reference. Returns the integer n converted to base base as a string. The base argument must be one of 2, 8, 10, or 16. For base 2, 8, or 16, the returned string is prefixed with a base marker of '0b', '0o', or '0x', respectively. If n is not a Python int, it is converted with  $PyNumber_Index()$  first.

#### Py\_ssize\_t PyNumber\_AsSsize\_t (PyObject \*o, PyObject \*exc)

Returns o converted to a Py\_ssize\_t value if o can be interpreted as an integer. If the call fails, an exception is raised and -1 is returned.

If o can be converted to a Python int but the attempt to convert to a Py\_ssize\_t value would raise an OverflowError, then the exc argument is the type of exception that will be raised (usually IndexError or OverflowError). If exc is NULL, then the exception is cleared and the value is clipped to PY\_SSIZE\_T\_MIN for a negative integer or PY\_SSIZE\_T\_MAX for a positive integer.

#### int PyIndex\_Check (PyObject \*o)

Returns 1 if o is an index integer (has the nb\_index slot of the tp\_as\_number structure filled in), and 0 otherwise. This function always succeeds.

# 7.3 Sequence Protocol

#### int PySequence\_Check (PyObject \*o)

Return 1 if the object provides sequence protocol, and 0 otherwise. Note that it returns 1 for Python classes with a \_\_getitem\_\_() method unless they are dict subclasses since in general case it is impossible to determine what the type of keys it supports. This function always succeeds.

#### Py\_ssize\_t PySequence\_Size (PyObject \*o)

#### Py\_ssize\_t PySequence\_Length (PyObject \*o)

Returns the number of objects in sequence o on success, and -1 on failure. This is equivalent to the Python expression len (o).

#### PyObject\* PySequence\_Concat (PyObject \*o1, PyObject \*o2)

Return value: New reference. Return the concatenation of o1 and o2 on success, and NULL on failure. This is the equivalent of the Python expression o1 + o2.

#### PyObject\* PySequence\_Repeat (PyObject \*o, Py\_ssize\_t count)

Return value: New reference. Return the result of repeating sequence object o count times, or NULL on failure. This is the equivalent of the Python expression o \* count.

#### PyObject\* PySequence InPlaceConcat (PyObject \*o1, PyObject \*o2)

Return value: New reference. Return the concatenation of o1 and o2 on success, and NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python expression o1 += o2.

#### PyObject\* PySequence\_InPlaceRepeat (PyObject \*o, Py\_ssize\_t count)

Return value: New reference. Return the result of repeating sequence object o count times, or NULL on failure. The operation is done in-place when o supports it. This is the equivalent of the Python expression  $\circ$  \*= count.

#### PyObject\* PySequence\_GetItem (PyObject \*o, Py\_ssize\_t i)

*Return value: New reference.* Return the *i*th element of o, or *NULL* on failure. This is the equivalent of the Python expression o[i].

#### PyObject\* PySequence\_GetSlice (PyObject \*o, Py\_ssize\_t i1, Py\_ssize\_t i2)

*Return value: New reference.* Return the slice of sequence object o between i1 and i2, or NULL on failure. This is the equivalent of the Python expression o[i1:i2].

#### int PySequence\_SetItem (PyObject \*o, Py\_ssize\_t i, PyObject \*v)

Assign object v to the ith element of o. Raise an exception and return -1 on failure; return 0 on success. This is the equivalent of the Python statement o[i] = v. This function *does not* steal a reference to v.

If v is NULL, the element is deleted, however this feature is deprecated in favour of using  $PySequence\_DelItem()$ .

#### int PySequence\_DelItem (PyObject \*o, Py\_ssize\_t i)

Delete the *i*th element of object o. Returns -1 on failure. This is the equivalent of the Python statement del o[i].

#### int PySequence\_SetSlice (PyObject \*o, Py\_ssize\_t i1, Py\_ssize\_t i2, PyObject \*v)

Assign the sequence object v to the slice in sequence object o from i1 to i2. This is the equivalent of the Python statement o[i1:i2] = v.

#### int PySequence\_DelSlice (PyObject \*o, Py\_ssize\_t i1, Py\_ssize\_t i2)

Delete the slice in sequence object o from il to i2. Returns -1 on failure. This is the equivalent of the Python statement del o[i1:i2].

#### Py\_ssize\_t PySequence\_Count (PyObject \*o, PyObject \*value)

Return the number of occurrences of *value* in o, that is, return the number of keys for which o [key] == value. On failure, return -1. This is equivalent to the Python expression o.count (value).

#### int PySequence\_Contains (PyObject \*o, PyObject \*value)

Determine if o contains *value*. If an item in o is equal to *value*, return 1, otherwise return 0. On error, return -1. This is equivalent to the Python expression value in o.

# Py\_ssize\_t PySequence\_Index (PyObject \*o, PyObject \*value)

Return the first index i for which o[i] == value. On error, return -1. This is equivalent to the Python expression o.index(value).

#### PyObject\* PySequence\_List (PyObject \*o)

*Return value: New reference.* Return a list object with the same contents as the sequence or iterable o, or *NULL* on failure. The returned list is guaranteed to be new. This is equivalent to the Python expression list (o).

## PyObject\* PySequence\_Tuple (PyObject \*o)

Return value: New reference. Return a tuple object with the same contents as the sequence or iterable o, or NULL on

failure. If o is a tuple, a new reference will be returned, otherwise a tuple will be constructed with the appropriate contents. This is equivalent to the Python expression tuple (o).

# PyObject\* PySequence\_Fast (PyObject \*o, const char \*m)

Return value: New reference. Return the sequence or iterable o as an object usable by the other PySequence\_Fast\* family of functions. If the object is not a sequence or iterable, raises TypeError with m as the message text. Returns NULL on failure.

The PySequence\_Fast\* functions are thus named because they assume o is a PyTupleObject or a PyListObject and access the data fields of o directly.

As a CPython implementation detail, if o is already a sequence or list, it will be returned.

# Py\_ssize\_t PySequence\_Fast\_GET\_SIZE (PyObject \*o)

Returns the length of o, assuming that o was returned by  $PySequence\_Fast$  () and that o is not NULL. The size can also be gotten by calling  $PySequence\_Size$  () on o, but  $PySequence\_Fast\_GET\_SIZE$  () is faster because it can assume o is a list or tuple.

# PyObject\* PySequence\_Fast\_GET\_ITEM (PyObject \*o, Py\_ssize\_t i)

Return value: Borrowed reference. Return the ith element of o, assuming that o was returned by  $PySequence\ Fast()$ , o is not NULL, and that i is within bounds.

# PyObject\*\* PySequence\_Fast\_ITEMS (PyObject \*o)

Return the underlying array of PyObject pointers. Assumes that o was returned by  $PySequence\_Fast$  () and o is not NULL.

Note, if a list gets resized, the reallocation may relocate the items array. So, only use the underlying array pointer in contexts where the sequence cannot change.

# PyObject\* PySequence\_ITEM (PyObject \*o, Py\_ssize\_t i)

Return value: New reference. Return the ith element of o or NULL on failure. Faster form of PySequence\_GetItem() but without checking that PySequence\_Check() on o is true and without adjustment for negative indices.

# 7.4 Mapping Protocol

See also PyObject\_GetItem(), PyObject\_SetItem() and PyObject\_DelItem().

# int PyMapping\_Check (PyObject \*o)

Return 1 if the object provides mapping protocol or supports slicing, and 0 otherwise. Note that it returns 1 for Python classes with a \_\_getitem\_\_() method since in general case it is impossible to determine what the type of keys it supports. This function always succeeds.

# Py\_ssize\_t PyMapping\_Size (PyObject \*o)

# Py\_ssize\_t PyMapping\_Length (PyObject \*o)

Returns the number of keys in object o on success, and -1 on failure. This is equivalent to the Python expression len (o).

# PyObject\* PyMapping\_GetItemString (PyObject \*o, const char \*key)

*Return value: New reference.* Return element of o corresponding to the string key or NULL on failure. This is the equivalent of the Python expression o [key]. See also  $PyObject\_GetItem()$ .

#### int PyMapping SetItemString (PyObject \*o, const char \*key, PyObject \*v)

Map the string key to the value v in object o. Returns -1 on failure. This is the equivalent of the Python statement o[key] = v. See also  $PyObject\_SetItem()$ .

# int PyMapping\_DelItem (PyObject \*o, PyObject \*key)

Remove the mapping for the object *key* from the object o. Return -1 on failure. This is equivalent to the Python statement del o[key]. This is an alias of  $PyObject\_DelItem()$ .

#### int **PyMapping\_DelItemString** (*PyObject* \*o, const char \*key)

Remove the mapping for the string *key* from the object o. Return -1 on failure. This is equivalent to the Python statement del o[key].

# int PyMapping\_HasKey (PyObject \*o, PyObject \*key)

Return 1 if the mapping object has the key *key* and 0 otherwise. This is equivalent to the Python expression key in o. This function always succeeds.

Note that exceptions which occur while calling the \_\_getitem\_\_() method will get suppressed. To get error reporting use PyObject GetItem() instead.

```
int PyMapping_HasKeyString (PyObject *o, const char *key)
```

Return 1 if the mapping object has the key *key* and 0 otherwise. This is equivalent to the Python expression key in o. This function always succeeds.

Note that exceptions which occur while calling the \_\_getitem\_\_() method and creating a temporary string object will get suppressed. To get error reporting use PyMapping\_GetItemString() instead.

```
PyObject* PyMapping_Keys (PyObject *o)
```

Return value: New reference. On success, return a list of the keys in object o. On failure, return NULL.

Changed in version 3.7: Previously, the function returned a list or a tuple.

```
PyObject* PyMapping_Values (PyObject *o)
```

Return value: New reference. On success, return a list of the values in object o. On failure, return NULL.

Changed in version 3.7: Previously, the function returned a list or a tuple.

```
PyObject* PyMapping_Items (PyObject *o)
```

*Return value: New reference.* On success, return a list of the items in object o, where each item is a tuple containing a key-value pair. On failure, return *NULL*.

Changed in version 3.7: Previously, the function returned a list or a tuple.

# 7.5 Iterator Protocol

There are two functions specifically for working with iterators.

```
int PyIter_Check (PyObject *o)
```

Return true if the object *o* supports the iterator protocol.

```
PyObject* PyIter_Next (PyObject *o)
```

*Return value: New reference.* Return the next value from the iteration o. The object must be an iterator (it is up to the caller to check this). If there are no remaining values, returns *NULL* with no exception set. If an error occurs while retrieving the item, returns *NULL* and passes along the exception.

To write a loop which iterates over an iterator, the C code should look something like this:

```
PyObject *iterator = PyObject_GetIter(obj);
PyObject *item;

if (iterator == NULL) {
    /* propagate error */
}

while (item = PyIter_Next(iterator)) {
    /* do something with item */
    ...
    /* release reference when done */
```

(continues on next page)

(continued from previous page)

```
Py_DECREF(item);
}

Py_DECREF(iterator);

if (PyErr_Occurred()) {
    /* propagate error */
}
else {
    /* continue doing useful work */
}
```

# 7.6 Buffer Protocol

Certain objects available in Python wrap access to an underlying memory array or *buffer*. Such objects include the built-in bytes and bytearray, and some extension types like array. Third-party libraries may define their own types for special purposes, such as image processing or numeric analysis.

While each of these types have their own semantics, they share the common characteristic of being backed by a possibly large memory buffer. It is then desirable, in some situations, to access that buffer directly and without intermediate copying.

Python provides such a facility at the C level in the form of the buffer protocol. This protocol has two sides:

- on the producer side, a type can export a "buffer interface" which allows objects of that type to expose information about their underlying buffer. This interface is described in the section *Buffer Object Structures*;
- on the consumer side, several means are available to obtain a pointer to the raw underlying data of an object (for example a method parameter).

Simple objects such as bytes and bytearray expose their underlying buffer in byte-oriented form. Other forms are possible; for example, the elements exposed by an array can be multi-byte values.

An example consumer of the buffer interface is the write() method of file objects: any object that can export a series of bytes through the buffer interface can be written to a file. While write() only needs read-only access to the internal contents of the object passed to it, other methods such as readinto() need write access to the contents of their argument. The buffer interface allows objects to selectively allow or reject exporting of read-write and read-only buffers.

There are two ways for a consumer of the buffer interface to acquire a buffer over a target object:

- call PyObject\_GetBuffer() with the right parameters;
- call PyArq\_ParseTuple() (or one of its siblings) with one of the y\*, w\* or s\* format codes.

In both cases, <code>PyBuffer\_Release()</code> must be called when the buffer isn't needed anymore. Failure to do so could lead to various issues such as resource leaks.

# 7.6.1 Buffer structure

Buffer structures (or simply "buffers") are useful as a way to expose the binary data from another object to the Python programmer. They can also be used as a zero-copy slicing mechanism. Using their ability to reference a block of memory, it is possible to expose any data to the Python programmer quite easily. The memory could be a large, constant array in a C extension, it could be a raw block of memory for manipulation before passing to an operating system library, or it could be used to pass around structured data in its native, in-memory format.

7.6. Buffer Protocol 69

Contrary to most data types exposed by the Python interpreter, buffers are not PyObject pointers but rather simple C structures. This allows them to be created and copied very simply. When a generic wrapper around a buffer is needed, a memoryview object can be created.

For short instructions how to write an exporting object, see *Buffer Object Structures*. For obtaining a buffer, see *PyObject\_GetBuffer()*.

#### Py buffer

#### void \*buf

A pointer to the start of the logical structure described by the buffer fields. This can be any location within the underlying physical memory block of the exporter. For example, with negative <code>strides</code> the value may point to the end of the memory block.

For *contiguous* arrays, the value points to the beginning of the memory block.

# void \*obj

A new reference to the exporting object. The reference is owned by the consumer and automatically decremented and set to *NULL* by *PyBuffer\_Release()*. The field is the equivalent of the return value of any standard C-API function.

As a special case, for *temporary* buffers that are wrapped by *PyMemoryView\_FromBuffer()* or *PyBuffer\_FillInfo()* this field is *NULL*. In general, exporting objects MUST NOT use this scheme.

#### Py\_ssize\_t len

product (shape) \* itemsize. For contiguous arrays, this is the length of the underlying memory block. For non-contiguous arrays, it is the length that the logical structure would have if it were copied to a contiguous representation.

Accessing ((char \*)buf)[0] up to ((char \*)buf)[len-1] is only valid if the buffer has been obtained by a request that guarantees contiguity. In most cases such a request will be PyBUF\_SIMPLE or PyBUF\_WRITABLE.

# int readonly

An indicator of whether the buffer is read-only. This field is controlled by the PyBUF\_WRITABLE flag.

#### Pv ssize titemsize

Item size in bytes of a single element. Same as the value of struct.calcsize() called on non-NULL format values.

Important exception: If a consumer requests a buffer without the PyBUF\_FORMAT flag, format will be set to NULL, but itemsize still has the value for the original format.

If *shape* is present, the equality product (shape) \* itemsize == len still holds and the consumer can use *itemsize* to navigate the buffer.

If shape is NULL as a result of a  $PyBUF\_SIMPLE$  or a  $PyBUF\_WRITABLE$  request, the consumer must disregard itemsize and assume itemsize == 1.

#### const char \*format

A *NUL* terminated string in struct module style syntax describing the contents of a single item. If this is *NULL*, "B" (unsigned bytes) is assumed.

This field is controlled by the PyBUF\_FORMAT flag.

#### int ndim

The number of dimensions the memory represents as an n-dimensional array. If it is 0, buf points to a single item representing a scalar. In this case, shape, strides and suboffsets MUST be NULL.

The macro PyBUF\_MAX\_NDIM limits the maximum number of dimensions to 64. Exporters MUST respect this limit, consumers of multi-dimensional buffers SHOULD be able to handle up to PyBUF MAX NDIM

dimensions.

### Py\_ssize\_t \*shape

An array of Py\_ssize\_t of length ndim indicating the shape of the memory as an n-dimensional array. Note that shape [0] \* ... \* shape [ndim-1] \* itemsize MUST be equal to <math>len.

Shape values are restricted to shape[n] >= 0. The case shape[n] == 0 requires special attention. See *complex arrays* for further information.

The shape array is read-only for the consumer.

#### Py\_ssize\_t \*strides

An array of Py\_ssize\_t of length *ndim* giving the number of bytes to skip to get to a new element in each dimension.

Stride values can be any integer. For regular arrays, strides are usually positive, but a consumer MUST be able to handle the case  $strides[n] \le 0$ . See *complex arrays* for further information.

The strides array is read-only for the consumer.

# Py\_ssize\_t \*suboffsets

An array of Py\_ssize\_t of length ndim. If suboffsets[n] >= 0, the values stored along the nth dimension are pointers and the suboffset value dictates how many bytes to add to each pointer after dereferencing. A suboffset value that is negative indicates that no de-referencing should occur (striding in a contiguous memory block).

If all suboffsets are negative (i.e. no de-referencing is needed), then this field must be NULL (the default value).

This type of array representation is used by the Python Imaging Library (PIL). See *complex arrays* for further information how to access elements of such an array.

The suboffsets array is read-only for the consumer.

#### void \*internal

This is for use internally by the exporting object. For example, this might be re-cast as an integer by the exporter and used to store flags about whether or not the shape, strides, and suboffsets arrays must be freed when the buffer is released. The consumer MUST NOT alter this value.

# 7.6.2 Buffer request types

Buffers are usually obtained by sending a buffer request to an exporting object via PyObject\_GetBuffer(). Since the complexity of the logical structure of the memory can vary drastically, the consumer uses the *flags* argument to specify the exact buffer type it can handle.

All Py\_buffer fields are unambiguously defined by the request type.

# request-independent fields

The following fields are not influenced by *flags* and must always be filled in with the correct values: obj, buf, len, itemsize, ndim.

#### readonly, format

#### PyBUF WRITABLE

Controls the *readonly* field. If set, the exporter MUST provide a writable buffer or else report failure. Otherwise, the exporter MAY provide either a read-only or writable buffer, but the choice MUST be consistent for all consumers.

7.6. Buffer Protocol 71

#### PyBUF\_FORMAT

Controls the *format* field. If set, this field MUST be filled in correctly. Otherwise, this field MUST be *NULL*.

PyBUF\_WRITABLE can be I'd to any of the flags in the next section. Since PyBUF\_SIMPLE is defined as 0, PyBUF\_WRITABLE can be used as a stand-alone flag to request a simple writable buffer.

 $PyBUF\_FORMAT$  can be I'd to any of the flags except  $PyBUF\_SIMPLE$ . The latter already implies format B (unsigned bytes).

# shape, strides, suboffsets

The flags that control the logical structure of the memory are listed in decreasing order of complexity. Note that each flag contains all bits of the flags below it.

Request	shape	strides	suboffsets
PyBUF_INDIRECT	yes	yes	if needed
PyBUF_STRIDES	yes	yes	NULL
PyBUF_ND	yes	NULL	NULL
PyBUF_SIMPLE	NULL	NULL	NULL

# contiguity requests

C or Fortran *contiguity* can be explicitly requested, with and without stride information. Without stride information, the buffer must be C-contiguous.

Request	shape	strides	suboffsets	contig
PyBUF_C_CONTIGUOUS	yes	yes	NULL	С
PyBUF_F_CONTIGUOUS	yes	yes	NULL	F
PyBUF_ANY_CONTIGUOUS	yes	yes	NULL	C or F
PyBUF_ND	yes	NULL	NULL	С

#### compound requests

All possible requests are fully defined by some combination of the flags in the previous section. For convenience, the buffer protocol provides frequently used combinations as single flags.

In the following table U stands for undefined contiguity. The consumer would have to call  $PyBuffer\_IsContiguous$  () to determine contiguity.

Request	shape	strides	suboffsets	contig	readonly	format
PyBUF_FULL	yes	yes	if needed	U	0	yes
PyBUF_FULL_RO	yes	yes	if needed	U	1 or 0	yes
PyBUF_RECORDS	yes	yes	NULL	U	0	yes
PyBUF_RECORDS_RO	yes	yes	NULL	U	1 or 0	yes
PyBUF_STRIDED	yes	yes	NULL	U	0	NULL
PyBUF_STRIDED_RO	yes	yes	NULL	U	1 or 0	NULL
PyBUF_CONTIG	yes	NULL	NULL	С	0	NULL
PyBUF_CONTIG_RO	yes	NULL	NULL	С	1 or 0	NULL

# 7.6.3 Complex arrays

# NumPy-style: shape and strides

The logical structure of NumPy-style arrays is defined by itemsize, ndim, shape and strides.

If ndim == 0, the memory location pointed to by buf is interpreted as a scalar of size itemsize. In that case, both shape and strides are NULL.

If strides is NULL, the array is interpreted as a standard n-dimensional C-array. Otherwise, the consumer must access an n-dimensional array as follows:

```
ptr = (char *)buf + indices[0] * strides[0] + ... + indices[n-1] * strides[n-1];
item = *((typeof(item) *)ptr);
```

As noted above, buf can point to any location within the actual memory block. An exporter can check the validity of a buffer with this function:

```
def verify_structure(memlen, itemsize, ndim, shape, strides, offset):
    """Verify that the parameters represent a valid array within
    the bounds of the allocated memory:
        char *mem: start of the physical memory block
        memlen: length of the physical memory block
        offset: (char *) buf - mem
    """
    if offset % itemsize:
        return False
    if offset < 0 or offset+itemsize > memlen:
        return False
    if any(v % itemsize for v in strides):
        return False
```

(continues on next page)

7.6. Buffer Protocol 73

(continued from previous page)

# PIL-style: shape, strides and suboffsets

In addition to the regular items, PIL-style arrays can contain pointers that must be followed in order to get to the next element in a dimension. For example, the regular three-dimensional C-array char v[2][2][3] can also be viewed as an array of 2 pointers to 2 two-dimensional arrays: char (\*v[2])[2][3]. In suboffsets representation, those two pointers can be embedded at the start of buf, pointing to two char x[2][3] arrays that can be located anywhere in memory.

Here is a function that returns a pointer to the element in an N-D array pointed to by an N-dimensional index when there are both non-NULL strides and suboffsets:

# 7.6.4 Buffer-related functions

```
int PyObject_CheckBuffer (PyObject *obj)
```

Return 1 if *obj* supports the buffer interface otherwise 0. When 1 is returned, it doesn't guarantee that  $PyObject\_GetBuffer()$  will succeed. This function always succeeds.

```
int PyObject_GetBuffer (PyObject *exporter, Py_buffer *view, int flags)
```

Send a request to *exporter* to fill in *view* as specified by *flags*. If the exporter cannot provide a buffer of the exact type, it MUST raise PyExc\_BufferError, set view->obj to *NULL* and return -1.

On success, fill in *view*, set view->obj to a new reference to *exporter* and return 0. In the case of chained buffer providers that redirect requests to a single object, view->obj MAY refer to this object instead of *exporter* (See *Buffer Object Structures*).

Successful calls to  $PyObject\_GetBuffer()$  must be paired with calls to  $PyBuffer\_Release()$ , similar to malloc() and free(). Thus, after the consumer is done with the buffer,  $PyBuffer\_Release()$  must be called exactly once.

#### void PyBuffer Release (Py buffer \*view)

Release the buffer *view* and decrement the reference count for view->obj. This function MUST be called when the buffer is no longer being used, otherwise reference leaks may occur.

It is an error to call this function on a buffer that was not obtained via PyObject\_GetBuffer().

#### Py\_ssize\_t PyBuffer\_SizeFromFormat (const char \*)

Return the implied *itemsize* from *format*. This function is not yet implemented.

#### int PyBuffer IsContiguous (Py buffer \*view, char order)

Return 1 if the memory defined by the *view* is C-style (*order* is 'C') or Fortran-style (*order* is 'F') *contiguous* or either one (*order* is 'A'). Return 0 otherwise. This function always succeeds.

# void\* PyBuffer\_GetPointer (Py\_buffer \*view, Py\_ssize\_t \*indices)

Get the memory area pointed to by the *indices* inside the given *view*. *indices* must point to an array of view->ndim indices.

# int PyBuffer\_FromContiguous (*Py\_buffer \*view*, void \*buf, Py\_ssize\_t len, char fort)

Copy contiguous *len* bytes from *buf* to *view*. *fort* can be 'C' or 'F' (for C-style or Fortran-style ordering). 0 is returned on success, -1 on error.

# int PyBuffer\_ToContiguous (void \*buf, Py\_buffer \*src, Py\_ssize\_t len, char order)

Copy *len* bytes from *src* to its contiguous representation in *buf*. *order* can be 'C' or 'F' or 'A' (for C-style or Fortran-style ordering or either one). 0 is returned on success, -1 on error.

This function fails if len != src -> len.

# void **PyBuffer\_FillContiguousStrides** (int *ndims*, Py\_ssize\_t \*shape, Py\_ssize\_t \*strides, int itemsize, char order)

Fill the *strides* array with byte-strides of a *contiguous* (C-style if *order* is 'C' or Fortran-style if *order* is 'F') array of the given shape with the given number of bytes per element.

```
int PyBuffer_FillInfo (Py_buffer *view, PyObject *exporter, void *buf, Py_ssize_t len, int readonly, int flags)
```

Handle buffer requests for an exporter that wants to expose *buf* of size *len* with writability set according to *readonly*. *buf* is interpreted as a sequence of unsigned bytes.

The *flags* argument indicates the request type. This function always fills in *view* as specified by flags, unless *buf* has been designated as read-only and *PyBUF\_WRITABLE* is set in *flags*.

On success, set view->obj to a new reference to *exporter* and return 0. Otherwise, raise PyExc\_BufferError, set view->obj to *NULL* and return -1;

If this function is used as part of a *getbufferproc*, *exporter* MUST be set to the exporting object and *flags* must be passed unmodified. Otherwise, *exporter* MUST be NULL.

# 7.7 Old Buffer Protocol

Deprecated since version 3.0.

These functions were part of the "old buffer protocol" API in Python 2. In Python 3, this protocol doesn't exist anymore but the functions are still exposed to ease porting 2.x code. They act as a compatibility wrapper around the *new buffer protocol*, but they don't give you control over the lifetime of the resources acquired when a buffer is exported.

Therefore, it is recommended that you call  $PyObject\_GetBuffer()$  (or the y\* or w\* format codes with the  $PyArg\_ParseTuple()$  family of functions) to get a buffer view over an object, and  $PyBuffer\_Release()$  when the buffer view can be released.

# int PyObject\_AsCharBuffer (PyObject \*obj, const char \*\*buffer, Py\_ssize\_t \*buffer\_len)

Returns a pointer to a read-only memory location usable as character-based input. The *obj* argument must support the single-segment character buffer interface. On success, returns 0, sets *buffer* to the memory location and *buffer\_len* to the buffer length. Returns -1 and sets a TypeError on error.

# int PyObject\_AsReadBuffer (PyObject \*obj, const void \*\*buffer, Py\_ssize\_t \*buffer\_len)

Returns a pointer to a read-only memory location containing arbitrary data. The *obj* argument must support the single-segment readable buffer interface. On success, returns 0, sets *buffer* to the memory location and *buffer\_len* to the buffer length. Returns -1 and sets a TypeError on error.

# int PyObject\_CheckReadBuffer (PyObject \*o)

Returns 1 if o supports the single-segment readable buffer interface. Otherwise returns 0. This function always succeeds.

Note that this function tries to get and release a buffer, and exceptions which occur while calling corresponding functions will get suppressed. To get error reporting use PyObject\_GetBuffer() instead.

# int PyObject\_AsWriteBuffer (PyObject \*obj, void \*\*buffer, Py\_ssize\_t \*buffer\_len)

Returns a pointer to a writable memory location. The *obj* argument must support the single-segment, character buffer interface. On success, returns 0, sets *buffer* to the memory location and *buffer\_len* to the buffer length. Returns -1 and sets a TypeError on error.

# **CONCRETE OBJECTS LAYER**

The functions in this chapter are specific to certain Python object types. Passing them an object of the wrong type is not a good idea; if you receive an object from a Python program and you are not sure that it has the right type, you must perform a type check first; for example, to check that an object is a dictionary, use <code>PyDict\_Check()</code>. The chapter is structured like the "family tree" of Python object types.

**Warning:** While the functions described in this chapter carefully check the type of the objects which are passed in, many of them do not check for *NULL* being passed instead of a valid object. Allowing *NULL* to be passed in can cause memory access violations and immediate termination of the interpreter.

# 8.1 Fundamental Objects

This section describes Python type objects and the singleton object None.

# 8.1.1 Type Objects

# PyTypeObject

The C structure of the objects used to describe built-in types.

#### PyObject\* PyType\_Type

This is the type object for type objects; it is the same object as type in the Python layer.

# int PyType\_Check (PyObject \*o)

Return true if the object o is a type object, including instances of types derived from the standard type object. Return false in all other cases.

#### int PyType\_CheckExact (PyObject \*o)

Return true if the object o is a type object, but not a subtype of the standard type object. Return false in all other cases.

# unsigned int PyType\_ClearCache()

Clear the internal lookup cache. Return the current version tag.

# unsigned long PyType\_GetFlags (PyTypeObject\* type)

Return the  $tp\_flags$  member of type. This function is primarily meant for use with  $Py\_LIMITED\_API$ ; the individual flag bits are guaranteed to be stable across Python releases, but access to  $tp\_flags$  itself is not part of the limited API.

New in version 3.2.

Changed in version 3.4: The return type is now unsigned long rather than long.

#### void PyType\_Modified (PyTypeObject \*type)

Invalidate the internal lookup cache for the type and all of its subtypes. This function must be called after any manual modification of the attributes or base classes of the type.

### int PyType\_HasFeature (*PyTypeObject* \*o, int *feature*)

Return true if the type object o sets the feature feature. Type features are denoted by single bit flags.

#### int PyType IS GC (PyTypeObject \*o)

Return true if the type object includes support for the cycle detector; this tests the type flag Py TPFLAGS HAVE GC.

# int PyType\_IsSubtype (PyTypeObject \*a, PyTypeObject \*b)

Return true if a is a subtype of b.

This function only checks for actual subtypes, which means that  $\_\_subclasscheck\_\_$  () is not called on b. Call  $PyObject\_IsSubclass()$  to do the same check that issubclass() would do.

# PyObject\* PyType\_GenericAlloc (PyTypeObject \*type, Py\_ssize\_t nitems)

Return value: New reference. Generic handler for the  $tp\_alloc$  slot of a type object. Use Python's default memory allocation mechanism to allocate a new instance and initialize all its contents to NULL.

# PyObject\* PyType\_GenericNew (PyTypeObject \*type, PyObject \*args, PyObject \*kwds)

Return value: New reference. Generic handler for the  $tp\_new$  slot of a type object. Create a new instance using the type's  $tp\_alloc$  slot.

# int PyType\_Ready (PyTypeObject \*type)

Finalize a type object. This should be called on all type objects to finish their initialization. This function is responsible for adding inherited slots from a type's base class. Return 0 on success, or return -1 and sets an exception on error.

# void\* PyType\_GetSlot (PyTypeObject \*type, int slot)

Return the function pointer stored in the given slot. If the result is *NULL*, this indicates that either the slot is *NULL*, or that the function was called with invalid parameters. Callers will typically cast the result pointer into the appropriate function type.

See PyType\_Slot.slot for possible values of the *slot* argument.

An exception is raised if *type* is not a heap type.

New in version 3.4.

### **Creating Heap-Allocated Types**

The following functions and structs are used to create *heap types*.

#### PyObject\* PyType\_FromSpecWithBases (PyType\_Spec \*spec, PyObject \*bases)

Return value: New reference. Creates and returns a heap type object from the spec (Py\_TPFLAGS\_HEAPTYPE).

If bases is a tuple, the created heap type contains all types contained in it as base types.

If bases is NULL, the Py tp base slot is used instead. If that also is NULL, the new type derives from object.

This function calls PyType\_Ready () on the new type.

New in version 3.3.

#### PyObject\* PyType FromSpec (PyType Spec \*spec)

Return value: New reference. Equivalent to PyType\_FromSpecWithBases (spec, NULL).

# PyType\_Spec

Structure defining a type's behavior.

#### const char\* PyType\_Spec.name

Name of the type, used to set PyTypeObject.tp\_name.

### int PyType\_Spec.basicsize

#### int PyType\_Spec.itemsize

Size of the instance in bytes, used to set  $PyTypeObject.tp\_basicsize$  and  $PyTypeObject.tp\_itemsize$ .

#### int PyType\_Spec.flags

Type flags, used to set PyTypeObject.tp\_flags.

If the  $Py\_TPFLAGS\_HEAPTYPE$  flag is not set,  $PyType\_FromSpecWithBases()$  sets it automatically.

# PyType\_Slot \*PyType\_Spec.slots

Array of PyType\_Slot structures. Terminated by the special slot value {0, NULL}.

#### PyType\_Slot

Structure defining optional functionality of a type, containing a slot ID and a value pointer.

#### int PyType Slot.slot

A slot ID.

Slot IDs are named like the field names of the structures PyTypeObject, PyNumberMethods, PySequenceMethods, PyMappingMethods and PyAsyncMethods with an added Py\_prefix. For example, use:

- Py\_tp\_dealloc to set PyTypeObject.tp\_dealloc
- Py nb add to set PyNumberMethods.nb add
- Py\_sq\_length to set PySequenceMethods.sq\_length

The following fields cannot be set using *PyType\_Spec* and *PyType\_Slot*:

- tp\_dict
- tp\_mro
- tp\_cache
- tp\_subclasses
- tp\_weaklist
- tp\_print
- tp\_weaklistoffset
- tp dictoffset
- bf\_getbuffer
- bf\_releasebuffer

Setting  $Py\_tp\_bases$  may be problematic on some platforms. To avoid issues, use the *bases* argument of  $PyType\_FromSpecWithBases$  () instead.

#### void \*PyType\_Slot.pfunc

The desired value of the slot. In most cases, this is a pointer to a function.

May not be NULL.

# 8.1.2 The None Object

Note that the PyTypeObject for None is not directly exposed in the Python/C API. Since None is a singleton, testing for object identity (using == in C) is sufficient. There is no PyNone\_Check () function for the same reason.

# PyObject\* Py\_None

The Python None object, denoting lack of value. This object has no methods. It needs to be treated just like any other object with respect to reference counts.

# Py\_RETURN\_NONE

Properly handle returning Py\_None from within a C function (that is, increment the reference count of None and return it.)

# 8.2 Numeric Objects

# 8.2.1 Integer Objects

All integers are implemented as "long" integer objects of arbitrary size.

On error, most PyLong\_As\* APIs return (return type) -1 which cannot be distinguished from a number. Use PyErr\_Occurred() to disambiguate.

#### PyLongObject

This subtype of PyObject represents a Python integer object.

# PyTypeObject PyLong\_Type

This instance of PyTypeObject represents the Python integer type. This is the same object as int in the Python layer.

#### int PyLong\_Check (*PyObject* \*p)

Return true if its argument is a PyLongObject or a subtype of PyLongObject.

#### int PyLong\_CheckExact (PyObject \*p)

Return true if its argument is a PyLongObject, but not a subtype of PyLongObject.

#### PyObject\* PyLong FromLong (long v)

Return value: New reference. Return a new PyLongObject object from v, or NULL on failure.

The current implementation keeps an array of integer objects for all integers between -5 and 256, when you create an int in that range you actually just get back a reference to the existing object. So it should be possible to change the value of 1. I suspect the behaviour of Python in this case is undefined. :-)

# *PyObject\** **PyLong\_FromUnsignedLong** (unsigned long *v*)

Return value: New reference. Return a new PyLongObject object from a C unsigned long, or NULL on failure.

#### PyObject\* PyLong\_FromSsize\_t (Py\_ssize\_t v)

Return value: New reference. Return a new PyLongObject object from a CPy ssize t, or NULL on failure.

#### PyObject\* PyLong\_FromSize\_t (size\_t v)

Return value: New reference. Return a new PyLongObject object from a C size\_t, or NULL on failure.

# *PyObject\** **PyLong\_FromLongLong** (long long *v*)

Return value: New reference. Return a new PyLongObject object from a Clong long, or NULL on failure.

#### PyObject\* PyLong FromUnsignedLongLong (unsigned long long v)

Return value: New reference. Return a new PyLongObject object from a C unsigned long long, or NULL on failure.

#### *PyObject\** **PyLong FromDouble** (double *v*)

Return value: New reference. Return a new PyLongObject object from the integer part of v, or NULL on failure.

# *PyObject\** **PyLong\_FromString** (const char \*str, char \*\*pend, int base)

Return value: New reference. Return a new PyLongObject based on the string value in str, which is interpreted according to the radix in base. If pend is non-NULL, \*pend will point to the first character in str which follows the representation of the number. If base is 0, str is interpreted using the integers definition; in this case, leading zeros in a non-zero decimal number raises a ValueError. If base is not 0, it must be between 2 and 36, inclusive. Leading spaces and single underscores after a base specifier and between digits are ignored. If there are no digits, ValueError will be raised.

# PyObject\* PyLong\_FromUnicode (Py\_UNICODE \*u, Py\_ssize\_t length, int base)

Return value: New reference. Convert a sequence of Unicode digits to a Python integer value. The Unicode string is first encoded to a byte string using PyUnicode\_EncodeDecimal() and then converted using PyLong\_FromString().

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py\_UNICODE API; please migrate to using PyLong\_FromUnicodeObject().

# PyObject\* PyLong\_FromUnicodeObject (PyObject \*u, int base)

Return value: New reference. Convert a sequence of Unicode digits in the string u to a Python integer value. The Unicode string is first encoded to a byte string using PyUnicode\_EncodeDecimal() and then converted using PyLong\_FromString().

New in version 3.3.

# PyObject\* PyLong\_FromVoidPtr (void \*p)

*Return value: New reference.* Create a Python integer from the pointer p. The pointer value can be retrieved from the resulting value using  $PyLong\ AsVoidPtr()$ .

#### long PyLong\_AsLong (PyObject \*obj)

Return a C long representation of obj. If obj is not an instance of PyLongObject, first call its \_\_index\_\_() or \_\_int\_\_() method (if present) to convert it to a PyLongObject.

Raise OverflowError if the value of *obj* is out of range for a long.

Returns -1 on error. Use PyErr\_Occurred () to disambiguate.

Changed in version 3.8: Use \_\_index\_\_() if available.

Deprecated since version 3.8: Using \_\_int\_\_() is deprecated.

# long PyLong\_AsLongAndOverflow (PyObject \*obj, int \*overflow)

Return a C long representation of obj. If obj is not an instance of PyLongObject, first call its \_\_index\_\_() or \_\_int\_\_() method (if present) to convert it to a PyLongObject.

If the value of *obj* is greater than LONG\_MAX or less than LONG\_MIN, set \**overflow* to 1 or -1, respectively, and return -1; otherwise, set \**overflow* to 0. If any other exception occurs set \**overflow* to 0 and return -1 as usual.

Returns -1 on error. Use PyErr\_Occurred () to disambiguate.

Changed in version 3.8: Use \_\_index\_\_() if available.

Deprecated since version 3.8: Using \_\_int\_\_() is deprecated.

#### long long PyLong\_AsLongLong (PyObject \*obj)

Return a C long long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its \_\_index\_\_() or \_\_int\_\_() method (if present) to convert it to a *PyLongObject*.

Raise OverflowError if the value of obj is out of range for a long.

Returns -1 on error. Use PyErr\_Occurred() to disambiguate.

Changed in version 3.8: Use \_\_index\_\_() if available.

Deprecated since version 3.8: Using \_\_int\_\_() is deprecated.

### long long PyLong\_AsLongLongAndOverflow (PyObject \*obj, int \*overflow)

Return a C long long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its \_\_index\_\_() or \_\_int\_\_() method (if present) to convert it to a *PyLongObject*.

If the value of *obj* is greater than PY\_LLONG\_MAX or less than PY\_LLONG\_MIN, set \**overflow* to 1 or -1, respectively, and return -1; otherwise, set \**overflow* to 0. If any other exception occurs set \**overflow* to 0 and return -1 as usual.

Returns -1 on error. Use PyErr\_Occurred() to disambiguate.

New in version 3.2.

Changed in version 3.8: Use \_\_index\_\_() if available.

Deprecated since version 3.8: Using \_\_int\_\_() is deprecated.

# Py\_ssize\_t PyLong\_AsSsize\_t (PyObject \*pylong)

Return a C Py\_ssize\_t representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of *pylong* is out of range for a Py\_ssize\_t.

Returns -1 on error. Use PyErr\_Occurred() to disambiguate.

# unsigned long PyLong\_AsUnsignedLong (PyObject \*pylong)

Return a C unsigned long representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of pylong is out of range for a unsigned long.

Returns (unsigned long) -1 on error. Use PyErr Occurred() to disambiguate.

#### size\_t PyLong\_AsSize\_t (PyObject \*pylong)

Return a C size\_t representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of *pylong* is out of range for a size\_t.

Returns (size\_t) -1 on error. Use PyErr\_Occurred() to disambiguate.

# unsigned long long PyLong\_AsUnsignedLongLong (PyObject \*pylong)

Return a Cunsigned long long representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of pylong is out of range for an unsigned long long.

Returns (unsigned long long) -1 on error. Use PyErr\_Occurred() to disambiguate.

Changed in version 3.1: A negative *pylong* now raises OverflowError, not TypeError.

# unsigned long PyLong\_AsUnsignedLongMask (PyObject \*obj)

Return a C unsigned long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its \_\_index\_\_() or \_\_int\_\_() method (if present) to convert it to a *PyLongObject*.

If the value of *obj* is out of range for an unsigned long, return the reduction of that value modulo ULONG\_MAX + 1.

Returns (unsigned long) -1 on error. Use PyErr\_Occurred() to disambiguate.

Changed in version 3.8: Use \_\_index\_\_() if available.

Deprecated since version 3.8: Using \_\_int\_\_() is deprecated.

# unsigned long long PyLong\_AsUnsignedLongLongMask (PyObject \*obj)

Return a C unsigned long long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its \_\_index\_\_() or \_\_int\_\_() method (if present) to convert it to a *PyLongObject*.

If the value of obj is out of range for an unsigned long long, return the reduction of that value modulo PY ULLONG MAX + 1.

Returns (unsigned long long) -1 on error. Use PyErr\_Occurred() to disambiguate.

Changed in version 3.8: Use \_\_index\_\_() if available.

Deprecated since version 3.8: Using \_\_int\_\_() is deprecated.

# double PyLong\_AsDouble (PyObject \*pylong)

Return a C double representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of *pylong* is out of range for a double.

Returns -1.0 on error. Use PyErr\_Occurred () to disambiguate.

# void\* PyLong\_AsVoidPtr (PyObject \*pylong)

Convert a Python integer *pylong* to a C void pointer. If *pylong* cannot be converted, an OverflowError will be raised. This is only assured to produce a usable void pointer for values created with *PyLong\_FromVoidPtr()*.

Returns *NULL* on error. Use *PyErr\_Occurred()* to disambiguate.

# 8.2.2 Boolean Objects

Booleans in Python are implemented as a subclass of integers. There are only two booleans, Py\_False and Py\_True. As such, the normal creation and deletion functions don't apply to booleans. The following macros are available, however.

#### int PyBool Check (PyObject \*o)

Return true if o is of type PyBool\_Type.

#### *PyObject\** Py\_False

The Python False object. This object has no methods. It needs to be treated just like any other object with respect to reference counts.

#### PyObject\* Py\_True

The Python True object. This object has no methods. It needs to be treated just like any other object with respect to reference counts.

# Py\_RETURN\_FALSE

Return Py\_False from a function, properly incrementing its reference count.

#### Py RETURN TRUE

Return Py\_True from a function, properly incrementing its reference count.

#### PyObject\* PyBool\_FromLong (long v)

*Return value: New reference.* Return a new reference to Py\_True or Py\_False depending on the truth value of v.

# 8.2.3 Floating Point Objects

#### PyFloatObject

This subtype of PyObject represents a Python floating point object.

# PyTypeObject PyFloat\_Type

This instance of PyTypeObject represents the Python floating point type. This is the same object as float in the Python layer.

#### int PyFloat\_Check (PyObject \*p)

Return true if its argument is a PyFloatObject or a subtype of PyFloatObject.

#### int PyFloat\_CheckExact (PyObject \*p)

Return true if its argument is a PyFloatObject, but not a subtype of PyFloatObject.

### PyObject\* PyFloat\_FromString (PyObject \*str)

Return value: New reference. Create a PyFloatObject object based on the string value in str, or NULL on failure.

#### PyObject\* PyFloat\_FromDouble (double v)

Return value: New reference. Create a PyFloatObject object from v, or NULL on failure.

```
double PyFloat_AsDouble (PyObject *pyfloat)
```

Return a C double representation of the contents of *pyfloat*. If *pyfloat* is not a Python floating point object but has a \_\_float\_\_() method, this method will first be called to convert *pyfloat* into a float. If \_\_float\_\_() is not defined then it falls back to \_\_index\_\_(). This method returns -1.0 upon failure, so one should call PyErr\_Occurred() to check for errors.

Changed in version 3.8: Use \_\_index\_\_() if available.

# double PyFloat\_AS\_DOUBLE (PyObject \*pyfloat)

Return a C double representation of the contents of *pyfloat*, but without error checking.

### PyObject\* PyFloat\_GetInfo (void)

*Return value: New reference.* Return a structseq instance which contains information about the precision, minimum and maximum values of a float. It's a thin wrapper around the header file float.h.

#### double PyFloat\_GetMax()

Return the maximum representable finite float *DBL\_MAX* as C double.

#### double PyFloat\_GetMin()

Return the minimum normalized positive float *DBL\_MIN* as C double.

#### int PyFloat\_ClearFreeList()

Clear the float free list. Return the number of items that could not be freed.

# 8.2.4 Complex Number Objects

Python's complex number objects are implemented as two distinct types when viewed from the C API: one is the Python object exposed to Python programs, and the other is a C structure which represents the actual complex number value. The API provides functions for working with both.

#### **Complex Numbers as C Structures**

Note that the functions which accept these structures as parameters and return them as results do so by value rather than dereferencing them through pointers. This is consistent throughout the API.

### Py\_complex

The C structure which corresponds to the value portion of a Python complex number object. Most of the functions for dealing with complex number objects use structures of this type as input or output values, as appropriate. It is defined as:

```
typedef struct {
   double real;
   double imag;
} Py_complex;
```

# Py\_complex \_Py\_c\_sum (Py\_complex left, Py\_complex right)

Return the sum of two complex numbers, using the C Py\_complex representation.

#### Py\_complex \_Py\_c\_diff (Py\_complex left, Py\_complex right)

Return the difference between two complex numbers, using the C Py\_complex representation.

# Py\_complex \_Py\_c\_neg (Py\_complex complex)

Return the negation of the complex number complex, using the C Py\_complex representation.

# Py\_complex \_Py\_c\_prod (Py\_complex left, Py\_complex right)

Return the product of two complex numbers, using the C Py\_complex representation.

#### Py\_complex \_Py\_c\_quot (Py\_complex dividend, Py\_complex divisor)

Return the quotient of two complex numbers, using the C Py\_complex representation.

If divisor is null, this method returns zero and sets errno to EDOM.

# *Py\_complex* **\_Py\_c\_pow** (*Py\_complex num*, *Py\_complex exp*)

Return the exponentiation of *num* by *exp*, using the C Py\_complex representation.

If num is null and exp is not a positive real number, this method returns zero and sets errno to EDOM.

# **Complex Numbers as Python Objects**

#### PyComplexObject

This subtype of PyObject represents a Python complex number object.

# PyTypeObject PyComplex\_Type

This instance of PyTypeObject represents the Python complex number type. It is the same object as complex in the Python layer.

### int PyComplex\_Check (PyObject \*p)

Return true if its argument is a PyComplexObject or a subtype of PyComplexObject.

### int PyComplex\_CheckExact (PyObject \*p)

Return true if its argument is a PyComplexObject, but not a subtype of PyComplexObject.

# PyObject\* PyComplex\_FromCComplex (Py\_complex v)

Return value: New reference. Create a new Python complex number object from a C Py\_complex value.

#### PyObject\* PyComplex FromDoubles (double real, double imag)

Return value: New reference. Return a new PyComplexObject object from real and imag.

# double PyComplex\_RealAsDouble (PyObject \*op)

Return the real part of op as a C double.

# double PyComplex\_ImagAsDouble (PyObject \*op)

Return the imaginary part of op as a C double.

#### Py\_complex PyComplex\_AsCComplex (PyObject \*op)

Return the Py\_complex value of the complex number op.

If op is not a Python complex number object but has a  $\_complex\_$ () method, this method will first be called to convert op to a Python complex number object. If  $\_complex\_$ () is not defined then it falls back to  $\_float\_$ (). If  $\_float\_$ () is not defined then it falls back to  $\_index\_$ (). Upon failure, this method returns -1.0 as a real value.

Changed in version 3.8: Use \_\_index\_\_() if available.

# 8.3 Sequence Objects

Generic operations on sequence objects were discussed in the previous chapter; this section deals with the specific kinds of sequence objects that are intrinsic to the Python language.

# 8.3.1 Bytes Objects

These functions raise TypeError when expecting a bytes parameter and are called with a non-bytes parameter.

# PyBytesObject

This subtype of PyObject represents a Python bytes object.

# PyTypeObject PyBytes\_Type

This instance of PyTypeObject represents the Python bytes type; it is the same object as bytes in the Python layer.

#### int PyBytes Check (PyObject \*o)

Return true if the object o is a bytes object or an instance of a subtype of the bytes type.

#### int PyBytes\_CheckExact (PyObject \*o)

Return true if the object o is a bytes object, but not an instance of a subtype of the bytes type.

#### *PyObject\** **PyBytes\_FromString** (const char \*v)

*Return value: New reference.* Return a new bytes object with a copy of the string v as value on success, and *NULL* on failure. The parameter v must not be *NULL*; it will not be checked.

# *PyObject\** **PyBytes\_FromStringAndSize** (const char \*v, Py\_ssize\_t *len*)

Return value: New reference. Return a new bytes object with a copy of the string v as value and length len on success, and NULL on failure. If v is NULL, the contents of the bytes object are uninitialized.

#### PyObject\* PyBytes FromFormat (const char \*format, ...)

Return value: New reference. Take a C printf()-style format string and a variable number of arguments, calculate the size of the resulting Python bytes object and return a bytes object with the values formatted into it. The variable arguments must be C types and must correspond exactly to the format characters in the format string. The following format characters are allowed:

Format Characters	Туре	Comment
용용	n/a	The literal % character.
%C	int	A single byte, represented as a C int.
%d	int	Equivalent to printf("%d").
%u	unsigned int	Equivalent to printf("%u").1
%ld	long	Equivalent to printf("%ld").1
%lu	unsigned long	Equivalent to printf("%lu").1
%zd	Py_ssize_t	Equivalent to printf("%zd").1
%zu	size_t	Equivalent to printf("%zu").1
%i	int	Equivalent to printf("%i").1
%X	int	Equivalent to printf("%x").1
%S	const char*	A null-terminated C character array.
%p	const void*	The hex representation of a C pointer. Mostly equivalent to
		printf("%p") except that it is guaranteed to start with the literal
		0x regardless of what the platform's printf yields.

An unrecognized format character causes all the rest of the format string to be copied as-is to the result object, and any extra arguments discarded.

<sup>&</sup>lt;sup>1</sup> For integer specifiers (d, u, ld, lu, zd, zu, i, x): the 0-conversion flag has effect even when a precision is given.

#### PyObject\* PyBytes\_FromFormatV (const char \*format, va\_list vargs)

*Return value: New reference.* Identical to *PyBytes\_FromFormat()* except that it takes exactly two arguments.

# PyObject\* PyBytes\_FromObject (PyObject \*o)

Return value: New reference. Return the bytes representation of object o that implements the buffer protocol.

# Py\_ssize\_t PyBytes\_Size (PyObject \*o)

Return the length of the bytes in bytes object o.

#### Py ssize t PyBytes GET SIZE (PyObject \*o)

Macro form of PyBytes\_Size() but without error checking.

# char\* PyBytes\_AsString (PyObject \*o)

Return a pointer to the contents of o. The pointer refers to the internal buffer of o, which consists of len(o) + 1 bytes. The last byte in the buffer is always null, regardless of whether there are any other null bytes. The data must not be modified in any way, unless the object was just created using PyBytes\_FromStringAndSize(NULL, size). It must not be deallocated. If o is not a bytes object at all,  $PyBytes_AsString()$  returns NULL and raises TypeError.

# char\* PyBytes\_AS\_STRING (PyObject \*string)

Macro form of PyBytes\_AsString() but without error checking.

# int PyBytes\_AsStringAndSize (PyObject \*obj, char \*\*buffer, Py\_ssize\_t \*length)

Return the null-terminated contents of the object obj through the output variables buffer and length.

If *length* is *NULL*, the bytes object may not contain embedded null bytes; if it does, the function returns -1 and a ValueError is raised.

The buffer refers to an internal buffer of *obj*, which includes an additional null byte at the end (not counted in *length*). The data must not be modified in any way, unless the object was just created using PyBytes\_FromStringAndSize(NULL, size). It must not be deallocated. If *obj* is not a bytes object at all, *PyBytes\_AsStringAndSize()* returns -1 and raises TypeError.

Changed in version 3.5: Previously, TypeError was raised when embedded null bytes were encountered in the bytes object.

# void PyBytes\_Concat (PyObject \*\*bytes, PyObject \*newpart)

Create a new bytes object in \*bytes containing the contents of newpart appended to bytes; the caller will own the new reference. The reference to the old value of bytes will be stolen. If the new object cannot be created, the old reference to bytes will still be discarded and the value of \*bytes will be set to NULL; the appropriate exception will be set

# void PyBytes\_ConcatAndDel (PyObject \*\*bytes, PyObject \*newpart)

Create a new bytes object in \*bytes containing the contents of newpart appended to bytes. This version decrements the reference count of newpart.

#### int **PyBytes Resize** (*PyObject* \*\*bytes, Py ssize t newsize)

A way to resize a bytes object even though it is "immutable". Only use this to build up a brand new bytes object; don't use this if the bytes may already be known in other parts of the code. It is an error to call this function if the refcount on the input bytes object is not one. Pass the address of an existing bytes object as an Ivalue (it may be written into), and the new size desired. On success, \*bytes holds the resized bytes object and 0 is returned; the address in \*bytes may differ from its input value. If the reallocation fails, the original bytes object at \*bytes is deallocated, \*bytes is set to NULL, MemoryError is set, and -1 is returned.

# 8.3.2 Byte Array Objects

#### PyByteArrayObject

This subtype of PyObject represents a Python bytearray object.

#### PyTypeObject PyByteArray\_Type

This instance of PyTypeObject represents the Python bytearray type; it is the same object as bytearray in the Python layer.

# Type check macros

# int PyByteArray\_Check (PyObject \*o)

Return true if the object o is a bytearray object or an instance of a subtype of the bytearray type.

#### int PyByteArray\_CheckExact (PyObject \*o)

Return true if the object o is a bytearray object, but not an instance of a subtype of the bytearray type.

#### **Direct API functions**

# PyObject\* PyByteArray\_FromObject (PyObject \*o)

Return value: New reference. Return a new bytearray object from any object, o, that implements the buffer protocol.

# PyObject\* PyByteArray\_FromStringAndSize (const char \*string, Py\_ssize\_t len)

Return value: New reference. Create a new bytearray object from string and its length, len. On failure, NULL is returned.

# PyObject\* PyByteArray\_Concat (PyObject \*a, PyObject \*b)

Return value: New reference. Concat bytearrays a and b and return a new bytearray with the result.

# Py\_ssize\_t PyByteArray\_Size (PyObject \*bytearray)

Return the size of *bytearray* after checking for a *NULL* pointer.

```
char* PyByteArray_AsString (PyObject *bytearray)
```

Return the contents of *bytearray* as a char array after checking for a *NULL* pointer. The returned array always has an extra null byte appended.

```
int PyByteArray_Resize (PyObject *bytearray, Py_ssize_t len)
```

Resize the internal buffer of bytearray to len.

#### **Macros**

These macros trade safety for speed and they don't check pointers.

```
char* PyByteArray_AS_STRING (PyObject *bytearray)
```

Macro version of PyByteArray\_AsString().

```
Py_ssize_t PyByteArray_GET_SIZE (PyObject *bytearray)
```

Macro version of PyByteArray\_Size().

# 8.3.3 Unicode Objects and Codecs

#### **Unicode Objects**

Since the implementation of **PEP 393** in Python 3.3, Unicode objects internally use a variety of representations, in order to allow handling the complete range of Unicode characters while staying memory efficient. There are special cases for strings where all code points are below 128, 256, or 65536; otherwise, code points must be below 1114112 (which is the full Unicode range).

 $Py\_UNICODE*$  and UTF-8 representations are created on demand and cached in the Unicode object. The  $Py\_UNICODE*$  representation is deprecated and inefficient; it should be avoided in performance- or memory-sensitive situations.

Due to the transition between the old APIs and the new APIs, Unicode objects can internally be in two states depending on how they were created:

- "canonical" Unicode objects are all objects created by a non-deprecated Unicode API. They use the most efficient representation allowed by the implementation.
- "legacy" Unicode objects have been created through one of the deprecated APIs (typically PyUnicode\_FromUnicode()) and only bear the Py\_UNICODE\* representation; you will have to call PyUnicode\_READY() on them before calling any other API.

# **Unicode Type**

These are the basic Unicode object types used for the Unicode implementation in Python:

Py\_UCS4

Py\_UCS2

Py\_UCS1

These types are typedefs for unsigned integer types wide enough to contain characters of 32 bits, 16 bits and 8 bits, respectively. When dealing with single Unicode characters, use *Py\_UCS4*.

New in version 3.3.

# Py\_UNICODE

This is a typedef of wchar\_t, which is a 16-bit type or 32-bit type depending on the platform.

Changed in version 3.3: In previous versions, this was a 16-bit type or a 32-bit type depending on whether you selected a "narrow" or "wide" Unicode version of Python at build time.

#### PyASCIIObject

# PyCompactUnicodeObject

# PyUnicodeObject

These subtypes of *PyObject* represent a Python Unicode object. In almost all cases, they shouldn't be used directly, since all API functions that deal with Unicode objects take and return *PyObject* pointers.

New in version 3.3.

# PyTypeObject PyUnicode\_Type

This instance of PyTypeObject represents the Python Unicode type. It is exposed to Python code as str.

The following APIs are really C macros and can be used to do fast checks and to access internal read-only data of Unicode objects:

#### int PyUnicode\_Check (PyObject \*o)

Return true if the object o is a Unicode object or an instance of a Unicode subtype.

# int PyUnicode\_CheckExact (PyObject \*o)

Return true if the object o is a Unicode object, but not an instance of a subtype.

# int PyUnicode\_READY (PyObject \*o)

Ensure the string object o is in the "canonical" representation. This is required before using any of the access macros described below.

Returns 0 on success and -1 with an exception set on failure, which in particular happens if memory allocation fails.

New in version 3.3.

# Py\_ssize\_t PyUnicode\_GET\_LENGTH (PyObject \*o)

Return the length of the Unicode string, in code points. o has to be a Unicode object in the "canonical" representation (not checked).

New in version 3.3.

```
Py_UCS1* PyUnicode_1BYTE_DATA (PyObject *o)
Py_UCS2* PyUnicode_2BYTE_DATA (PyObject *o)
Py_UCS4* PyUnicode_4BYTE_DATA (PyObject *o)
```

Return a pointer to the canonical representation cast to UCS1, UCS2 or UCS4 integer types for direct character access. No checks are performed if the canonical representation has the correct character size; use <code>PyUnicode\_KIND()</code> to select the right macro. Make sure <code>PyUnicode\_READY()</code> has been called before accessing this.

New in version 3.3.

```
PyUnicode_WCHAR_KIND
PyUnicode_1BYTE_KIND
PyUnicode_2BYTE_KIND
PyUnicode_4BYTE_KIND
```

Return values of the  $PyUnicode\_KIND$  () macro.

New in version 3.3.

#### int PyUnicode\_KIND (PyObject \*o)

Return one of the PyUnicode kind constants (see above) that indicate how many bytes per character this Unicode object uses to store its data. o has to be a Unicode object in the "canonical" representation (not checked).

New in version 3.3.

# void\* PyUnicode\_DATA (PyObject \*o)

Return a void pointer to the raw Unicode buffer. o has to be a Unicode object in the "canonical" representation (not checked).

New in version 3.3.

# void PyUnicode\_WRITE (int kind, void \*data, Py\_ssize\_t index, Py\_UCS4 value)

Write into a canonical representation *data* (as obtained with *PyUnicode\_DATA()*). This macro does not do any sanity checks and is intended for usage in loops. The caller should cache the *kind* value and *data* pointer as obtained from other macro calls. *index* is the index in the string (starts at 0) and *value* is the new code point value which should be written to that location.

New in version 3.3.

# Py\_UCS4 PyUnicode\_READ (int kind, void \*data, Py\_ssize\_t index)

Read a code point from a canonical representation *data* (as obtained with PyUnicode\_DATA()). No checks or ready calls are performed.

New in version 3.3.

# Py\_UCS4 PyUnicode\_READ\_CHAR (PyObject \*o, Py\_ssize\_t index)

Read a character from a Unicode object o, which must be in the "canonical" representation. This is less efficient than  $PyUnicode\_READ()$  if you do multiple consecutive reads.

New in version 3.3.

#### PyUnicode\_MAX\_CHAR\_VALUE (PyObject \*o)

Return the maximum code point that is suitable for creating another string based on o, which must be in the "canonical" representation. This is always an approximation but more efficient than iterating over the string.

New in version 3.3.

#### int PyUnicode ClearFreeList()

Clear the free list. Return the total number of freed items.

# Py\_ssize\_t PyUnicode\_GET\_SIZE (PyObject \*o)

Return the size of the deprecated  $PY\_UNICODE$  representation, in code units (this includes surrogate pairs as 2 units). o has to be a Unicode object (not checked).

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Unicode API, please migrate to using PyUnicode\_GET\_LENGTH().

# Py\_ssize\_t PyUnicode\_GET\_DATA\_SIZE (PyObject \*o)

Return the size of the deprecated Py\_UNICODE representation in bytes. o has to be a Unicode object (not checked).

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Unicode API, please migrate to using PyUnicode\_GET\_LENGTH().

# Py\_UNICODE\* PyUnicode\_AS\_UNICODE (PyObject \*o)

```
const char* PyUnicode_AS_DATA (PyObject *o)
```

Return a pointer to a <code>Py\_UNICODE</code> representation of the object. The returned buffer is always terminated with an extra null code point. It may also contain embedded null code points, which would cause the string to be truncated when used in most <code>C</code> functions. The <code>AS\_DATA</code> form casts the pointer to <code>const\_char \*</code>. The <code>o</code> argument has to be a Unicode object (not checked).

Changed in version 3.3: This macro is now inefficient – because in many cases the  $Py\_UNICODE$  representation does not exist and needs to be created – and can fail (return NULL with an exception set). Try to port the code to use the new  $PyUnicode\_nBYTE\_DATA()$  macros or use  $PyUnicode\_WRITE()$  or  $PyUnicode\_READ()$ .

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Unicode API, please migrate to using the PyUnicode nBYTE DATA() family of macros.

# **Unicode Character Properties**

Unicode provides many different character properties. The most often needed ones are available through these macros which are mapped to C functions depending on the Python configuration.

#### int Py UNICODE ISSPACE (Py UNICODE ch)

Return 1 or 0 depending on whether ch is a whitespace character.

#### int Py\_UNICODE\_ISLOWER (Py\_UNICODE ch)

Return 1 or 0 depending on whether ch is a lowercase character.

# int Py\_UNICODE\_ISUPPER (Py\_UNICODE ch)

Return 1 or 0 depending on whether ch is an uppercase character.

# int Py\_UNICODE\_ISTITLE (Py\_UNICODE ch)

Return 1 or 0 depending on whether ch is a titlecase character.

# int Py\_UNICODE\_ISLINEBREAK (Py\_UNICODE ch)

Return 1 or 0 depending on whether ch is a linebreak character.

# int Py\_UNICODE\_ISDECIMAL (Py\_UNICODE ch)

Return 1 or 0 depending on whether ch is a decimal character.

#### int Py UNICODE ISDIGIT (Py UNICODE ch)

Return 1 or 0 depending on whether ch is a digit character.

# int Py\_UNICODE\_ISNUMERIC (Py\_UNICODE ch)

Return 1 or 0 depending on whether ch is a numeric character.

# int Py\_UNICODE\_ISALPHA (Py\_UNICODE ch)

Return 1 or 0 depending on whether ch is an alphabetic character.

#### int Py UNICODE ISALNUM (Py UNICODE ch)

Return 1 or 0 depending on whether *ch* is an alphanumeric character.

# int Py\_UNICODE\_ISPRINTABLE (Py\_UNICODE ch)

Return 1 or 0 depending on whether ch is a printable character. Nonprintable characters are those characters defined in the Unicode character database as "Other" or "Separator", excepting the ASCII space (0x20) which is considered printable. (Note that printable characters in this context are those which should not be escaped when repr() is invoked on a string. It has no bearing on the handling of strings written to sys.stdout or sys.stderr.)

These APIs can be used for fast direct character conversions:

# Py\_UNICODE Py\_UNICODE\_TOLOWER (Py\_UNICODE ch)

Return the character *ch* converted to lower case.

Deprecated since version 3.3: This function uses simple case mappings.

# Py\_UNICODE Py\_UNICODE\_TOUPPER (Py\_UNICODE ch)

Return the character *ch* converted to upper case.

Deprecated since version 3.3: This function uses simple case mappings.

#### Py\_UNICODE Py\_UNICODE\_TOTITLE (Py\_UNICODE ch)

Return the character *ch* converted to title case.

Deprecated since version 3.3: This function uses simple case mappings.

# int Py\_UNICODE\_TODECIMAL (Py\_UNICODE ch)

Return the character ch converted to a decimal positive integer. Return -1 if this is not possible. This macro does not raise exceptions.

# int Py\_UNICODE\_TODIGIT (Py\_UNICODE ch)

Return the character ch converted to a single digit integer. Return -1 if this is not possible. This macro does not raise exceptions.

# double Py\_UNICODE\_TONUMERIC (Py\_UNICODE ch)

Return the character ch converted to a double. Return -1.0 if this is not possible. This macro does not raise exceptions.

These APIs can be used to work with surrogates:

# Py\_UNICODE\_IS\_SURROGATE (ch)

Check if ch is a surrogate (0xD800 <= ch <= 0xDFFF).

# $\textbf{Py\_UNICODE\_IS\_HIGH\_SURROGATE}\ (ch)$

Check if ch is a high surrogate (0xD800 <= ch <= 0xDBFF).

#### Py UNICODE IS LOW SURROGATE (ch)

Check if ch is a low surrogate (0xDC00 <= ch <= 0xDFFF).

# Py\_UNICODE\_JOIN\_SURROGATES (high, low)

Join two surrogate characters and return a single Py\_UCS4 value. *high* and *low* are respectively the leading and trailing surrogates in a surrogate pair.

# **Creating and accessing Unicode strings**

To create Unicode objects and access their basic sequence properties, use these APIs:

# PyObject\* PyUnicode\_New (Py\_ssize\_t size, Py\_UCS4 maxchar)

Return value: New reference. Create a new Unicode object. maxchar should be the true maximum code point to

be placed in the string. As an approximation, it can be rounded up to the nearest value in the sequence 127, 255, 65535, 1114111.

This is the recommended way to allocate a new Unicode object. Objects created using this function are not resizable.

New in version 3.3.

#### PyObject\* PyUnicode\_FromKindAndData (int kind, const void \*buffer, Py\_ssize\_t size)

Return value: New reference. Create a new Unicode object with the given kind (possible values are PyUnicode\_1BYTE\_KIND etc., as returned by PyUnicode\_KIND()). The buffer must point to an array of size units of 1, 2 or 4 bytes per character, as given by the kind.

New in version 3.3.

# *PyObject\** **PyUnicode\_FromStringAndSize** (const char \*u, Py\_ssize\_t size)

Return value: New reference. Create a Unicode object from the char buffer u. The bytes will be interpreted as being UTF-8 encoded. The buffer is copied into the new object. If the buffer is not NULL, the return value might be a shared object, i.e. modification of the data is not allowed.

If u is NULL, this function behaves like  $PyUnicode\_FromUnicode$  () with the buffer set to NULL. This usage is deprecated in favor of  $PyUnicode\_New$  ().

# PyObject \*PyUnicode\_FromString (const char \*u)

Return value: New reference. Create a Unicode object from a UTF-8 encoded null-terminated char buffer u.

#### PyObject\* PyUnicode\_FromFormat (const char \*format, ...)

Return value: New reference. Take a C printf()-style format string and a variable number of arguments, calculate the size of the resulting Python Unicode string and return a string with the values formatted into it. The variable arguments must be C types and must correspond exactly to the format characters in the format ASCII-encoded string. The following format characters are allowed:

Format Characters	Туре	Comment
양양	n/a	The literal % character.
%C	int	A single character, represented as a C int.
%d	int	Equivalent to printf("%d").
%u	unsigned int	Equivalent to printf("%u").1
%ld	long	Equivalent to printf("%ld").1
%li	long	Equivalent to printf ("%li").1
%lu	unsigned long	Equivalent to printf ("%lu").1
%lld	long long	Equivalent to printf ("%lld").
%lli	long long	Equivalent to printf("%lli").1
%llu	unsigned long long	Equivalent to printf ("%llu").
%zd	Py_ssize_t	Equivalent to printf("%zd").1
%zi	Py_ssize_t	Equivalent to printf("%zi").1
%zu	size_t	Equivalent to printf ("%zu").1
%i	int	Equivalent to printf("%i").1
%X	int	Equivalent to printf("%x").1
%S	const char*	A null-terminated C character array.
%p	const void*	The hex representation of a C pointer. Mostly equivalent to
		printf("%p") except that it is guaranteed to start with
		the literal 0x regardless of what the platform's printf
		yields.
%A	PyObject*	The result of calling ascii().
%U	PyObject*	A Unicode object.
%V	PyObject*, const char*	A Unicode object (which may be <i>NULL</i> ) and a
		null-terminated C character array as a second parameter
		(which will be used, if the first parameter is <i>NULL</i> ).
%S	PyObject*	The result of calling PyObject_Str().
%R	PyObject*	The result of calling PyObject_Repr().

An unrecognized format character causes all the rest of the format string to be copied as-is to the result string, and any extra arguments discarded.

Note: The width formatter unit is number of characters rather than bytes. The precision formatter unit is number of bytes for "%s" and "%V" (if the PyObject\* argument is NULL), and a number of characters for "%A", "%U", "%S", "%R" and "%V" (if the PyObject\* argument is not NULL).

Changed in version 3.2: Support for "%lld" and "%llu" added.

Changed in version 3.3: Support for "%li", "%lli" and "%zi" added.

Changed in version 3.4: Support width and precision formatter for "%s", "%A", "%U", "%V", "%S", "%R" added.

# PyObject\* PyUnicode\_FromFormatV (const char \*format, va\_list vargs)

Return value: New reference. Identical to PyUnicode\_FromFormat () except that it takes exactly two arguments.

PyObject\* PyUnicode\_FromEncodedObject (PyObject \*obj, const char \*encoding, const char \*errors)

Return value: New reference. Decode an encoded object obj to a Unicode object.

bytes, bytearray and other *bytes-like objects* are decoded according to the given *encoding* and using the error handling defined by *errors*. Both can be *NULL* to have the interface use the default values (see *Built-in Codecs* for

<sup>&</sup>lt;sup>1</sup> For integer specifiers (d, u, ld, li, lu, lld, lli, llu, zd, zi, zu, i, x): the 0-conversion flag has effect even when a precision is given.

details).

All other objects, including Unicode objects, cause a TypeError to be set.

The API returns NULL if there was an error. The caller is responsible for decref'ing the returned objects.

# Py\_ssize\_t PyUnicode\_GetLength (PyObject \*unicode)

Return the length of the Unicode object, in code points.

New in version 3.3.

# Py\_ssize\_t PyUnicode\_CopyCharacters (*PyObject* \*to, Py\_ssize\_t to\_start, PyObject \*from, Py\_ssize\_t from\_start, Py\_ssize\_t how\_many)

Copy characters from one Unicode object into another. This function performs character conversion when necessary and falls back to memcpy () if possible. Returns -1 and sets an exception on error, otherwise returns the number of copied characters.

New in version 3.3.

# Py\_ssize\_t PyUnicode\_Fill (*PyObject \*unicode*, Py\_ssize\_t start, Py\_ssize\_t length, Py\_UCS4 fill\_char) Fill a string with a character: write fill\_char into unicode [start:start+length].

Fail if fill\_char is bigger than the string maximum character, or if the string has more than 1 reference.

Return the number of written character, or return -1 and raise an exception on error.

New in version 3.3.

# int PyUnicode\_WriteChar (PyObject \*unicode, Py\_ssize\_t index, Py\_UCS4 character)

Write a character to a string. The string must have been created through <code>PyUnicode\_New()</code>. Since Unicode strings are supposed to be immutable, the string must not be shared, or have been hashed yet.

This function checks that *unicode* is a Unicode object, that the index is not out of bounds, and that the object can be modified safely (i.e. that it its reference count is one).

New in version 3.3.

# Py\_UCS4 PyUnicode\_ReadChar (PyObject \*unicode, Py\_ssize\_t index)

Read a character from a string. This function checks that *unicode* is a Unicode object and the index is not out of bounds, in contrast to the macro version <code>PyUnicode\_READ\_CHAR()</code>.

New in version 3.3.

# PyObject\* PyUnicode\_Substring (PyObject \*str, Py\_ssize\_t start, Py\_ssize\_t end)

*Return value: New reference.* Return a substring of *str*, from character index *start* (included) to character index *end* (excluded). Negative indices are not supported.

New in version 3.3.

# Py\_UCS4\* PyUnicode\_AsuCS4 (PyObject \*u, Py\_UCS4 \*buffer, Py\_ssize\_t buflen, int copy\_null)

Copy the string u into a UCS4 buffer, including a null character, if  $copy\_null$  is set. Returns NULL and sets an exception on error (in particular, a SystemError if buflen is smaller than the length of u). buffer is returned on success.

New in version 3.3.

# Py\_UCS4\* PyUnicode\_AsUCS4Copy (PyObject \*u)

Copy the string u into a new UCS4 buffer that is allocated using  $PyMem\_Malloc()$ . If this fails, NULL is returned with a MemoryError set. The returned buffer always has an extra null code point appended.

New in version 3.3.

# Deprecated Py\_UNICODE APIs

Deprecated since version 3.3, will be removed in version 4.0.

These API functions are deprecated with the implementation of **PEP 393**. Extension modules can continue using them, as they will not be removed in Python 3.x, but need to be aware that their use can now cause performance and memory hits

#### PyObject\* PyUnicode FromUnicode (const Py UNICODE \*u, Py ssize t size)

Return value: New reference. Create a Unicode object from the Py\_UNICODE buffer u of the given size. u may be NULL which causes the contents to be undefined. It is the user's responsibility to fill in the needed data. The buffer is copied into the new object.

If the buffer is not NULL, the return value might be a shared object. Therefore, modification of the resulting Unicode object is only allowed when u is NULL.

If the buffer is *NULL*, *PyUnicode\_READY()* must be called once the string content has been filled before using any of the access macros such as *PyUnicode\_KIND()*.

Please migrate to using PyUnicode\_FromKindAndData(), PyUnicode\_FromWideChar() or PyUnicode\_New().

#### Py\_UNICODE\* PyUnicode\_AsUnicode (PyObject \*unicode)

Return a read-only pointer to the Unicode object's internal  $Py\_UNICODE$  buffer, or NULL on error. This will create the  $Py\_UNICODE*$  representation of the object if it is not yet available. The buffer is always terminated with an extra null code point. Note that the resulting  $Py\_UNICODE$  string may also contain embedded null code points, which would cause the string to be truncated when used in most C functions.

Please migrate to using PyUnicode\_AsUCS4(), PyUnicode\_AsWideChar(), PyUnicode\_ReadChar() or similar new APIs.

#### PyObject\* PyUnicode\_TransformDecimalToASCII (Py\_UNICODE \*s, Py\_ssize\_t size)

Return value: New reference. Create a Unicode object by replacing all decimal digits in Py\_UNICODE buffer of the given size by ASCII digits 0–9 according to their decimal value. Return NULL if an exception occurs.

# Py\_UNICODE\* PyUnicode\_AsUnicodeAndSize (PyObject \*unicode, Py\_ssize\_t \*size)

Like  $PyUnicode\_AsUnicode$  (), but also saves the  $Py\_UNICODE$  () array length (excluding the extra null terminator) in *size*. Note that the resulting  $Py\_UNICODE*$  string may contain embedded null code points, which would cause the string to be truncated when used in most C functions.

New in version 3.3.

#### Py\_UNICODE\* PyUnicode\_AsUnicodeCopy (PyObject \*unicode)

Create a copy of a Unicode string ending with a null code point. Return NULL and raise a MemoryError exception on memory allocation failure, otherwise return a new allocated buffer (use  $PyMem\_Free$  () to free the buffer). Note that the resulting  $Py\_UNICODE*$  string may contain embedded null code points, which would cause the string to be truncated when used in most C functions.

New in version 3.2.

Please migrate to using PyUnicode\_AsUCS4Copy() or similar new APIs.

# Py\_ssize\_t PyUnicode\_GetSize (PyObject \*unicode)

Return the size of the deprecated  $PY\_UNICODE$  representation, in code units (this includes surrogate pairs as 2 units).

Please migrate to using PyUnicode\_GetLength().

# PyObject\* PyUnicode\_FromObject (PyObject \*obj)

*Return value: New reference.* Copy an instance of a Unicode subtype to a new true Unicode object if necessary. If *obj* is already a true Unicode object (not a subtype), return the reference with incremented refcount.

Objects other than Unicode or its subtypes will cause a TypeError.

# **Locale Encoding**

The current locale encoding can be used to decode text from the operating system.

# PyObject\* PyUnicode\_DecodeLocaleAndSize (const char \*str, Py\_ssize\_t len, const char \*errors)

Return value: New reference. Decode a string from UTF-8 on Android and VxWorks, or from the current locale encoding on other platforms. The supported error handlers are "strict" and "surrogateescape" (PEP 383). The decoder uses "strict" error handler if errors is NULL. str must end with a null character but cannot contain embedded null characters.

Use <code>PyUnicode\_DecodeFSDefaultAndSize()</code> to decode a string from <code>Py\_FileSystemDefaultEncoding()</code> the locale encoding read at Python startup).

This function ignores the Python UTF-8 mode.

#### See also:

The Py\_DecodeLocale() function.

New in version 3.3.

Changed in version 3.7: The function now also uses the current locale encoding for the surrogateescape error handler, except on Android. Previously, <code>Py\_DecodeLocale()</code> was used for the surrogateescape, and the current locale encoding was used for strict.

#### PyObject\* PyUnicode\_DecodeLocale (const char \*str, const char \*errors)

Return value: New reference. Similar to PyUnicode\_DecodeLocaleAndSize(), but compute the string length using strlen().

New in version 3.3.

#### PyObject\* PyUnicode\_EncodeLocale (PyObject \*unicode, const char \*errors)

Return value: New reference. Encode a Unicode object to UTF-8 on Android and VxWorks, or to the current locale encoding on other platforms. The supported error handlers are "strict" and "surrogateescape" (PEP 383). The encoder uses "strict" error handler if errors is NULL. Return a bytes object. unicode cannot contain embedded null characters.

Use PyUnicode\_EncodeFSDefault () to encode a string to Py\_FileSystemDefaultEncoding (the locale encoding read at Python startup).

This function ignores the Python UTF-8 mode.

#### See also:

The Py\_EncodeLocale() function.

New in version 3.3.

Changed in version 3.7: The function now also uses the current locale encoding for the surrogateescape error handler, except on Android. Previously, <code>Py\_EncodeLocale()</code> was used for the surrogateescape, and the current locale encoding was used for strict.

#### File System Encoding

To encode and decode file names and other environment strings, Py\_FileSystemDefaultEncoding should be used as the encoding, and Py\_FileSystemDefaultEncodeErrors should be used as the error handler (PEP 383 and PEP 529). To encode file names to bytes during argument parsing, the "O&" converter should be used, passing PyUnicode\_FSConverter() as the conversion function:

#### int PyUnicode\_FSConverter (PyObject\* obj, void\* result)

ParseTuple converter: encode str objects — obtained directly or through the os.PathLike interface — to bytes using <code>PyUnicode\_EncodeFSDefault()</code>; bytes objects are output as-is. result must be a <code>PyBytesObject\*</code> which must be released when it is no longer used.

New in version 3.1.

Changed in version 3.6: Accepts a path-like object.

To decode file names to str during argument parsing, the "O&" converter should be used, passing  $PyUnicode\_FSDecoder()$  as the conversion function:

# int PyUnicode\_FSDecoder (PyObject\* obj, void\* result)

ParseTuple converter: decode bytes objects — obtained either directly or indirectly through the os.PathLike interface — to str using PyUnicode\_DecodeFSDefaultAndSize(); str objects are output as-is. result must be a PyUnicodeObject\* which must be released when it is no longer used.

New in version 3.2.

Changed in version 3.6: Accepts a path-like object.

#### PyObject\* PyUnicode\_DecodeFSDefaultAndSize (const char \*s, Py\_ssize\_t size)

*Return value: New reference.* Decode a string using Py\_FileSystemDefaultEncoding and the Py FileSystemDefaultEncodeErrors error handler.

If Py\_FileSystemDefaultEncoding is not set, fall back to the locale encoding.

Py\_FileSystemDefaultEncoding is initialized at startup from the locale encoding and cannot be modified later. If you need to decode a string from the current locale encoding, use PyUnicode DecodeLocaleAndSize().

#### See also:

The Py\_DecodeLocale() function.

 $Changed \ in \ version \ 3.6: \ Use \ \verb"Py_FileSystemDefaultEncodeErrors" \ error \ handler.$ 

#### PyObject\* PyUnicode\_DecodeFSDefault (const char \*s)

*Return value: New reference.* Decode a null-terminated string using Py\_FileSystemDefaultEncoding and the Py\_FileSystemDefaultEncodeErrors error handler.

If Py\_FileSystemDefaultEncoding is not set, fall back to the locale encoding.

Use PyUnicode\_DecodeFSDefaultAndSize() if you know the string length.

Changed in version 3.6: Use Py\_FileSystemDefaultEncodeErrors error handler.

# PyObject\* PyUnicode\_EncodeFSDefault (PyObject \*unicode)

Return value: New reference. Encode a Unicode object to Py\_FileSystemDefaultEncoding with the Py\_FileSystemDefaultEncodeErrors error handler, and return bytes. Note that the resulting bytes object may contain null bytes.

If Py\_FileSystemDefaultEncoding is not set, fall back to the locale encoding.

Py\_FileSystemDefaultEncoding is initialized at startup from the locale encoding and cannot be modified later. If you need to encode a string to the current locale encoding, use PyUnicode\_EncodeLocale().

### See also:

The Py\_EncodeLocale() function.

New in version 3.2.

Changed in version 3.6: Use Py FileSystemDefaultEncodeErrors error handler.

# wchar\_t Support

wchar\_t support for platforms which support it:

# PyObject\* PyUnicode\_FromWideChar (const wchar\_t \*w, Py\_ssize\_t size)

Return value: New reference. Create a Unicode object from the wchar\_t buffer w of the given size. Passing -1 as the size indicates that the function must itself compute the length, using wcslen. Return NULL on failure.

#### Py ssize t PyUnicode AsWideChar (PyObject \*unicode, wchar t \*w, Py ssize t size)

Copy the Unicode object contents into the wchar\_t buffer w. At most size wchar\_t characters are copied (excluding a possibly trailing null termination character). Return the number of wchar\_t characters copied or -1 in case of an error. Note that the resulting wchar\_t\* string may or may not be null-terminated. It is the responsibility of the caller to make sure that the wchar\_t\* string is null-terminated in case this is required by the application. Also, note that the wchar\_t\* string might contain null characters, which would cause the string to be truncated when used with most C functions.

# wchar\_t\* PyUnicode\_AsWideCharString (PyObject \*unicode, Py\_ssize\_t \*size)

Convert the Unicode object to a wide character string. The output string always ends with a null character. If *size* is not *NULL*, write the number of wide characters (excluding the trailing null termination character) into \*size. Note that the resulting wchar\_t string might contain null characters, which would cause the string to be truncated when used with most C functions. If *size* is *NULL* and the wchar\_t \* string contains null characters a ValueError is raised.

Returns a buffer allocated by PyMem\_Alloc() (use PyMem\_Free() to free it) on success. On error, returns *NULL* and \*size is undefined. Raises a MemoryError if memory allocation is failed.

New in version 3.2.

Changed in version 3.7: Raises a ValueError if size is NULL and the wchar t\* string contains null characters.

# **Built-in Codecs**

Python provides a set of built-in codecs which are written in C for speed. All of these codecs are directly usable via the following functions.

Many of the following APIs take two arguments encoding and errors, and they have the same semantics as the ones of the built-in str() string object constructor.

Setting encoding to *NULL* causes the default encoding to be used which is ASCII. The file system calls should use <code>PyUnicode\_FSConverter()</code> for encoding file names. This uses the variable <code>Py\_FileSystemDefaultEncoding</code> internally. This variable should be treated as read-only: on some systems, it will be a pointer to a static string, on others, it will change at run-time (such as when the application invokes setlocale).

Error handling is set by errors which may also be set to *NULL* meaning to use the default handling defined for the codec. Default error handling for all built-in codecs is "strict" (ValueError is raised).

The codecs all use a similar interface. Only deviation from the following generic ones are documented for simplicity.

#### **Generic Codecs**

These are the generic codec APIs:

PyObject\* PyUnicode\_Decode (const char \*s, Py\_ssize\_t size, const char \*encoding, const char \*errors)

Return value: New reference. Create a Unicode object by decoding size bytes of the encoded string s. encoding and errors have the same meaning as the parameters of the same name in the str() built-in function. The codec to be used is looked up using the Python codec registry. Return NULL if an exception was raised by the codec.

- PyObject\* PyUnicode\_AsEncodedString (PyObject \*unicode, const char \*encoding, const char \*errors)

  Return value: New reference. Encode a Unicode object and return the result as Python bytes object. encoding and errors have the same meaning as the parameters of the same name in the Unicode encode () method. The codec to be used is looked up using the Python codec registry. Return NULL if an exception was raised by the codec.
- *PyObject\** **PyUnicode\_Encode** (const *Py\_UNICODE \*s*, Py\_ssize\_t *size*, const char \**encoding*, const char \**errors*)

Return value: New reference. Encode the  $Py\_UNICODE$  buffer s of the given size and return a Python bytes object. encoding and errors have the same meaning as the parameters of the same name in the Unicode encode () method. The codec to be used is looked up using the Python codec registry. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py\_UNICODE API; please migrate to using PyUnicode\_AsEncodedString().

#### **UTF-8 Codecs**

These are the UTF-8 codec APIs:

PyObject\* PyUnicode\_DecodeUTF8 (const char \*s, Py\_ssize\_t size, const char \*errors)

*Return value: New reference.* Create a Unicode object by decoding *size* bytes of the UTF-8 encoded string *s*. Return *NULL* if an exception was raised by the codec.

PyObject\* PyUnicode\_DecodeUTF8Stateful (const char \*s, Py\_ssize\_t size, const char \*errors, Py ssize t \*consumed)

Return value: New reference. If consumed is NULL, behave like PyUnicode\_DecodeUTF8(). If consumed is not NULL, trailing incomplete UTF-8 byte sequences will not be treated as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in consumed.

PyObject\* PyUnicode\_AsUTF8String (PyObject \*unicode)

*Return value: New reference.* Encode a Unicode object using UTF-8 and return the result as Python bytes object. Error handling is "strict". Return *NULL* if an exception was raised by the codec.

const char\* PyUnicode\_AsUTF8AndSize (PyObject \*unicode, Py\_ssize\_t \*size)

Return a pointer to the UTF-8 encoding of the Unicode object, and store the size of the encoded representation (in bytes) in *size*. The *size* argument can be *NULL*; in this case no size will be stored. The returned buffer always has an extra null byte appended (not included in *size*), regardless of whether there are any other null code points.

In the case of an error, NULL is returned with an exception set and no size is stored.

This caches the UTF-8 representation of the string in the Unicode object, and subsequent calls will return a pointer to the same buffer. The caller is not responsible for deallocating the buffer.

New in version 3.3.

Changed in version 3.7: The return type is now const char \* rather of char \*.

const char\* PyUnicode\_AsUTF8 (PyObject \*unicode)

As PyUnicode\_AsUTF8AndSize(), but does not store the size.

New in version 3.3.

Changed in version 3.7: The return type is now const char \* rather of char \*.

PyObject\* PyUnicode\_EncodeUTF8 (const Py\_UNICODE \*s, Py\_ssize\_t size, const char \*errors)

*Return value: New reference.* Encode the *Py\_UNICODE* buffer *s* of the given *size* using UTF-8 and return a Python bytes object. Return *NULL* if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py\_UNICODE API; please migrate to using PyUnicode\_AsUTF8String(), PyUnicode\_AsUTF8AndSize() or PyUnicode\_AsEncodedString().

#### **UTF-32 Codecs**

These are the UTF-32 codec APIs:

PyObject\* PyUnicode DecodeUTF32 (const char \*s, Py\_ssize\_t size, const char \*errors, int \*byteorder)

*Return value: New reference.* Decode *size* bytes from a UTF-32 encoded buffer string and return the corresponding Unicode object. *errors* (if non-*NULL*) defines the error handling. It defaults to "strict".

If byteorder is non-NULL, the decoder starts decoding using the given byte order:

```
*byteorder == -1: little endian

*byteorder == 0: native order

*byteorder == 1: big endian
```

If \*byteorder is zero, and the first four bytes of the input data are a byte order mark (BOM), the decoder switches to this byte order and the BOM is not copied into the resulting Unicode string. If \*byteorder is -1 or 1, any byte order mark is copied to the output.

After completion, \*byteorder is set to the current byte order at the end of input data.

If byteorder is NULL, the codec starts in native order mode.

Return *NULL* if an exception was raised by the codec.

PyObject\* PyUnicode\_DecodeUTF32Stateful (const char \*s, Py\_ssize\_t size, const char \*errors, int \*by-teorder, Py\_ssize\_t \*consumed)

Return value: New reference. If consumed is NULL, behave like PyUnicode\_DecodeUTF32(). If consumed is not NULL, PyUnicode\_DecodeUTF32Stateful() will not treat trailing incomplete UTF-32 byte sequences (such as a number of bytes not divisible by four) as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in consumed.

# PyObject\* PyUnicode\_AsUTF32String (PyObject \*unicode)

*Return value: New reference.* Return a Python byte string using the UTF-32 encoding in native byte order. The string always starts with a BOM mark. Error handling is "strict". Return *NULL* if an exception was raised by the codec.

PyObject\* PyUnicode\_EncodeUTF32 (const Py\_UNICODE \*s, Py\_ssize\_t size, const char \*errors, int byte-order)

*Return value: New reference.* Return a Python bytes object holding the UTF-32 encoded value of the Unicode data in *s.* Output is written according to the following byte order:

```
byteorder == -1: little endian
byteorder == 0: native byte order (writes a BOM mark)
byteorder == 1: big endian
```

If byteorder is 0, the output string will always start with the Unicode BOM mark (U+FEFF). In the other two modes, no BOM mark is prepended.

If Py\_UNICODE\_WIDE is not defined, surrogate pairs will be output as a single code point.

Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py\_UNICODE API; please migrate to using PyUnicode\_AsUTF32String() or PyUnicode\_AsEncodedString().

# **UTF-16 Codecs**

These are the UTF-16 codec APIs:

PyObject\* PyUnicode\_DecodeUTF16 (const char \*s, Py\_ssize\_t size, const char \*errors, int \*byteorder)

*Return value: New reference.* Decode *size* bytes from a UTF-16 encoded buffer string and return the corresponding Unicode object. *errors* (if non-*NULL*) defines the error handling. It defaults to "strict".

If byteorder is non-NULL, the decoder starts decoding using the given byte order:

```
*byteorder == -1: little endian

*byteorder == 0: native order

*byteorder == 1: big endian
```

If \*byteorder is zero, and the first two bytes of the input data are a byte order mark (BOM), the decoder switches to this byte order and the BOM is not copied into the resulting Unicode string. If \*byteorder is -1 or 1, any byte order mark is copied to the output (where it will result in either a \ufeff or a \ufeff character).

After completion, \*byteorder is set to the current byte order at the end of input data.

If byteorder is NULL, the codec starts in native order mode.

Return NULL if an exception was raised by the codec.

```
PyObject* PyUnicode_DecodeUTF16Stateful (const char *s, Py_ssize_t size, const char *errors, int *by-teorder, Py_ssize_t *consumed)
```

Return value: New reference. If consumed is NULL, behave like PyUnicode\_DecodeUTF16(). If consumed is not NULL, PyUnicode\_DecodeUTF16Stateful() will not treat trailing incomplete UTF-16 byte sequences (such as an odd number of bytes or a split surrogate pair) as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in consumed.

```
PyObject* PyUnicode_AsUTF16String (PyObject *unicode)
```

*Return value: New reference.* Return a Python byte string using the UTF-16 encoding in native byte order. The string always starts with a BOM mark. Error handling is "strict". Return *NULL* if an exception was raised by the codec.

```
PyObject* PyUnicode_EncodeUTF16 (const Py_UNICODE *s, Py_ssize_t size, const char *errors, int byte-order)
```

*Return value: New reference.* Return a Python bytes object holding the UTF-16 encoded value of the Unicode data in *s.* Output is written according to the following byte order:

```
byteorder == -1: little endian
byteorder == 0: native byte order (writes a BOM mark)
byteorder == 1: big endian
```

If byteorder is 0, the output string will always start with the Unicode BOM mark (U+FEFF). In the other two modes, no BOM mark is prepended.

If  $Py\_UNICODE\_WIDE$  is defined, a single  $Py\_UNICODE$  value may get represented as a surrogate pair. If it is not defined, each  $Py\_UNICODE$  values is interpreted as a UCS-2 character.

Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py\_UNICODE API; please migrate to using PyUnicode\_AsUTF16String() or PyUnicode\_AsEncodedString().

# **UTF-7 Codecs**

These are the UTF-7 codec APIs:

```
PyObject* PyUnicode_DecodeUTF7 (const char *s, Py_ssize_t size, const char *errors)
```

*Return value: New reference.* Create a Unicode object by decoding *size* bytes of the UTF-7 encoded string *s*. Return *NULL* if an exception was raised by the codec.

PyObject\* PyUnicode\_DecodeUTF7Stateful (const char \*s, Py\_ssize\_t size, const char \*errors, Py ssize t \*consumed)

Return value: New reference. If consumed is NULL, behave like PyUnicode\_DecodeUTF7(). If consumed is not NULL, trailing incomplete UTF-7 base-64 sections will not be treated as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in consumed.

PyObject\* PyUnicode\_EncodeUTF7 (const Py\_UNICODE \*s, Py\_ssize\_t size, int base64SetO, int base64WhiteSpace, const char \*errors)

*Return value: New reference.* Encode the *Py\_UNICODE* buffer of the given size using UTF-7 and return a Python bytes object. Return *NULL* if an exception was raised by the codec.

If *base64SetO* is nonzero, "Set O" (punctuation that has no otherwise special meaning) will be encoded in base-64. If *base64WhiteSpace* is nonzero, whitespace will be encoded in base-64. Both are set to zero for the Python "utf-7" codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py\_UNICODE API; please migrate to using PyUnicode\_AsEncodedString().

#### **Unicode-Escape Codecs**

These are the "Unicode Escape" codec APIs:

- PyObject\* PyUnicode\_DecodeUnicodeEscape (const char \*s, Py\_ssize\_t size, const char \*errors)
  - *Return value: New reference.* Create a Unicode object by decoding *size* bytes of the Unicode-Escape encoded string *s.* Return *NULL* if an exception was raised by the codec.
- PyObject\* PyUnicode\_AsUnicodeEscapeString (PyObject \*unicode)

*Return value: New reference.* Encode a Unicode object using Unicode-Escape and return the result as a bytes object. Error handling is "strict". Return *NULL* if an exception was raised by the codec.

- PyObject\* PyUnicode\_EncodeUnicodeEscape (const Py\_UNICODE \*s, Py\_ssize\_t size)
  - *Return value: New reference.* Encode the *Py\_UNICODE* buffer of the given *size* using Unicode-Escape and return a bytes object. Return *NULL* if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style *Py\_UNICODE* API; please migrate to using *PyUnicode\_AsUnicodeEscapeString()*.

#### **Raw-Unicode-Escape Codecs**

These are the "Raw Unicode Escape" codec APIs:

PyObject\* PyUnicode\_DecodeRawUnicodeEscape (const char \*s, Py\_ssize\_t size, const char \*errors)

*Return value: New reference.* Create a Unicode object by decoding *size* bytes of the Raw-Unicode-Escape encoded string *s.* Return *NULL* if an exception was raised by the codec.

PyObject\* PyUnicode\_AsRawUnicodeEscapeString (PyObject \*unicode)

*Return value: New reference.* Encode a Unicode object using Raw-Unicode-Escape and return the result as a bytes object. Error handling is "strict". Return *NULL* if an exception was raised by the codec.

PyObject\* PyUnicode\_EncodeRawUnicodeEscape (const Py\_UNICODE \*s, Py\_ssize\_t size)

*Return value: New reference.* Encode the *Py\_UNICODE* buffer of the given *size* using Raw-Unicode-Escape and return a bytes object. Return *NULL* if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py\_UNICODE API; please migrate to using PyUnicode\_AsRawUnicodeEscapeString() or PyUnicode\_AsEncodedString().

#### **Latin-1 Codecs**

These are the Latin-1 codec APIs: Latin-1 corresponds to the first 256 Unicode ordinals and only these are accepted by the codecs during encoding.

PyObject\* PyUnicode\_DecodeLatin1 (const char \*s, Py\_ssize\_t size, const char \*errors)

*Return value: New reference.* Create a Unicode object by decoding *size* bytes of the Latin-1 encoded string *s*. Return *NULL* if an exception was raised by the codec.

PyObject\* PyUnicode\_AsLatin1String (PyObject \*unicode)

*Return value: New reference.* Encode a Unicode object using Latin-1 and return the result as Python bytes object. Error handling is "strict". Return *NULL* if an exception was raised by the codec.

PyObject\* PyUnicode\_EncodeLatin1 (const Py\_UNICODE \*s, Py\_ssize\_t size, const char \*errors)

*Return value: New reference.* Encode the *Py\_UNICODE* buffer of the given *size* using Latin-1 and return a Python bytes object. Return *NULL* if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py\_UNICODE API; please migrate to using PyUnicode\_AsLatin1String() or PyUnicode\_AsEncodedString().

#### **ASCII Codecs**

These are the ASCII codec APIs. Only 7-bit ASCII data is accepted. All other codes generate errors.

PyObject\* PyUnicode\_DecodeASCII (const char \*s, Py\_ssize\_t size, const char \*errors)

*Return value: New reference.* Create a Unicode object by decoding *size* bytes of the ASCII encoded string *s*. Return *NULL* if an exception was raised by the codec.

PyObject\* PyUnicode\_AsASCIIString (PyObject \*unicode)

*Return value: New reference.* Encode a Unicode object using ASCII and return the result as Python bytes object. Error handling is "strict". Return *NULL* if an exception was raised by the codec.

PyObject\* PyUnicode EncodeASCII (const Py\_UNICODE \*s, Py\_ssize\_t size, const char \*errors)

*Return value: New reference.* Encode the *Py\_UNICODE* buffer of the given *size* using ASCII and return a Python bytes object. Return *NULL* if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py\_UNICODE API; please migrate to using PyUnicode\_AsASCIIString() or PyUnicode\_AsEncodedString().

## **Character Map Codecs**

This codec is special in that it can be used to implement many different codecs (and this is in fact what was done to obtain most of the standard codecs included in the <code>encodings</code> package). The codec uses mapping to encode and decode characters. The mapping objects provided must support the <code>\_\_getitem\_\_()</code> mapping interface; dictionaries and sequences work well.

These are the mapping codec APIs:

PyObject\* PyUnicode\_DecodeCharmap (const char \*data, Py\_ssize\_t size, PyObject \*mapping, const char \*errors)

*Return value: New reference.* Create a Unicode object by decoding *size* bytes of the encoded string *s* using the given *mapping* object. Return *NULL* if an exception was raised by the codec.

If mapping is NULL, Latin-1 decoding will be applied. Else mapping must map bytes ordinals (integers in the range from 0 to 255) to Unicode strings, integers (which are then interpreted as Unicode ordinals) or None. Unmapped data bytes – ones which cause a LookupError, as well as ones which get mapped to None, 0xFFFE or '\ufffe', are treated as undefined mappings and cause an error.

#### PyObject\* PyUnicode\_AsCharmapString (PyObject \*unicode, PyObject \*mapping)

*Return value: New reference.* Encode a Unicode object using the given *mapping* object and return the result as a bytes object. Error handling is "strict". Return *NULL* if an exception was raised by the codec.

The *mapping* object must map Unicode ordinal integers to bytes objects, integers in the range from 0 to 255 or None. Unmapped character ordinals (ones which cause a LookupError) as well as mapped to None are treated as "undefined mapping" and cause an error.

# PyObject\* PyUnicode\_EncodeCharmap (const Py\_UNICODE \*s, Py\_ssize\_t size, PyObject \*mapping, const char \*errors)

Return value: New reference. Encode the Py\_UNICODE buffer of the given size using the given mapping object and return the result as a bytes object. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py\_UNICODE API; please migrate to using PyUnicode\_AsCharmapString() or PyUnicode\_AsEncodedString().

The following codec API is special in that maps Unicode to Unicode.

#### PyObject\* PyUnicode\_Translate (PyObject \*unicode, PyObject \*mapping, const char \*errors)

*Return value: New reference.* Translate a Unicode object using the given *mapping* object and return the resulting Unicode object. Return *NULL* if an exception was raised by the codec.

The *mapping* object must map Unicode ordinal integers to Unicode strings, integers (which are then interpreted as Unicode ordinals) or None (causing deletion of the character). Unmapped character ordinals (ones which cause a LookupError) are left untouched and are copied as-is.

# PyObject\* PyUnicode\_TranslateCharmap (const Py\_UNICODE \*s, Py\_ssize\_t size, PyObject \*mapping, const char \*errors)

Return value: New reference. Translate a Py\_UNICODE buffer of the given size by applying a character mapping table to it and return the resulting Unicode object. Return NULL when an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py\_UNICODE API; please migrate to using PyUnicode\_Translate(). or generic codec based API

#### **MBCS** codecs for Windows

These are the MBCS codec APIs. They are currently only available on Windows and use the Win32 MBCS converters to implement the conversions. Note that MBCS (or DBCS) is a class of encodings, not just one. The target encoding is defined by the user settings on the machine running the codec.

## PyObject\* PyUnicode\_DecodeMBCS (const char \*s, Py\_ssize\_t size, const char \*errors)

*Return value: New reference.* Create a Unicode object by decoding *size* bytes of the MBCS encoded string *s*. Return *NULL* if an exception was raised by the codec.

# PyObject\* PyUnicode\_DecodeMBCSStateful (const char \*s, Py\_ssize\_t size, const char \*errors, Py ssize t \*consumed)

Return value: New reference. If consumed is NULL, behave like <code>PyUnicode\_DecodeMBCS()</code>. If consumed is not NULL, <code>PyUnicode\_DecodeMBCSStateful()</code> will not decode trailing lead byte and the number of bytes that have been decoded will be stored in consumed.

#### PyObject\* PyUnicode\_AsMBCSString (PyObject \*unicode)

*Return value: New reference.* Encode a Unicode object using MBCS and return the result as Python bytes object. Error handling is "strict". Return *NULL* if an exception was raised by the codec.

#### PyObject\* PyUnicode EncodeCodePage (int code page, PyObject \*unicode, const char \*errors)

*Return value: New reference.* Encode the Unicode object using the specified code page and return a Python bytes object. Return *NULL* if an exception was raised by the codec. Use CP\_ACP code page to get the MBCS encoder.

New in version 3.3.

PyObject\* PyUnicode\_EncodeMBCS (const Py\_UNICODE \*s, Py\_ssize\_t size, const char \*errors)

*Return value: New reference.* Encode the *Py\_UNICODE* buffer of the given *size* using MBCS and return a Python bytes object. Return *NULL* if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py\_UNICODE API; please migrate to using PyUnicode\_AsMBCSString(), PyUnicode\_EncodeCodePage() or PyUnicode\_AsEncodedString().

#### **Methods & Slots**

#### **Methods and Slot Functions**

The following APIs are capable of handling Unicode objects and strings on input (we refer to them as strings in the descriptions) and return Unicode objects or integers as appropriate.

They all return NULL or -1 if an exception occurs.

- PyObject\* PyUnicode\_Concat (PyObject \*left, PyObject \*right)
  - Return value: New reference. Concat two strings giving a new Unicode string.
- PyObject\* PyUnicode\_Split (PyObject \*s, PyObject \*sep, Py\_ssize\_t maxsplit)

Return value: New reference. Split a string giving a list of Unicode strings. If sep is NULL, splitting will be done at all whitespace substrings. Otherwise, splits occur at the given separator. At most maxsplit splits will be done. If negative, no limit is set. Separators are not included in the resulting list.

- PyObject\* PyUnicode\_Splitlines (PyObject \*s, int keepend)
  - Return value: New reference. Split a Unicode string at line breaks, returning a list of Unicode strings. CRLF is considered to be one line break. If keepend is 0, the Line break characters are not included in the resulting strings.
- PyObject\* PyUnicode\_Translate (PyObject \*str, PyObject \*table, const char \*errors)

Translate a string by applying a character mapping table to it and return the resulting Unicode object.

The mapping table must map Unicode ordinal integers to Unicode ordinal integers or None (causing deletion of the character).

Mapping tables need only provide the \_\_getitem\_\_() interface; dictionaries and sequences work well. Unmapped character ordinals (ones which cause a LookupError) are left untouched and are copied as-is.

errors has the usual meaning for codecs. It may be NULL which indicates to use the default error handling.

- PyObject\* PyUnicode\_Join (PyObject \*separator, PyObject \*seq)
  - Return value: New reference. Join a sequence of strings using the given separator and return the resulting Unicode string.
- Py\_ssize\_t PyUnicode\_Tailmatch (PyObject \*str, PyObject \*substr, Py\_ssize\_t start, Py\_ssize\_t end, int direction)

Return 1 if *substr* matches str[start:end] at the given tail end (*direction* == -1 means to do a prefix match, *direction* == 1 a suffix match), 0 otherwise. Return -1 if an error occurred.

- Py\_ssize\_t PyUnicode\_Find (PyObject \*str, PyObject \*substr, Py\_ssize\_t start, Py\_ssize\_t end, int direction)

  Return the first position of substr in str[start:end] using the given direction (direction == 1 means to do a forward search, direction == -1 a backward search). The return value is the index of the first match; a value of -1 indicates that no match was found, and -2 indicates that an error occurred and an exception has been set.
- Py\_ssize\_t PyUnicode\_FindChar ( $PyObject *str, Py\_UCS4 ch$ , Py\_ssize\_t start, Py\_ssize\_t end, int direction)

  Return the first position of the character ch in str[start:end] using the given direction (direction == 1 means to do a forward search, direction == -1 a backward search). The return value is the index of the first match; a value of -1 indicates that no match was found, and -2 indicates that an error occurred and an exception has been set.

New in version 3.3.

Changed in version 3.7: start and end are now adjusted to behave like str[start:end].

## Py\_ssize\_t PyUnicode\_Count (PyObject \*str, PyObject \*substr, Py\_ssize\_t start, Py\_ssize\_t end)

Return the number of non-overlapping occurrences of *substr* in str[start:end]. Return -1 if an error occurred.

## PyObject\* PyUnicode Replace (PyObject \*str, PyObject \*substr, PyObject \*replstr, Py\_ssize\_t maxcount)

Return value: New reference. Replace at most maxcount occurrences of substr in str with replstr and return the resulting Unicode object. maxcount == -1 means replace all occurrences.

## int PyUnicode\_Compare (PyObject \*left, PyObject \*right)

Compare two strings and return -1, 0, 1 for less than, equal, and greater than, respectively.

This function returns -1 upon failure, so one should call PyErr\_Occurred() to check for errors.

## int PyUnicode\_CompareWithASCIIString (PyObject \*uni, const char \*string)

Compare a Unicode object, uni, with string and return -1, 0, 1 for less than, equal, and greater than, respectively. It is best to pass only ASCII-encoded strings, but the function interprets the input string as ISO-8859-1 if it contains non-ASCII characters.

This function does not raise exceptions.

#### PyObject\* PyUnicode\_RichCompare (PyObject \*left, PyObject \*right, int op)

Return value: New reference. Rich compare two Unicode strings and return one of the following:

- NULL in case an exception was raised
- Py\_True or Py\_False for successful comparisons
- Py\_NotImplemented in case the type combination is unknown

Possible values for op are Py\_GT, Py\_GE, Py\_EQ, Py\_NE, Py\_LT, and Py\_LE.

## PyObject\* PyUnicode\_Format (PyObject \*format, PyObject \*args)

Return value: New reference. Return a new string object from format and args; this is analogous to format % args.

#### int PyUnicode\_Contains (PyObject \*container, PyObject \*element)

Check whether *element* is contained in *container* and return true or false accordingly.

element has to coerce to a one element Unicode string. -1 is returned if there was an error.

#### void PyUnicode\_InternInPlace (PyObject \*\*string)

Intern the argument \*string in place. The argument must be the address of a pointer variable pointing to a Python Unicode string object. If there is an existing interned string that is the same as \*string, it sets \*string to it (decrementing the reference count of the old string object and incrementing the reference count of the interned string object), otherwise it leaves \*string alone and interns it (incrementing its reference count). (Clarification: even though there is a lot of talk about reference counts, think of this function as reference-count-neutral; you own the object after the call if and only if you owned it before the call.)

#### PyObject\* PyUnicode\_InternFromString (const char \*v)

Return value: New reference. A combination of PyUnicode\_FromString() and PyUnicode\_InternInPlace(), returning either a new Unicode string object that has been interned, or a new ("owned") reference to an earlier interned string object with the same value.

## 8.3.4 Tuple Objects

## PyTupleObject

This subtype of PyObject represents a Python tuple object.

#### PyTypeObject PyTuple\_Type

This instance of PyTypeObject represents the Python tuple type; it is the same object as tuple in the Python layer.

#### int PyTuple\_Check (PyObject \*p)

Return true if p is a tuple object or an instance of a subtype of the tuple type.

#### int PyTuple\_CheckExact (PyObject \*p)

Return true if p is a tuple object, but not an instance of a subtype of the tuple type.

#### PyObject\* PyTuple\_New (Py\_ssize\_t len)

Return value: New reference. Return a new tuple object of size len, or NULL on failure.

#### *PyObject\** **PyTuple\_Pack** (Py\_ssize\_t n, ...)

Return value: New reference. Return a new tuple object of size n, or NULL on failure. The tuple values are initialized to the subsequent n C arguments pointing to Python objects. PyTuple\_Pack(2, a, b) is equivalent to Py\_BuildValue("(00)", a, b).

## Py\_ssize\_t PyTuple\_Size (PyObject \*p)

Take a pointer to a tuple object, and return the size of that tuple.

#### Py\_ssize\_t PyTuple\_GET\_SIZE (PyObject \*p)

Return the size of the tuple p, which must be non-NULL and point to a tuple; no error checking is performed.

#### PyObject\* PyTuple\_GetItem (PyObject \*p, Py\_ssize\_t pos)

*Return value: Borrowed reference.* Return the object at position *pos* in the tuple pointed to by *p*. If *pos* is out of bounds, return *NULL* and sets an IndexError exception.

#### PyObject\* PyTuple\_GET\_ITEM (PyObject \*p, Py\_ssize\_t pos)

Return value: Borrowed reference. Like PyTuple\_GetItem(), but does no checking of its arguments.

## PyObject\* PyTuple\_GetSlice (PyObject \*p, Py\_ssize\_t low, Py\_ssize\_t high)

Return value: New reference. Take a slice of the tuple pointed to by p from low to high and return it as a new tuple.

## int PyTuple\_SetItem (PyObject \*p, Py\_ssize\_t pos, PyObject \*o)

Insert a reference to object o at position pos of the tuple pointed to by p. Return 0 on success.

**Note:** This function "steals" a reference to o.

## void PyTuple\_SET\_ITEM (PyObject \*p, Py\_ssize\_t pos, PyObject \*o)

Like PyTuple SetItem(), but does no error checking, and should only be used to fill in brand new tuples.

**Note:** This function "steals" a reference to o.

#### int \_PyTuple\_Resize (*PyObject* \*\*p, Py\_ssize\_t newsize)

Can be used to resize a tuple. *newsize* will be the new length of the tuple. Because tuples are *supposed* to be immutable, this should only be used if there is only one reference to the object. Do *not* use this if the tuple may already be known to some other part of the code. The tuple will always grow or shrink at the end. Think of this as destroying the old tuple and creating a new one, only more efficiently. Returns 0 on success. Client code should never assume that the resulting value of \*p will be the same as before calling this function. If the object referenced by \*p is replaced, the original \*p is destroyed. On failure, returns -1 and sets \*p to *NULL*, and raises MemoryError or SystemError.

## int PyTuple\_ClearFreeList()

Clear the free list. Return the total number of freed items.

## 8.3.5 Struct Sequence Objects

Struct sequence objects are the C equivalent of namedtuple() objects, i.e. a sequence whose items can also be accessed through attributes. To create a struct sequence, you first have to create a specific struct sequence type.

#### PyTypeObject\* PyStructSequence\_NewType (PyStructSequence\_Desc \*desc)

*Return value: New reference.* Create a new struct sequence type from the data in *desc*, described below. Instances of the resulting type can be created with *PyStructSequence New()*.

## void PyStructSequence\_InitType (PyTypeObject \*type, PyStructSequence\_Desc \*desc)

Initializes a struct sequence type type from desc in place.

#### int PyStructSequence\_InitType2 (PyTypeObject \*type, PyStructSequence\_Desc \*desc)

The same as PyStructSequence\_InitType, but returns 0 on success and -1 on failure.

New in version 3.4.

#### PyStructSequence\_Desc

Contains the meta information of a struct sequence type to create.

Field	С Туре	Meaning
name	const char *	name of the struct sequence type
doc	const char *	pointer to docstring for the type or NULL to omit
fields	PyStructSequence_Fiel	d pointer to NULL-terminated array with field names of the
	*	new type
n_in_sequenceint		number of fields visible to the Python side (if used as
		tuple)

#### PyStructSequence\_Field

Describes a field of a struct sequence. As a struct sequence is modeled as a tuple, all fields are typed as PyObject\*. The index in the fields array of the  $PyStructSequence\_Desc$  determines which field of the struct sequence is described.

Field	С Туре	Meaning	
name	const	name for the field or NULL to end the list of named fields, set to PyStructSe-	
	char *	quence_UnnamedField to leave unnamed	
doc	const	field docstring or NULL to omit	
	char *		

#### char\* PyStructSequence\_UnnamedField

Special value for a field name to leave it unnamed.

#### PyObject\* PyStructSequence\_New (PyTypeObject \*type)

Return value: New reference. Creates an instance of type, which must have been created with PyStructSequence\_NewType().

#### PyObject\* PyStructSequence\_GetItem (PyObject \*p, Py\_ssize\_t pos)

Return value: Borrowed reference. Return the object at position pos in the struct sequence pointed to by p. No bounds checking is performed.

#### PyObject\* PyStructSequence\_GET\_ITEM (PyObject \*p, Py\_ssize\_t pos)

Return value: Borrowed reference. Macro equivalent of PyStructSequence\_GetItem().

#### void PyStructSequence\_SetItem (PyObject \*p, Py\_ssize\_t pos, PyObject \*o)

Sets the field at index pos of the struct sequence p to value o. Like  $PyTuple\_SET\_ITEM()$ , this should only be used to fill in brand new instances.

**Note:** This function "steals" a reference to o.

#### void PyStructSequence\_SET\_ITEM (PyObject \*p, Py\_ssize\_t \*pos, PyObject \*o)

Macro equivalent of PyStructSequence\_SetItem().

**Note:** This function "steals" a reference to o.

## 8.3.6 List Objects

#### PyListObject

This subtype of PyObject represents a Python list object.

#### PyTypeObject PyList\_Type

This instance of PyTypeObject represents the Python list type. This is the same object as list in the Python layer.

#### int PyList\_Check (PyObject \*p)

Return true if *p* is a list object or an instance of a subtype of the list type.

#### int PyList\_CheckExact (PyObject \*p)

Return true if p is a list object, but not an instance of a subtype of the list type.

#### PyObject\* PyList\_New (Py\_ssize\_t len)

Return value: New reference. Return a new list of length len on success, or NULL on failure.

**Note:** If *len* is greater than zero, the returned list object's items are set to NULL. Thus you cannot use abstract API functions such as *PySequence\_SetItem()* or expose the object to Python code before setting all items to a real object with *PyList\_SetItem()*.

#### Py\_ssize\_t PyList\_Size (PyObject \*list)

Return the length of the list object in *list*; this is equivalent to len(list) on a list object.

#### Py\_ssize\_t PyList\_GET\_SIZE (PyObject \*list)

Macro form of PyList\_Size() without error checking.

## PyObject\* PyList\_GetItem (PyObject \*list, Py\_ssize\_t index)

Return value: Borrowed reference. Return the object at position index in the list pointed to by list. The position must be non-negative; indexing from the end of the list is not supported. If index is out of bounds (<0 or >=len(list)), return NULL and set an IndexError exception.

## PyObject\* PyList\_GET\_ITEM (PyObject \*list, Py\_ssize\_t i)

Return value: Borrowed reference. Macro form of PyList GetItem() without error checking.

#### int PyList SetItem (PyObject \*list, Py ssize t index, PyObject \*item)

Set the item at index index in list to item. Return 0 on success or -1 on failure.

**Note:** This function "steals" a reference to *item* and discards a reference to an item already in the list at the affected position.

## void PyList\_SET\_ITEM (PyObject \*list, Py\_ssize\_t i, PyObject \*o)

Macro form of PyList\_SetItem() without error checking. This is normally only used to fill in new lists where there is no previous content.

**Note:** This macro "steals" a reference to *item*, and, unlike *PyList\_SetItem()*, does *not* discard a reference to any item that is being replaced; any reference in *list* at position *i* will be leaked.

## int PyList\_Insert (PyObject \*list, Py\_ssize\_t index, PyObject \*item)

Insert the item *item* into list *list* in front of index *index*. Return 0 if successful; return -1 and set an exception if unsuccessful. Analogous to list.insert(index, item).

#### int PyList\_Append (PyObject \*list, PyObject \*item)

Append the object *item* at the end of list *list*. Return 0 if successful; return -1 and set an exception if unsuccessful. Analogous to list.append(item).

## PyObject\* PyList\_GetSlice (PyObject \*list, Py\_ssize\_t low, Py\_ssize\_t high)

Return value: New reference. Return a list of the objects in *list* containing the objects between low and high. Return NULL and set an exception if unsuccessful. Analogous to list[low:high]. Negative indices, as when slicing from Python, are not supported.

## int PyList\_SetSlice (PyObject \*list, Py\_ssize\_t low, Py\_ssize\_t high, PyObject \*itemlist)

Set the slice of *list* between *low* and *high* to the contents of *itemlist*. Analogous to list[low:high] = itemlist. The *itemlist* may be *NULL*, indicating the assignment of an empty list (slice deletion). Return 0 on success, -1 on failure. Negative indices, as when slicing from Python, are not supported.

## int PyList\_Sort (PyObject \*list)

Sort the items of *list* in place. Return 0 on success, -1 on failure. This is equivalent to list.sort().

## int PyList\_Reverse (PyObject \*list)

Reverse the items of *list* in place. Return 0 on success, -1 on failure. This is the equivalent of list.reverse().

#### PyObject\* PyList\_AsTuple (PyObject \*list)

*Return value: New reference.* Return a new tuple object containing the contents of *list*; equivalent to tuple (list).

## int PyList\_ClearFreeList()

Clear the free list. Return the total number of freed items.

New in version 3.3.

# 8.4 Container Objects

## 8.4.1 Dictionary Objects

#### PyDictObject

This subtype of PyObject represents a Python dictionary object.

#### PyTypeObject PyDict\_Type

This instance of PyTypeObject represents the Python dictionary type. This is the same object as dict in the Python layer.

## int PyDict\_Check (PyObject \*p)

Return true if p is a dict object or an instance of a subtype of the dict type.

#### int PyDict\_CheckExact (PyObject \*p)

Return true if p is a dict object, but not an instance of a subtype of the dict type.

#### PyObject\* PyDict\_New()

Return value: New reference. Return a new empty dictionary, or NULL on failure.

#### PyObject\* PyDictProxy\_New (PyObject \*mapping)

Return value: New reference. Return a types. MappingProxyType object for a mapping which enforces readonly behavior. This is normally used to create a view to prevent modification of the dictionary for non-dynamic class types.

#### void PyDict\_Clear (PyObject \*p)

Empty an existing dictionary of all key-value pairs.

## int PyDict\_Contains (PyObject \*p, PyObject \*key)

Determine if dictionary p contains key. If an item in p is matches key, return 1, otherwise return 0. On error, return -1. This is equivalent to the Python expression key in p.

#### PyObject\* PyDict\_Copy (PyObject \*p)

Return value: New reference. Return a new dictionary that contains the same key-value pairs as p.

#### int PyDict\_SetItem (PyObject \*p, PyObject \*key, PyObject \*val)

Insert *value* into the dictionary p with a key of *key*. *key* must be *hashable*; if it isn't, TypeError will be raised. Return 0 on success or -1 on failure.

## int PyDict\_SetItemString (PyObject \*p, const char \*key, PyObject \*val)

Insert *value* into the dictionary *p* using *key* as a key. *key* should be a const char\*. The key object is created using PyUnicode\_FromString(key). Return 0 on success or -1 on failure.

#### int PyDict\_DelItem (PyObject \*p, PyObject \*key)

Remove the entry in dictionary p with key key. key must be hashable; if it isn't, TypeError is raised. Return 0 on success or -1 on failure.

## int PyDict\_DelItemString (PyObject \*p, const char \*key)

Remove the entry in dictionary p which has a key specified by the string key. Return 0 on success or -1 on failure.

## PyObject\* PyDict\_GetItem (PyObject \*p, PyObject \*key)

*Return value: Borrowed reference.* Return the object from dictionary *p* which has a key *key*. Return *NULL* if the key *key* is not present, but *without* setting an exception.

Note that exceptions which occur while calling \_\_hash\_\_() and \_\_eq\_\_() methods will get suppressed. To get error reporting use PyDict\_GetItemWithError() instead.

#### PyObject\* PyDict\_GetItemWithError (PyObject \*p, PyObject \*key)

*Return value: Borrowed reference.* Variant of PyDict\_GetItem() that does not suppress exceptions. Return *NULL* with an exception set if an exception occurred. Return *NULL* without an exception set if the key wasn't present.

## PyObject\* PyDict\_GetItemString (PyObject \*p, const char \*key)

Return value: Borrowed reference. This is the same as PyDict\_GetItem(), but key is specified as a const char\*, rather than a PyObject\*.

Note that exceptions which occur while calling \_\_hash\_\_() and \_\_eq\_\_() methods and creating a temporary string object will get suppressed. To get error reporting use PyDict\_GetItemWithError() instead.

## PyObject\* PyDict\_SetDefault (PyObject \*p, PyObject \*key, PyObject \*defaultobj)

Return value: Borrowed reference. This is the same as the Python-level dict.setdefault(). If present, it returns the value corresponding to key from the dictionary p. If the key is not in the dict, it is inserted with value defaultobj and defaultobj is returned. This function evaluates the hash function of key only once, instead of evaluating it independently for the lookup and the insertion.

New in version 3.4.

## PyObject\* PyDict\_Items (PyObject \*p)

Return value: New reference. Return a PyListObject containing all the items from the dictionary.

#### PyObject\* PyDict\_Keys (PyObject \*p)

Return value: New reference. Return a PyListObject containing all the keys from the dictionary.

#### PyObject\* PyDict\_Values (PyObject \*p)

Return value: New reference. Return a PyListObject containing all the values from the dictionary p.

#### Py\_ssize\_t PyDict\_Size (PyObject \*p)

Return the number of items in the dictionary. This is equivalent to len(p) on a dictionary.

```
int PyDict_Next (PyObject *p, Py_ssize_t *ppos, PyObject **pkey, PyObject **pvalue)
```

Iterate over all key-value pairs in the dictionary p. The Py\_ssize\_t referred to by ppos must be initialized to 0 prior to the first call to this function to start the iteration; the function returns true for each pair in the dictionary, and false once all pairs have been reported. The parameters pkey and pvalue should either point to PyObject\* variables that will be filled in with each key and value, respectively, or may be NULL. Any references returned through them are borrowed. ppos should not be altered during iteration. Its value represents offsets within the internal dictionary structure, and since the structure is sparse, the offsets are not consecutive.

#### For example:

```
PyObject *key, *value;
Py_ssize_t pos = 0;
while (PyDict_Next(self->dict, &pos, &key, &value)) {
    /* do something interesting with the values... */
    ...
}
```

The dictionary *p* should not be mutated during iteration. It is safe to modify the values of the keys as you iterate over the dictionary, but only so long as the set of keys does not change. For example:

```
PyObject *key, *value;
Py_ssize_t pos = 0;

while (PyDict_Next(self->dict, &pos, &key, &value)) {
    long i = PyLong_AsLong(value);
    if (i == -1 && PyErr_Occurred()) {
        return -1;
    }
    PyObject *o = PyLong_FromLong(i + 1);
    if (o == NULL)
        return -1;
    if (PyDict_SetItem(self->dict, key, o) < 0) {
        Py_DECREF(o);
        return -1;
    }
    Py_DECREF(o);
}</pre>
```

## int PyDict\_Merge (PyObject \*a, PyObject \*b, int override)

Iterate over mapping object b adding key-value pairs to dictionary a. b may be a dictionary, or any object supporting  $PyMapping\_Keys$  () and  $PyObject\_GetItem$  (). If override is true, existing pairs in a will be replaced if a matching key is found in b, otherwise pairs will only be added if there is not a matching key in a. Return 0 on success or -1 if an exception was raised.

#### int PyDict\_Update (PyObject \*a, PyObject \*b)

This is the same as PyDict\_Merge (a, b, 1) in C, and is similar to a update (b) in Python except that  $PyDict_Update$  () doesn't fall back to the iterating over a sequence of key value pairs if the second argument has no "keys" attribute. Return 0 on success or -1 if an exception was raised.

#### int PyDict\_MergeFromSeq2 (PyObject \*a, PyObject \*seq2, int override)

Update or merge into dictionary a, from the key-value pairs in seq2. seq2 must be an iterable object producing iterable objects of length 2, viewed as key-value pairs. In case of duplicate keys, the last wins if override is true,

else the first wins. Return 0 on success or -1 if an exception was raised. Equivalent Python (except for the return value):

```
def PyDict_MergeFromSeq2(a, seq2, override):
    for key, value in seq2:
        if override or key not in a:
        a[key] = value
```

#### int PyDict\_ClearFreeList()

Clear the free list. Return the total number of freed items.

New in version 3.3.

## 8.4.2 Set Objects

This section details the public API for set and frozenset objects. Any functionality not listed below is best accessed using the either the abstract object protocol (including PyObject\_CallMethod(), PyObject\_RichCompareBool(), PyObject\_Hash(), PyObject\_Repr(), PyObject\_IsTrue(), PyObject\_Print(), and PyObject\_GetIter()) or the abstract number protocol (including PyNumber\_And(), PyNumber\_Subtract(), PyNumber\_Or(), PyNumber\_Xor(), PyNumber\_InPlaceAnd(), PyNumber\_InPlaceSubtract(), PyNumber\_InPlaceOr(), and PyNumber\_InPlaceXor()).

## PySetObject

This subtype of *PyObject* is used to hold the internal data for both set and frozenset objects. It is like a *PyDictObject* in that it is a fixed size for small sets (much like tuple storage) and will point to a separate, variable sized block of memory for medium and large sized sets (much like list storage). None of the fields of this structure should be considered public and are subject to change. All access should be done through the documented API rather than by manipulating the values in the structure.

#### PyTypeObject PySet Type

This is an instance of PyTypeObject representing the Python set type.

#### PyTypeObject PyFrozenSet\_Type

This is an instance of PyTypeObject representing the Python frozenset type.

The following type check macros work on pointers to any Python object. Likewise, the constructor functions work with any iterable Python object.

```
int PySet Check (PyObject *p)
```

Return true if *p* is a set object or an instance of a subtype.

```
int PyFrozenSet_Check (PyObject *p)
```

Return true if *p* is a frozenset object or an instance of a subtype.

```
int PyAnySet_Check (PyObject *p)
```

Return true if p is a set object, a frozenset object, or an instance of a subtype.

```
int PyAnySet_CheckExact (PyObject *p)
```

Return true if *p* is a set object or a frozenset object but not an instance of a subtype.

```
int PyFrozenSet_CheckExact (PyObject *p)
```

Return true if *p* is a frozenset object but not an instance of a subtype.

```
PyObject* PySet_New (PyObject *iterable)
```

Return value: New reference. Return a new set containing objects returned by the *iterable*. The *iterable* may be *NULL* to create a new empty set. Return the new set on success or *NULL* on failure. Raise TypeError if *iterable* is not actually iterable. The constructor is also useful for copying a set (c=set (s)).

#### PyObject\* PyFrozenSet\_New (PyObject \*iterable)

Return value: New reference. Return a new frozenset containing objects returned by the *iterable*. The *iterable* may be *NULL* to create a new empty frozenset. Return the new set on success or *NULL* on failure. Raise TypeError if *iterable* is not actually iterable.

The following functions and macros are available for instances of set or frozenset or instances of their subtypes.

#### Py ssize t PySet Size (PyObject \*anyset)

Return the length of a set or frozenset object. Equivalent to len(anyset). Raises a PyExc\_SystemError if *anyset* is not a set, frozenset, or an instance of a subtype.

#### Py\_ssize\_t PySet\_GET\_SIZE (PyObject \*anyset)

Macro form of PySet\_Size () without error checking.

```
int PySet_Contains (PyObject *anyset, PyObject *key)
```

Return 1 if found, 0 if not found, and -1 if an error is encountered. Unlike the Python \_\_contains\_\_() method, this function does not automatically convert unhashable sets into temporary frozensets. Raise a TypeError if the key is unhashable. Raise PyExc\_SystemError if anyset is not a set, frozenset, or an instance of a subtype.

#### int PySet\_Add (PyObject \*set, PyObject \*key)

Add key to a set instance. Also works with frozenset instances (like PyTuple\_SetItem() it can be used to fill-in the values of brand new frozensets before they are exposed to other code). Return 0 on success or -1 on failure. Raise a TypeError if the key is unhashable. Raise a MemoryError if there is no room to grow. Raise a SystemError if set is not an instance of set or its subtype.

The following functions are available for instances of set or its subtypes but not for instances of frozenset or its subtypes.

## int PySet\_Discard (PyObject \*set, PyObject \*key)

Return 1 if found and removed, 0 if not found (no action taken), and -1 if an error is encountered. Does not raise KeyError for missing keys. Raise a TypeError if the *key* is unhashable. Unlike the Python discard() method, this function does not automatically convert unhashable sets into temporary frozensets. Raise PyExc\_SystemError if *set* is not an instance of set or its subtype.

#### PyObject\* PySet\_Pop (PyObject \*set)

Return value: New reference. Return a new reference to an arbitrary object in the set, and removes the object from the set. Return NULL on failure. Raise KeyError if the set is empty. Raise a SystemError if set is not an instance of set or its subtype.

#### int PySet\_Clear (PyObject \*set)

Empty an existing set of all elements.

## int PySet\_ClearFreeList()

Clear the free list. Return the total number of freed items.

New in version 3.3.

## 8.5 Function Objects

## 8.5.1 Function Objects

There are a few functions specific to Python functions.

#### PyFunctionObject

The C structure used for functions.

#### PyTypeObject PyFunction\_Type

This is an instance of PyTypeObject and represents the Python function type. It is exposed to Python programmers as types. FunctionType.

## int PyFunction\_Check (PyObject \*o)

Return true if o is a function object (has type  $PyFunction\_Type$ ). The parameter must not be NULL.

#### PyObject\* PyFunction New (PyObject \*code, PyObject \*globals)

*Return value: New reference.* Return a new function object associated with the code object *code. globals* must be a dictionary with the global variables accessible to the function.

The function's docstring and name are retrieved from the code object. \_\_module\_\_ is retrieved from globals. The argument defaults, annotations and closure are set to NULL. \_\_qualname\_\_ is set to the same value as the function's name.

#### PyObject\* PyFunction NewWithQualName (PyObject \*code, PyObject \*globals, PyObject \*qualname)

Return value: New reference. As PyFunction\_New(), but also allows setting the function object's \_\_qualname\_\_ attribute. qualname should be a unicode object or NULL; if NULL, the \_\_qualname\_\_ attribute is set to the same value as its \_\_name\_\_ attribute.

New in version 3.3.

#### PyObject\* PyFunction\_GetCode (PyObject \*op)

Return value: Borrowed reference. Return the code object associated with the function object op.

## PyObject\* PyFunction\_GetGlobals (PyObject \*op)

Return value: Borrowed reference. Return the globals dictionary associated with the function object op.

## PyObject\* PyFunction\_GetModule (PyObject \*op)

*Return value: Borrowed reference.* Return the \_\_module\_\_ attribute of the function object op. This is normally a string containing the module name, but can be set to any other object by Python code.

## PyObject\* PyFunction\_GetDefaults (PyObject \*op)

Return value: Borrowed reference. Return the argument default values of the function object op. This can be a tuple of arguments or NULL.

#### int PyFunction\_SetDefaults (PyObject \*op, PyObject \*defaults)

Set the argument default values for the function object op. defaults must be Py\_None or a tuple.

Raises SystemError and returns -1 on failure.

## PyObject\* PyFunction\_GetClosure (PyObject \*op)

*Return value: Borrowed reference.* Return the closure associated with the function object *op*. This can be *NULL* or a tuple of cell objects.

#### int PyFunction\_SetClosure (PyObject \*op, PyObject \*closure)

Set the closure associated with the function object op. closure must be Py None or a tuple of cell objects.

Raises SystemError and returns -1 on failure.

## PyObject \*PyFunction\_GetAnnotations (PyObject \*op)

*Return value: Borrowed reference.* Return the annotations of the function object *op.* This can be a mutable dictionary or *NULL*.

#### int PyFunction\_SetAnnotations (PyObject \*op, PyObject \*annotations)

Set the annotations for the function object op. annotations must be a dictionary or Py\_None.

Raises SystemError and returns -1 on failure.

## 8.5.2 Instance Method Objects

An instance method is a wrapper for a PyCFunction and the new way to bind a PyCFunction to a class object. It replaces the former call PyMethod\_New(func, NULL, class).

#### PyTypeObject PyInstanceMethod\_Type

This instance of PyTypeObject represents the Python instance method type. It is not exposed to Python programs.

## int PyInstanceMethod\_Check (PyObject \*o)

Return true if o is an instance method object (has type  $PyInstanceMethod\_Type$ ). The parameter must not be NULL.

#### PyObject\* PyInstanceMethod\_New (PyObject \*func)

*Return value: New reference.* Return a new instance method object, with *func* being any callable object *func* is the function that will be called when the instance method is called.

#### PyObject\* PyInstanceMethod\_Function (PyObject \*im)

Return value: Borrowed reference. Return the function object associated with the instance method im.

#### PyObject\* PyInstanceMethod\_GET\_FUNCTION (PyObject \*im)

Return value: Borrowed reference. Macro version of PyInstanceMethod\_Function() which avoids error checking.

## 8.5.3 Method Objects

Methods are bound function objects. Methods are always bound to an instance of a user-defined class. Unbound methods (methods bound to a class object) are no longer available.

#### PyTypeObject PyMethod\_Type

This instance of PyTypeObject represents the Python method type. This is exposed to Python programs as types. MethodType.

#### int PyMethod\_Check (PyObject \*o)

Return true if o is a method object (has type  $PyMethod\_Type$ ). The parameter must not be NULL.

## PyObject\* PyMethod\_New (PyObject \*func, PyObject \*self)

Return value: New reference. Return a new method object, with func being any callable object and self the instance the method should be bound. func is the function that will be called when the method is called. self must not be NULL.

#### PyObject\* PyMethod\_Function (PyObject \*meth)

Return value: Borrowed reference. Return the function object associated with the method meth.

#### PyObject\* PyMethod GET FUNCTION (PyObject \*meth)

Return value: Borrowed reference. Macro version of PyMethod\_Function() which avoids error checking.

## PyObject\* PyMethod\_Self (PyObject \*meth)

Return value: Borrowed reference. Return the instance associated with the method meth.

#### PyObject\* PyMethod GET SELF (PyObject \*meth)

Return value: Borrowed reference. Macro version of PyMethod\_Self() which avoids error checking.

#### int PyMethod ClearFreeList()

Clear the free list. Return the total number of freed items.

## 8.5.4 Cell Objects

"Cell" objects are used to implement variables referenced by multiple scopes. For each such variable, a cell object is created to store the value; the local variables of each stack frame that references the value contains a reference to the cells from outer scopes which also use that variable. When the value is accessed, the value contained in the cell is used instead of the cell object itself. This de-referencing of the cell object requires support from the generated byte-code; these are not automatically de-referenced when accessed. Cell objects are not likely to be useful elsewhere.

#### PyCellObject

The C structure used for cell objects.

#### PyTypeObject PyCell\_Type

The type object corresponding to cell objects.

```
int PyCell_Check (ob)
```

Return true if *ob* is a cell object; *ob* must not be *NULL*.

```
PyObject* PyCell_New (PyObject *ob)
```

Return value: New reference. Create and return a new cell object containing the value ob. The parameter may be NULL.

```
PyObject* PyCell Get (PyObject *cell)
```

Return value: New reference. Return the contents of the cell cell.

```
PyObject* PyCell_GET (PyObject *cell)
```

Return value: Borrowed reference. Return the contents of the cell cell, but without checking that cell is non-NULL and a cell object.

```
int PyCell Set (PyObject *cell, PyObject *value)
```

Set the contents of the cell object *cell* to *value*. This releases the reference to any current content of the cell. *value* may be *NULL*. *cell* must be non-*NULL*; if it is not a cell object, -1 will be returned. On success, 0 will be returned.

```
void PyCell_SET (PyObject *cell, PyObject *value)
```

Sets the value of the cell object *cell* to *value*. No reference counts are adjusted, and no checks are made for safety; *cell* must be non-*NULL* and must be a cell object.

## 8.5.5 Code Objects

Code objects are a low-level detail of the CPython implementation. Each one represents a chunk of executable code that hasn't yet been bound into a function.

## PyCodeObject

The C structure of the objects used to describe code objects. The fields of this type are subject to change at any time.

```
PyTypeObject PyCode_Type
```

This is an instance of PyTypeObject representing the Python code type.

```
int PyCode_Check (PyObject *co)
```

Return true if co is a code object.

```
int PyCode_GetNumFree (PyCodeObject *co)
```

Return the number of free variables in *co*.

```
PyCodeObject* PyCode_New (int argcount, int kwonlyargcount, int nlocals, int stacksize, int flags, PyObject *code, PyObject *consts, PyObject *names, PyObject *varnames, PyObject *filename, PyObject *name, int first-lineno, PyObject *lnotab)
```

Return value: New reference. Return a new code object. If you need a dummy code object to create a frame, use

PyCode\_NewEmpty() instead. Calling PyCode\_New() directly can bind you to a precise Python version since the definition of the bytecode changes often.

Raises an auditing event code.\_\_new\_\_ with arguments code, filename, name, argcount, posonlyargcount, kwonlyargcount, nlocals, stacksize, flags.

PyCodeObject\* PyCode\_NewWithPosOnlyArgs (int argcount, int posonlyargcount, int kwonlyargcount, int nlocals, int stacksize, int flags, PyObject \*code, PyObject \*consts, PyObject \*names, PyObject \*freevars, PyObject \*freevars, PyObject \*filename, PyObject \*name, int firstlineno, PyObject \*lnotab)

Return value: New reference. Similar to  $PyCode_New()$ , but with an extra "posonlyargcount" for positonal-only arguments.

New in version 3.8.

PyCodeObject\* PyCode\_NewEmpty (const char \*filename, const char \*funcname, int firstlineno)

Return value: New reference. Return a new empty code object with the specified filename, function name, and first line number. It is illegal to exec() or eval() the resulting code object.

## 8.6 Other Objects

## 8.6.1 File Objects

These APIs are a minimal emulation of the Python 2 C API for built-in file objects, which used to rely on the buffered I/O (FILE\*) support from the C standard library. In Python 3, files and streams use the new  $i \circ$  module, which defines several layers over the low-level unbuffered I/O of the operating system. The functions described below are convenience C wrappers over these new APIs, and meant mostly for internal error reporting in the interpreter; third-party code is advised to access the  $i \circ$  APIs instead.

**PyFile\_FromFd** (int *fd*, const char \*name, const char \*mode, int buffering, const char \*encoding, const char \*errors, const char \*newline, int closefd)

Return value: New reference. Create a Python file object from the file descriptor of an already opened file fd. The arguments name, encoding, errors and newline can be NULL to use the defaults; buffering can be -1 to use the default. name is ignored and kept for backward compatibility. Return NULL on failure. For a more comprehensive description of the arguments, please refer to the io.open() function documentation.

**Warning:** Since Python streams have their own buffering layer, mixing them with OS-level file descriptors can produce various issues (such as unexpected ordering of data).

Changed in version 3.2: Ignore *name* attribute.

#### int PyObject\_AsFileDescriptor(PyObject \*p)

Return the file descriptor associated with p as an int. If the object is an integer, its value is returned. If not, the object's fileno() method is called if it exists; the method must return an integer, which is returned as the file descriptor value. Sets an exception and returns -1 on failure.

```
PyObject* PyFile_GetLine (PyObject *p, int n)
```

Return value: New reference. Equivalent to p.readline([n]), this function reads one line from the object p. p may be a file object or any object with a readline() method. If n is 0, exactly one line is read, regardless of the length of the line. If n is greater than 0, no more than n bytes will be read from the file; a partial line can be returned. In both cases, an empty string is returned if the end of the file is reached immediately. If n is less than 0, however, one line is read regardless of length, but EOFError is raised if the end of the file is reached immediately.

#### int PyFile\_SetOpenCodeHook (Py\_OpenCodeHookFunction handler)

Overrides the normal behavior of io.open\_code () to pass its parameter through the provided handler.

The handler is a function of type PyObject \*(\*) (PyObject \*path, void \*userData), where path is guaranteed to be PyUnicodeObject.

The *userData* pointer is passed into the hook function. Since hook functions may be called from different runtimes, this pointer should not refer directly to Python state.

As this hook is intentionally used during import, avoid importing new modules during its execution unless they are known to be frozen or available in sys.modules.

Once a hook has been set, it cannot be removed or replaced, and later calls to PyFile\_SetOpenCodeHook () will fail. On failure, the function returns -1 and sets an exception if the interpreter has been initialized.

This function is safe to call before Py\_Initialize().

New in version 3.8.

## int PyFile\_WriteObject (PyObject \*obj, PyObject \*p, int flags)

Write object *obj* to file object *p*. The only supported flag for *flags* is Py\_PRINT\_RAW; if given, the str() of the object is written instead of the repr(). Return 0 on success or -1 on failure; the appropriate exception will be set.

#### int PyFile\_WriteString (const char \*s, PyObject \*p)

Write string s to file object p. Return 0 on success or -1 on failure; the appropriate exception will be set.

## 8.6.2 Module Objects

#### PyTypeObject PyModule\_Type

This instance of PyTypeObject represents the Python module type. This is exposed to Python programs as types. ModuleType.

#### int PyModule\_Check (PyObject \*p)

Return true if p is a module object, or a subtype of a module object.

#### int PyModule\_CheckExact (PyObject \*p)

Return true if *p* is a module object, but not a subtype of *PyModule\_Type*.

#### PyObject\* PyModule\_NewObject (PyObject \*name)

Return value: New reference. Return a new module object with the \_\_name\_\_ attribute set to name. The module's \_\_name\_\_, \_\_doc\_\_, \_\_package\_\_, and \_\_loader\_\_ attributes are filled in (all but \_\_name\_\_ are set to None); the caller is responsible for providing a \_\_file\_\_ attribute.

New in version 3.3.

Changed in version 3.4: \_\_package\_\_ and \_\_loader\_\_ are set to None.

#### PyObject\* PyModule New (const char \*name)

Return value: New reference. Similar to PyModule\_NewObject(), but the name is a UTF-8 encoded string instead of a Unicode object.

#### PyObject\* PyModule\_GetDict (PyObject \*module)

Return value: Borrowed reference. Return the dictionary object that implements module's namespace; this object is the same as the \_\_dict\_\_ attribute of the module object. If module is not a module object (or a subtype of a module object), SystemError is raised and NULL is returned.

It is recommended extensions use other  $PyModule_*()$  and  $PyObject_*()$  functions rather than directly manipulate a module's  $\_\_dict\_\_$ .

#### PyObject\* PyModule\_GetNameObject (PyObject \*module)

*Return value: New reference.* Return *module*'s \_\_name\_\_ value. If the module does not provide one, or if it is not a string, SystemError is raised and *NULL* is returned.

New in version 3.3.

#### const char\* PyModule GetName (PyObject \*module)

Similar to PyModule GetNameObject () but return the name encoded to 'utf-8'.

#### void\* PyModule GetState (PyObject \*module)

Return the "state" of the module, that is, a pointer to the block of memory allocated at module creation time, or *NULL*. See *PyModuleDef.m\_size*.

#### PyModuleDef\* PyModule\_GetDef (PyObject \*module)

Return a pointer to the <code>PyModuleDef</code> struct from which the module was created, or <code>NULL</code> if the module wasn't created from a definition.

## PyObject\* PyModule\_GetFilenameObject (PyObject \*module)

Return value: New reference. Return the name of the file from which module was loaded using module's \_\_file\_\_ attribute. If this is not defined, or if it is not a unicode string, raise SystemError and return NULL; otherwise return a reference to a Unicode object.

New in version 3.2.

#### const char\* PyModule\_GetFilename (PyObject \*module)

Similar to PyModule\_GetFilenameObject() but return the filename encoded to 'utf-8'.

Deprecated since version 3.2: PyModule\_GetFilename() raises UnicodeEncodeError on unencodable filenames, use PyModule\_GetFilenameObject() instead.

## Initializing C modules

Modules objects are usually created from extension modules (shared libraries which export an initialization function), or compiled-in modules (where the initialization function is added using <code>PyImport\_AppendInittab()</code>). See building or extending-with-embedding for details.

The initialization function can either pass a module definition instance to <code>PyModule\_Create()</code>, and return the resulting module object, or request "multi-phase initialization" by returning the definition struct itself.

## PyModuleDef

The module definition struct, which holds all information needed to create a module object. There is usually only one statically initialized variable of this type for each module.

#### PyModuleDef\_Base m\_base

Always initialize this member to PyModuleDef\_HEAD\_INIT.

#### const char \*m\_name

Name for the new module.

#### const char \*m\_doc

Docstring for the module; usually a docstring variable created with PyDoc\_STRVAR() is used.

## $Py_ssize_t m_size$

Module state may be kept in a per-module memory area that can be retrieved with <code>PyModule\_GetState()</code>, rather than in static globals. This makes modules safe for use in multiple sub-interpreters.

This memory area is allocated based on  $m\_size$  on module creation, and freed when the module object is deallocated, after the  $m\_free$  function has been called, if present.

Setting m\_size to -1 means that the module does not support sub-interpreters, because it has global state.

Setting it to a non-negative value means that the module can be re-initialized and specifies the additional amount of memory it requires for its state. Non-negative m\_size is required for multi-phase initialization.

See PEP 3121 for more details.

#### PyMethodDef\* m methods

A pointer to a table of module-level functions, described by PyMethodDef values. Can be NULL if no functions are present.

#### PyModuleDef Slot\* m slots

An array of slot definitions for multi-phase initialization, terminated by a  $\{0, NULL\}$  entry. When using single-phase initialization,  $m\_slots$  must be NULL.

Changed in version 3.5: Prior to version 3.5, this member was always set to NULL, and was defined as:

inquiry m\_reload

#### traverseproc m\_traverse

A traversal function to call during GC traversal of the module object, or NULL if not needed. This function may be called before module state is allocated ( $PyModule\_GetState()$ ) may return NULL), and before the  $Py\_mod\_exec$  function is executed.

#### inquiry m\_clear

A clear function to call during GC clearing of the module object, or *NULL* if not needed. This function may be called before module state is allocated (*PyModule\_GetState()* may return *NULL*), and before the *Py\_mod\_exec* function is executed.

## freefunc m\_ free

A function to call during deallocation of the module object, or *NULL* if not needed. This function may be called before module state is allocated (*PyModule\_GetState()* may return *NULL*), and before the *Py\_mod\_exec* function is executed.

#### Single-phase initialization

The module initialization function may create and return the module object directly. This is referred to as "single-phase initialization", and uses one of the following two module creation functions:

#### PyObject\* PyModule Create (PyModuleDef \*def)

*Return value: New reference.* Create a new module object, given the definition in *def*. This behaves like *PyModule\_Create2()* with *module\_api\_version* set to PYTHON\_API\_VERSION.

## PyObject\* PyModule\_Create2 (PyModuleDef \*def, int module\_api\_version)

*Return value: New reference.* Create a new module object, given the definition in *def*, assuming the API version *module\_api\_version.* If that version does not match the version of the running interpreter, a RuntimeWarning is emitted.

**Note:** Most uses of this function should be using <code>PyModule\_Create()</code> instead; only use this if you are sure you need it.

Before it is returned from in the initialization function, the resulting module object is typically populated using functions like  $PyModule\_AddObject()$ .

## Multi-phase initialization

An alternate way to specify extensions is to request "multi-phase initialization". Extension modules created this way behave more like Python modules: the initialization is split between the *creation phase*, when the module object is created, and

the *execution phase*, when it is populated. The distinction is similar to the \_\_new\_\_() and \_\_init\_\_() methods of classes.

Unlike modules created using single-phase initialization, these modules are not singletons: if the *sys.modules* entry is removed and the module is re-imported, a new module object is created, and the old module is subject to normal garbage collection – as with Python modules. By default, multiple modules created from the same definition should be independent: changes to one should not affect the others. This means that all state should be specific to the module object (using e.g. using *PyModule\_GetState()*), or its contents (such as the module's \_\_dict\_\_ or individual classes created with *PyType\_FromSpec()*).

All modules created using multi-phase initialization are expected to support *sub-interpreters*. Making sure multiple modules are independent is typically enough to achieve this.

To request multi-phase initialization, the initialization function (PyInit\_modulename) returns a PyModuleDef instance with non-empty  $m\_slots$ . Before it is returned, the PyModuleDef instance must be initialized with the following function:

```
PyObject* PyModuleDef_Init (PyModuleDef *def)
```

*Return value: Borrowed reference.* Ensures a module definition is a properly initialized Python object that correctly reports its type and reference count.

Returns *def* cast to PyObject\*, or *NULL* if an error occurred.

New in version 3.5.

The *m\_slots* member of the module definition must point to an array of PyModuleDef\_Slot structures:

#### PyModuleDef\_Slot

#### int slot

A slot ID, chosen from the available values explained below.

#### void\* value

Value of the slot, whose meaning depends on the slot ID.

New in version 3.5.

The  $m\_slots$  array must be terminated by a slot with id 0.

The available slot types are:

## Py\_mod\_create

Specifies a function that is called to create the module object itself. The *value* pointer of this slot must point to a function of the signature:

```
PyObject* create_module (PyObject *spec, PyModuleDef *def)
```

The function receives a ModuleSpec instance, as defined in **PEP 451**, and the module definition. It should return a new module object, or set an error and return *NULL*.

This function should be kept minimal. In particular, it should not call arbitrary Python code, as trying to import the same module again may result in an infinite loop.

Multiple Py\_mod\_create slots may not be specified in one module definition.

If  $Py_{mod_create}$  is not specified, the import machinery will create a normal module object using  $Py_{module_New()}$ . The name is taken from spec, not the definition, to allow extension modules to dynamically adjust to their place in the module hierarchy and be imported under different names through symlinks, all while sharing a single module definition.

There is no requirement for the returned object to be an instance of <code>PyModule\_Type</code>. Any type can be used, as long as it supports setting and getting import-related attributes. However, only <code>PyModule\_Type</code> instances may

be returned if the PyModuleDef has non-NULL m\_traverse, m\_clear, m\_free; non-zero m\_size; or slots other than Py\_mod\_create.

#### Py\_mod\_exec

Specifies a function that is called to *execute* the module. This is equivalent to executing the code of a Python module: typically, this function adds classes and constants to the module. The signature of the function is:

```
int exec module (PyObject* module)
```

If multiple Py mod exec slots are specified, they are processed in the order they appear in the m slots array.

See PEP 489 for more details on multi-phase initialization.

#### Low-level module creation functions

The following functions are called under the hood when using multi-phase initialization. They can be used directly, for example when creating module objects dynamically. Note that both PyModule\_FromDefAndSpec and PyModule\_ExecDef must be called to fully initialize a module.

#### PyObject \* PyModule\_FromDefAndSpec (PyModuleDef \*def, PyObject \*spec)

Return value: New reference. Create a new module object, given the definition in module and the ModuleSpec spec. This behaves like PyModule\_FromDefAndSpec2() with module\_api\_version set to PYTHON\_API\_VERSION.

New in version 3.5.

## PyObject \* PyModule\_FromDefAndSpec2 (PyModuleDef \*def, PyObject \*spec, int module\_api\_version)

Return value: New reference. Create a new module object, given the definition in module and the ModuleSpec spec, assuming the API version module\_api\_version. If that version does not match the version of the running interpreter, a RuntimeWarning is emitted.

**Note:** Most uses of this function should be using <code>PyModule\_FromDefAndSpec()</code> instead; only use this if you are sure you need it.

New in version 3.5.

#### int PyModule ExecDef (PyObject \*module, PyModuleDef \*def)

Process any execution slots (Py\_mod\_exec) given in def.

New in version 3.5.

## int PyModule\_SetDocString (PyObject \*module, const char \*docstring)

Set the docstring for *module* to *docstring*. This function is called automatically when creating a module from PyModuleDef, using either PyModule\_Create or PyModule\_FromDefAndSpec.

New in version 3.5.

#### int PyModule\_AddFunctions (PyObject \*module, PyMethodDef \*functions)

Add the functions from the *NULL* terminated *functions* array to *module*. Refer to the *PyMethodDef* documentation for details on individual entries (due to the lack of a shared module namespace, module level "functions" implemented in C typically receive the module as their first parameter, making them similar to instance methods on Python classes). This function is called automatically when creating a module from PyModuleDef, using either PyModule\_Create or PyModule\_FromDefAndSpec.

New in version 3.5.

## **Support functions**

The module initialization function (if using single phase initialization) or a function called from a module execution slot (if using multi-phase initialization), can use the following functions to help initialize the module state:

```
int PyModule_AddObject (PyObject *module, const char *name, PyObject *value)
```

Add an object to *module* as *name*. This is a convenience function which can be used from the module's initialization function. This steals a reference to *value* on success. Return -1 on error, 0 on success.

**Note:** Unlike other functions that steal references, PyModule\_AddObject () only decrements the reference count of *value* on success.

This means that its return value must be checked, and calling code must  $Py\_DECREF$  () value manually on error. Example usage:

```
Py_INCREF(spam);
if (PyModule_AddObject(module, "spam", spam) < 0) {
    Py_DECREF(module);
    Py_DECREF(spam);
    return NULL;
}</pre>
```

#### int PyModule\_AddIntConstant (PyObject \*module, const char \*name, long value)

Add an integer constant to *module* as *name*. This convenience function can be used from the module's initialization function. Return -1 on error, 0 on success.

```
int PyModule_AddStringConstant (PyObject *module, const char *name, const char *value)
```

Add a string constant to *module* as *name*. This convenience function can be used from the module's initialization function. The string *value* must be *NULL*-terminated. Return -1 on error, 0 on success.

```
int PyModule_AddIntMacro (PyObject *module, macro)
```

Add an int constant to *module*. The name and the value are taken from *macro*. For example  $PyModule\_AddIntMacro(module, AF_INET)$  adds the int constant  $AF\_INET$  with the value of  $AF\_INET$  to *module*. Return -1 on error, 0 on success.

```
int PyModule AddStringMacro (PyObject *module, macro)
```

Add a string constant to module.

## Module lookup

Single-phase initialization creates singleton modules that can be looked up in the context of the current interpreter. This allows the module object to be retrieved later with only a reference to the module definition.

These functions will not work on modules created using multi-phase initialization, since multiple such modules can be created from a single definition.

```
PyObject* PyState_FindModule (PyModuleDef *def)
```

Return value: Borrowed reference. Returns the module object that was created from def for the current interpreter. This method requires that the module object has been attached to the interpreter state with  $PyState\_AddModule()$  beforehand. In case the corresponding module object is not found or has not been attached to the interpreter state yet, it returns NULL.

```
int PyState_AddModule (PyObject *module, PyModuleDef *def)
```

Attaches the module object passed to the function to the interpreter state. This allows the module object to be accessible via <code>PyState\_FindModule()</code>.

Only effective on modules created using single-phase initialization.

New in version 3.3.

#### int PyState RemoveModule (PyModuleDef \*def)

Removes the module object created from def from the interpreter state.

New in version 3.3.

## 8.6.3 Iterator Objects

Python provides two general-purpose iterator objects. The first, a sequence iterator, works with an arbitrary sequence supporting the <u>\_\_getitem\_\_()</u> method. The second works with a callable object and a sentinel value, calling the callable for each item in the sequence, and ending the iteration when the sentinel value is returned.

#### PyTypeObject PySeqIter\_Type

Type object for iterator objects returned by  $PySeqIter_New()$  and the one-argument form of the iter() built-in function for built-in sequence types.

## int PySeqIter\_Check (op)

Return true if the type of *op* is *PySeqIter\_Type*.

```
PyObject* PySeqIter_New (PyObject *seq)
```

*Return value: New reference.* Return an iterator that works with a general sequence object, *seq.* The iteration ends when the sequence raises IndexError for the subscripting operation.

## PyTypeObject PyCallIter\_Type

Type object for iterator objects returned by  $PyCallIter_New()$  and the two-argument form of the iter() built-in function.

#### int PyCallIter\_Check (op)

Return true if the type of *op* is *PyCallIter\_Type*.

```
PyObject* PyCallIter_New (PyObject *callable, PyObject *sentinel)
```

*Return value: New reference.* Return a new iterator. The first parameter, *callable*, can be any Python callable object that can be called with no parameters; each call to it should return the next item in the iteration. When *callable* returns a value equal to *sentinel*, the iteration will be terminated.

## 8.6.4 Descriptor Objects

"Descriptors" are objects that describe some attribute of an object. They are found in the dictionary of type objects.

#### PyTypeObject PyProperty\_Type

The type object for the built-in descriptor types.

```
PyObject* PyDescr_NewGetSet (PyTypeObject *type, struct PyGetSetDef *getset)
```

Return value: New reference.

```
PyObject* PyDescr NewMember (PyTypeObject *type, struct PyMemberDef *meth)
```

Return value: New reference.

```
PyObject* PyDescr_NewMethod (PyTypeObject *type, struct PyMethodDef *meth)
```

Return value: New reference.

```
PyObject* PyDescr_NewWrapper (PyTypeObject *type, struct wrapperbase *wrapper, void *wrapped)
```

Return value: New reference.

```
PyObject * \texttt{PyDescr\_NewClassMethod} (PyTypeObject * type, PyMethodDef * method) \\
```

Return value: New reference.

```
int PyDescr_IsData (PyObject *descr)
```

Return true if the descriptor objects *descr* describes a data attribute, or false if it describes a method. *descr* must be a descriptor object; there is no error checking.

```
PyObject* PyWrapper_New (PyObject *, PyObject *)
```

Return value: New reference.

## 8.6.5 Slice Objects

```
PyTypeObject PySlice_Type
```

The type object for slice objects. This is the same as slice in the Python layer.

```
int PySlice_Check (PyObject *ob)
```

Return true if ob is a slice object; ob must not be NULL.

```
PyObject* PySlice_New (PyObject *start, PyObject *stop, PyObject *step)
```

*Return value: New reference.* Return a new slice object with the given values. The *start*, *stop*, and *step* parameters are used as the values of the slice object attributes of the same names. Any of the values may be *NULL*, in which case the None will be used for the corresponding attribute. Return *NULL* if the new object could not be allocated.

```
int PySlice_GetIndices (PyObject *slice, Py_ssize_t length, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t *step)
```

Retrieve the start, stop and step indices from the slice object *slice*, assuming a sequence of length *length*. Treats indices greater than *length* as errors.

Returns 0 on success and -1 on error with no exception set (unless one of the indices was not None and failed to be converted to an integer, in which case -1 is returned with an exception set).

You probably do not want to use this function.

Changed in version 3.2: The parameter type for the *slice* parameter was PySliceObject\* before.

```
int PySlice_GetIndicesEx (PyObject *slice, Py_ssize_t length, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t *step, Py_ssize_t *slicelength)
```

Usable replacement for PySlice\_GetIndices(). Retrieve the start, stop, and step indices from the slice object *slice* assuming a sequence of length *length*, and store the length of the slice in *slicelength*. Out of bounds indices are clipped in a manner consistent with the handling of normal slices.

Returns 0 on success and -1 on error with exception set.

**Note:** This function is considered not safe for resizable sequences. Its invocation should be replaced by a combination of *PySlice\_Unpack()* and *PySlice\_AdjustIndices()* where

```
if (PySlice_GetIndicesEx(slice, length, &start, &stop, &step, &slicelength) < 0) {
    // return error
}</pre>
```

is replaced by

```
if (PySlice_Unpack(slice, &start, &stop, &step) < 0) {
    // return error
}
slicelength = PySlice_AdjustIndices(length, &start, &stop, step);</pre>
```

Changed in version 3.2: The parameter type for the *slice* parameter was PySliceObject\* before.

Changed in version 3.6.1: If Py\_LIMITED\_API is not set or set to the value between 0x03050400 and 0x03060000 (not including) or 0x03060100 or higher PySlice\_GetIndicesEx () is implemented as a

macro using PySlice\_Unpack() and PySlice\_AdjustIndices(). Arguments start, stop and step are evaluated more than once.

Deprecated since version 3.6.1: If Py\_LIMITED\_API is set to the value less than 0x03050400 or between 0x03060000 and 0x03060100 (not including) PySlice\_GetIndicesEx() is a deprecated function.

## int PySlice\_Unpack (PyObject \*slice, Py\_ssize\_t \*start, Py\_ssize\_t \*stop, Py\_ssize\_t \*step)

Extract the start, stop and step data members from a slice object as C integers. Silently reduce values larger than PY\_SSIZE\_T\_MAX to PY\_SSIZE\_T\_MAX, silently boost the start and stop values less than PY\_SSIZE\_T\_MIN to PY\_SSIZE\_T\_MIN, and silently boost the step values less than -PY\_SSIZE\_T\_MAX to -PY\_SSIZE\_T\_MAX.

Return -1 on error, 0 on success.

New in version 3.6.1.

# Py\_ssize\_t PySlice\_AdjustIndices (Py\_ssize\_t length, Py\_ssize\_t \*start, Py\_ssize\_t \*stop, Py\_ssize\_t step)

Adjust start/end slice indices assuming a sequence of the specified length. Out of bounds indices are clipped in a manner consistent with the handling of normal slices.

Return the length of the slice. Always successful. Doesn't call Python code.

New in version 3.6.1.

## 8.6.6 Ellipsis Object

## PyObject \*Py\_Ellipsis

The Python Ellipsis object. This object has no methods. It needs to be treated just like any other object with respect to reference counts. Like Py\_None it is a singleton object.

## 8.6.7 MemoryView objects

A memoryview object exposes the C level *buffer interface* as a Python object which can then be passed around like any other object.

#### PyObject \*PyMemoryView\_FromObject (PyObject \*obj)

Return value: New reference. Create a memoryview object from an object that provides the buffer interface. If obj supports writable buffer exports, the memoryview object will be read/write, otherwise it may be either read-only or read/write at the discretion of the exporter.

#### PyObject \*PyMemoryView\_FromMemory (char \*mem, Py\_ssize\_t size, int flags)

*Return value: New reference.* Create a memoryview object using *mem* as the underlying buffer. *flags* can be one of PyBUF\_READ or PyBUF\_WRITE.

New in version 3.3.

## PyObject \*PyMemoryView\_FromBuffer (Py\_buffer \*view)

*Return value: New reference.* Create a memoryview object wrapping the given buffer structure *view*. For simple byte buffers, <code>PyMemoryView\_FromMemory()</code> is the preferred function.

#### PyObject \*PyMemoryView\_GetContiguous (PyObject \*obj, int buffertype, char order)

*Return value: New reference.* Create a memoryview object to a *contiguous* chunk of memory (in either 'C' or 'F'ortran *order*) from an object that defines the buffer interface. If memory is contiguous, the memoryview object points to the original memory. Otherwise, a copy is made and the memoryview points to a new bytes object.

## int PyMemoryView\_Check (PyObject \*obj)

Return true if the object *obj* is a memoryview object. It is not currently allowed to create subclasses of memoryview.

#### Py\_buffer \*PyMemoryView\_GET\_BUFFER (PyObject \*mview)

Return a pointer to the memoryview's private copy of the exporter's buffer. *mview* **must** be a memoryview instance; this macro doesn't check its type, you must do it yourself or you will risk crashes.

#### Py\_buffer \*PyMemoryView\_GET\_BASE (PyObject \*mview)

Return either a pointer to the exporting object that the memoryview is based on or *NULL* if the memoryview has been created by one of the functions <code>PyMemoryView\_FromMemory()</code> or <code>PyMemoryView\_FromBuffer()</code>. <code>mview must</code> be a memoryview instance.

## 8.6.8 Weak Reference Objects

Python supports *weak references* as first-class objects. There are two specific object types which directly implement weak references. The first is a simple reference object, and the second acts as a proxy for the original object as much as it can.

#### int PyWeakref\_Check (ob)

Return true if ob is either a reference or proxy object.

#### int PyWeakref\_CheckRef (ob)

Return true if *ob* is a reference object.

#### int PyWeakref\_CheckProxy (ob)

Return true if *ob* is a proxy object.

## PyObject\* PyWeakref\_NewRef (PyObject \*ob, PyObject \*callback)

Return value: New reference. Return a weak reference object for the object ob. This will always return a new reference, but is not guaranteed to create a new object; an existing reference object may be returned. The second parameter, callback, can be a callable object that receives notification when ob is garbage collected; it should accept a single parameter, which will be the weak reference object itself. callback may also be None or NULL. If ob is not a weakly-referencable object, or if callback is not callable, None, or NULL, this will return NULL and raise TypeError.

#### PyObject\* PyWeakref\_NewProxy (PyObject \*ob, PyObject \*callback)

Return value: New reference. Return a weak reference proxy object for the object ob. This will always return a new reference, but is not guaranteed to create a new object; an existing proxy object may be returned. The second parameter, callback, can be a callable object that receives notification when ob is garbage collected; it should accept a single parameter, which will be the weak reference object itself. callback may also be None or NULL. If ob is not a weakly-referencable object, or if callback is not callable, None, or NULL, this will return NULL and raise TypeError.

#### PvObject\* PvWeakref GetObject (PvObject \*ref)

*Return value: Borrowed reference.* Return the referenced object from a weak reference, *ref.* If the referent is no longer live, returns Py\_None.

**Note:** This function returns a **borrowed reference** to the referenced object. This means that you should always call  $Py\_INCREF()$  on the object except if you know that it cannot be destroyed while you are still using it.

#### PyObject\* PyWeakref\_GET\_OBJECT (PyObject \*ref)

*Return value: Borrowed reference.* Similar to PyWeakref\_GetObject(), but implemented as a macro that does no error checking.

#### 8.6.9 Capsules

Refer to using-capsules for more information on using these objects.

New in version 3.1.

#### PyCapsule

This subtype of *PyObject* represents an opaque value, useful for C extension modules who need to pass an opaque value (as a void\* pointer) through Python code to other C code. It is often used to make a C function pointer defined in one module available to other modules, so the regular import mechanism can be used to access C APIs defined in dynamically loaded modules.

#### PyCapsule\_Destructor

The type of a destructor callback for a capsule. Defined as:

```
typedef void (*PyCapsule_Destructor) (PyObject *);
```

See PyCapsule\_New() for the semantics of PyCapsule\_Destructor callbacks.

## int PyCapsule\_CheckExact (PyObject \*p)

Return true if its argument is a *PyCapsule*.

#### PyObject\* PyCapsule\_New (void \*pointer, const char \*name, PyCapsule\_Destructor destructor)

Return value: New reference. Create a PyCapsule encapsulating the pointer. The pointer argument may not be NULL.

On failure, set an exception and return NULL.

The *name* string may either be *NULL* or a pointer to a valid C string. If non-*NULL*, this string must outlive the capsule. (Though it is permitted to free it inside the *destructor*.)

If the destructor argument is not NULL, it will be called with the capsule as its argument when it is destroyed.

If this capsule will be stored as an attribute of a module, the *name* should be specified as modulename. attributename. This will enable other modules to import the capsule using <code>PyCapsule\_Import()</code>.

#### void\* PyCapsule\_GetPointer (PyObject \*capsule, const char \*name)

Retrieve the *pointer* stored in the capsule. On failure, set an exception and return *NULL*.

The *name* parameter must compare exactly to the name stored in the capsule. If the name stored in the capsule is *NULL*, the *name* passed in must also be *NULL*. Python uses the C function strcmp() to compare capsule names.

#### PyCapsule\_Destructor PyCapsule\_GetDestructor (PyObject \*capsule)

Return the current destructor stored in the capsule. On failure, set an exception and return NULL.

It is legal for a capsule to have a *NULL* destructor. This makes a *NULL* return code somewhat ambiguous; use *PyCapsule\_IsValid()* or *PyErr\_Occurred()* to disambiguate.

## void\* PyCapsule\_GetContext (PyObject \*capsule)

Return the current context stored in the capsule. On failure, set an exception and return NULL.

It is legal for a capsule to have a *NULL* context. This makes a *NULL* return code somewhat ambiguous; use *PyCapsule\_IsValid()* or *PyErr\_Occurred()* to disambiguate.

## const char\* PyCapsule\_GetName (PyObject \*capsule)

Return the current name stored in the capsule. On failure, set an exception and return NULL.

It is legal for a capsule to have a *NULL* name. This makes a *NULL* return code somewhat ambiguous; use *PyCapsule\_IsValid()* or *PyErr\_Occurred()* to disambiguate.

#### void\* PyCapsule\_Import (const char \*name, int no\_block)

Import a pointer to a C object from a capsule attribute in a module. The *name* parameter should specify the full name to the attribute, as in module.attribute. The *name* stored in the capsule must match this string exactly. If *no\_block* is true, import the module without blocking (using PyImport\_ImportModuleNoBlock()). If no\_block is false, import the module conventionally (using PyImport\_ImportModule()).

Return the capsule's internal pointer on success. On failure, set an exception and return NULL.

#### int **PyCapsule IsValid** (*PyObject \*capsule*, const char \*name)

Determines whether or not *capsule* is a valid capsule. A valid capsule is non-*NULL*, passes  $PyCapsule\_CheckExact()$ , has a non-*NULL* pointer stored in it, and its internal name matches the *name* parameter. (See  $PyCapsule\_GetPointer()$ ) for information on how capsule names are compared.)

In other words, if PyCapsule\_IsValid() returns a true value, calls to any of the accessors (any function starting with PyCapsule\_Get()) are guaranteed to succeed.

Return a nonzero value if the object is valid and matches the name passed in. Return 0 otherwise. This function will not fail.

#### int PyCapsule\_SetContext (PyObject \*capsule, void \*context)

Set the context pointer inside capsule to context.

Return 0 on success. Return nonzero and set an exception on failure.

#### int PyCapsule\_SetDestructor (PyObject \*capsule, PyCapsule\_Destructor destructor)

Set the destructor inside *capsule* to *destructor*.

Return 0 on success. Return nonzero and set an exception on failure.

#### int PyCapsule SetName (PyObject \*capsule, const char \*name)

Set the name inside *capsule* to *name*. If non-*NULL*, the name must outlive the capsule. If the previous *name* stored in the capsule was not *NULL*, no attempt is made to free it.

Return 0 on success. Return nonzero and set an exception on failure.

#### int PyCapsule\_SetPointer (PyObject \*capsule, void \*pointer)

Set the void pointer inside *capsule* to *pointer*. The pointer may not be *NULL*.

Return 0 on success. Return nonzero and set an exception on failure.

## 8.6.10 Generator Objects

Generator objects are what Python uses to implement generator iterators. They are normally created by iterating over a function that yields values, rather than explicitly calling PyGen\_New() or PyGen\_NewWithQualName().

#### PyGenObject

The C structure used for generator objects.

## PyTypeObject PyGen\_Type

The type object corresponding to generator objects.

#### int PyGen\_Check (PyObject \*ob)

Return true if ob is a generator object; ob must not be NULL.

#### int PyGen\_CheckExact (PyObject \*ob)

Return true if *ob*'s type is *PyGen\_Type*; *ob* must not be *NULL*.

## PyObject\* PyGen\_New (PyFrameObject \*frame)

*Return value: New reference.* Create and return a new generator object based on the *frame* object. A reference to *frame* is stolen by this function. The argument must not be *NULL*.

#### PyObject \* PyGen\_NewWithQualName (PyFrameObject \*frame, PyObject \*name, PyObject \*qualname)

Return value: New reference. Create and return a new generator object based on the frame object, with \_\_name\_\_ and \_\_qualname\_\_ set to name and qualname. A reference to frame is stolen by this function. The frame argument must not be NULL.

## 8.6.11 Coroutine Objects

New in version 3.5.

Coroutine objects are what functions declared with an async keyword return.

#### PyCoroObject

The C structure used for coroutine objects.

#### PyTypeObject PyCoro\_Type

The type object corresponding to coroutine objects.

```
int PyCoro_CheckExact (PyObject *ob)
```

Return true if *ob*'s type is *PyCoro\_Type*; *ob* must not be *NULL*.

```
PyObject* PyCoro_New (PyFrameObject *frame, PyObject *name, PyObject *qualname)
```

Return value: New reference. Create and return a new coroutine object based on the frame object, with \_\_name\_\_ and \_\_qualname\_\_ set to name and qualname. A reference to frame is stolen by this function. The frame argument must not be NULL.

## 8.6.12 Context Variables Objects

**Note:** Changed in version 3.7.1: In Python 3.7.1 the signatures of all context variables C APIs were **changed** to use *PyObject* pointers instead of *PyContext*, *PyContextVar*, and *PyContextToken*, e.g.:

```
// in 3.7.0:
PyContext *PyContext_New(void);

// in 3.7.1+:
PyObject *PyContext_New(void);
```

See bpo-34762 for more details.

New in version 3.7.

This section details the public C API for the contextvars module.

#### **PvContext**

The C structure used to represent a contextvars. Context object.

#### PyContextVar

The C structure used to represent a contextvars. ContextVar object.

#### PyContextToken

The C structure used to represent a contextvars. Token object.

## PyTypeObject PyContext\_Type

The type object representing the *context* type.

## PyTypeObject PyContextVar\_Type

The type object representing the *context variable* type.

#### PyTypeObject PyContextToken\_Type

The type object representing the *context variable token* type.

Type-check macros:

```
int PyContext_CheckExact (PyObject *o)
```

Return true if o is of type PyContext\_Type. o must not be NULL. This function always succeeds.

#### int PyContextVar\_CheckExact (PyObject \*o)

Return true if o is of type PyContextVar\_Type. o must not be NULL. This function always succeeds.

#### int PyContextToken\_CheckExact (PyObject \*o)

Return true if o is of type  $PyContextToken\_Type$ . o must not be NULL. This function always succeeds.

Context object management functions:

#### PyObject \*PyContext\_New (void)

Return value: New reference. Create a new empty context object. Returns NULL if an error has occurred.

#### PyObject \*PyContext\_Copy (PyObject \*ctx)

*Return value: New reference.* Create a shallow copy of the passed *ctx* context object. Returns NULL if an error has occurred.

## PyObject \*PyContext\_CopyCurrent (void)

*Return value: New reference.* Create a shallow copy of the current thread context. Returns NULL if an error has occurred.

#### int PyContext\_Enter (PyObject \*ctx)

Set *ctx* as the current context for the current thread. Returns 0 on success, and -1 on error.

#### int PyContext\_Exit (PyObject \*ctx)

Deactivate the *ctx* context and restore the previous context as the current context for the current thread. Returns 0 on success, and -1 on error.

#### int PyContext\_ClearFreeList()

Clear the context variable free list. Return the total number of freed items. This function always succeeds.

Context variable functions:

#### PyObject \*PyContextVar\_New (const char \*name, PyObject \*def)

*Return value: New reference.* Create a new ContextVar object. The *name* parameter is used for introspection and debug purposes. The *def* parameter may optionally specify the default value for the context variable. If an error has occurred, this function returns NULL.

#### int PyContextVar\_Get (PyObject \*var, PyObject \*default\_value, PyObject \*\*value)

Get the value of a context variable. Returns -1 if an error has occurred during lookup, and 0 if no error occurred, whether or not a value was found.

If the context variable was found, *value* will be a pointer to it. If the context variable was *not* found, *value* will point to:

- *default\_value*, if not NULL;
- the default value of *var*, if not NULL;
- NULL

If the value was found, the function will create a new reference to it.

## PyObject \*PyContextVar\_Set (PyObject \*var, PyObject \*value)

*Return value: New reference.* Set the value of *var* to *value* in the current context. Returns a pointer to a *PyObject* object, or NULL if an error has occurred.

#### int PyContextVar\_Reset (PyObject \*var, PyObject \*token)

Reset the state of the *var* context variable to that it was in before *PyContextVar\_Set* () that returned the *token* was called. This function returns 0 on success and -1 on error.

## 8.6.13 DateTime Objects

Various date and time objects are supplied by the datetime module. Before using any of these functions, the header file datetime.h must be included in your source (note that this is not included by Python.h), and the macro PyDateTime\_IMPORT must be invoked, usually as part of the module initialisation function. The macro puts a pointer to a C structure into a static variable, PyDateTimeAPI, that is used by the following macros.

Macro for access to the UTC singleton:

#### PyObject\* PyDateTime\_TimeZone\_UTC

Returns the time zone singleton representing UTC, the same object as datetime.timezone.utc.

New in version 3.7.

Type-check macros:

## int PyDate\_Check (PyObject \*ob)

Return true if ob is of type PyDateTime\_DateType or a subtype of PyDateTime\_DateType. ob must not be NULL.

#### int PyDate\_CheckExact (PyObject \*ob)

Return true if ob is of type PyDateTime\_DateType. ob must not be NULL.

#### int PyDateTime\_Check (PyObject \*ob)

Return true if ob is of type PyDateTime\_DateTimeType or a subtype of PyDateTime\_DateTimeType. ob must not be NULL.

#### int PyDateTime CheckExact (PyObject \*ob)

Return true if ob is of type PyDateTime\_DateTimeType. ob must not be NULL.

#### int PyTime\_Check (PyObject \*ob)

Return true if ob is of type PyDateTime\_TimeType or a subtype of PyDateTime\_TimeType. ob must not be NULL.

#### int PyTime\_CheckExact (PyObject \*ob)

Return true if ob is of type PyDateTime\_TimeType. ob must not be NULL.

#### int PyDelta\_Check (PyObject \*ob)

Return true if ob is of type PyDateTime\_DeltaType or a subtype of PyDateTime\_DeltaType. ob must not be NULL.

#### int PyDelta\_CheckExact (PyObject \*ob)

Return true if *ob* is of type PyDateTime\_DeltaType. *ob* must not be *NULL*.

## int PyTZInfo\_Check (PyObject \*ob)

Return true if ob is of type PyDateTime\_TZInfoType or a subtype of PyDateTime\_TZInfoType. ob must not be NULL.

#### int PyTZInfo CheckExact (PyObject \*ob)

Return true if *ob* is of type PyDateTime\_TZInfoType. *ob* must not be *NULL*.

Macros to create objects:

## PyObject\* PyDate\_FromDate (int year, int month, int day)

Return value: New reference. Return a datetime. date object with the specified year, month and day.

# PyObject\* PyDateTime\_FromDateAndTime (int year, int month, int day, int hour, int minute, int second, int usecond)

Return value: New reference. Return a datetime datetime object with the specified year, month, day, hour, minute, second and microsecond.

# PyObject\* PyDateTime\_FromDateAndTimeAndFold (int year, int month, int day, int hour, int minute, int second, int usecond, int fold)

Return value: New reference. Return a datetime.datetime object with the specified year, month, day, hour, minute, second, microsecond and fold.

New in version 3.6.

## PyObject\* PyTime\_FromTime (int hour, int minute, int second, int usecond)

Return value: New reference. Return a datetime.time object with the specified hour, minute, second and microsecond.

#### PyObject\* PyTime FromTimeAndFold (int hour, int minute, int second, int usecond, int fold)

Return value: New reference. Return a datetime.time object with the specified hour, minute, second, microsecond and fold.

New in version 3.6.

#### PyObject\* PyDelta\_FromDSU (int days, int seconds, int useconds)

Return value: New reference. Return a datetime.timedelta object representing the given number of days, seconds and microseconds. Normalization is performed so that the resulting number of microseconds and seconds lie in the ranges documented for datetime.timedelta objects.

#### PyObject\* PyTimeZone\_FromOffset (PyDateTime\_DeltaType\* offset)

Return value: New reference. Return a datetime.timezone object with an unnamed fixed offset represented by the offset argument.

New in version 3.7.

#### PyObject\* PyTimeZone\_FromOffsetAndName (PyDateTime\_DeltaType\* offset, PyUnicode\* name)

*Return value: New reference.* Return a datetime.timezone object with a fixed offset represented by the *offset* argument and with tzname *name*.

New in version 3.7.

Macros to extract fields from date objects. The argument must be an instance of PyDateTime\_Date, including subclasses (such as PyDateTime\_DateTime). The argument must not be *NULL*, and the type is not checked:

#### int PyDateTime\_GET\_YEAR (PyDateTime\_Date \*o)

Return the year, as a positive int.

#### int PyDateTime\_GET\_MONTH (PyDateTime\_Date \*o)

Return the month, as an int from 1 through 12.

#### int PyDateTime\_GET\_DAY (PyDateTime\_Date \*o)

Return the day, as an int from 1 through 31.

Macros to extract fields from datetime objects. The argument must be an instance of PyDateTime\_DateTime, including subclasses. The argument must not be *NULL*, and the type is not checked:

#### int PyDateTime\_DATE\_GET\_HOUR (PyDateTime\_DateTime \*o)

Return the hour, as an int from 0 through 23.

#### int PyDateTime\_DATE\_GET\_MINUTE (PyDateTime\_DateTime \*o)

Return the minute, as an int from 0 through 59.

## $int \ \textbf{PyDateTime\_DATE\_GET\_SECOND} \ (PyDateTime\_DateTime \ *o)$

Return the second, as an int from 0 through 59.

#### int PyDateTime DATE GET MICROSECOND (PyDateTime DateTime \*0)

Return the microsecond, as an int from 0 through 999999.

Macros to extract fields from time objects. The argument must be an instance of PyDateTime\_Time, including subclasses. The argument must not be *NULL*, and the type is not checked:

#### int PyDateTime\_TIME\_GET\_HOUR (PyDateTime\_Time \*o)

Return the hour, as an int from 0 through 23.

#### int PyDateTime\_TIME\_GET\_MINUTE (PyDateTime\_Time \*o)

Return the minute, as an int from 0 through 59.

## int PyDateTime\_TIME\_GET\_SECOND (PyDateTime\_Time \*o)

Return the second, as an int from 0 through 59.

#### int PyDateTime\_TIME\_GET\_MICROSECOND (PyDateTime\_Time \*o)

Return the microsecond, as an int from 0 through 999999.

Macros to extract fields from time delta objects. The argument must be an instance of PyDateTime\_Delta, including subclasses. The argument must not be *NULL*, and the type is not checked:

## int PyDateTime\_DELTA\_GET\_DAYS (PyDateTime\_Delta \*o)

Return the number of days, as an int from -999999999 to 999999999.

New in version 3.3.

## int PyDateTime\_DELTA\_GET\_SECONDS (PyDateTime\_Delta \*o)

Return the number of seconds, as an int from 0 through 86399.

New in version 3.3.

## int PyDateTime\_DELTA\_GET\_MICROSECONDS (PyDateTime\_Delta \*o)

Return the number of microseconds, as an int from 0 through 999999.

New in version 3.3.

Macros for the convenience of modules implementing the DB API:

## PyObject\* PyDateTime\_FromTimestamp (PyObject \*args)

Return value: New reference. Create and return a new datetime.datetime object given an argument tuple suitable for passing to datetime.datetime.fromtimestamp().

## PyObject\* PyDate\_FromTimestamp (PyObject \*args)

Return value: New reference. Create and return a new datetime.date object given an argument tuple suitable for passing to datetime.date.fromtimestamp().

## INITIALIZATION, FINALIZATION, AND THREADS

See also Python Initialization Configuration.

# 9.1 Before Python Initialization

In an application embedding Python, the Py\_Initialize() function must be called before using any other Python/C API functions; with the exception of a few functions and the *global configuration variables*.

The following functions can be safely called before Python is initialized:

- Configuration functions:
  - PyImport\_AppendInittab()
  - PyImport\_ExtendInittab()
  - PyInitFrozenExtensions()
  - PyMem\_SetAllocator()
  - PyMem\_SetupDebugHooks()
  - PyObject\_SetArenaAllocator()
  - Py\_SetPath()
  - Py\_SetProgramName()
  - Py\_SetPythonHome()
  - Py\_SetStandardStreamEncoding()
  - PySys\_AddWarnOption()
  - PySys\_AddXOption()
  - PySys\_ResetWarnOptions()
- Informative functions:
  - Py\_IsInitialized()
  - PyMem\_GetAllocator()
  - PyObject\_GetArenaAllocator()
  - Py\_GetBuildInfo()
  - Py\_GetCompiler()
  - Py\_GetCopyright()

- Py\_GetPlatform()
- Py\_GetVersion()
- Utilities:
  - Py\_DecodeLocale()
- Memory allocators:
  - PyMem RawMalloc()
  - PyMem\_RawRealloc()
  - PyMem\_RawCalloc()
  - PyMem\_RawFree()

Note: The following functions should not be called before Py\_Initialize(): Py\_EncodeLocale(), Py\_GetPath(), Py\_GetPrefix(), Py\_GetExecPrefix(), Py\_GetProgramFullPath(), Py\_GetPythonHome(), Py\_GetProgramName() and PyEval\_InitThreads().

## 9.2 Global configuration variables

Python has variables for the global configuration to control different features and options. By default, these flags are controlled by command line options.

When a flag is set by an option, the value of the flag is the number of times that the option was set. For example,  $\neg b$  sets  $Py\_BytesWarningFlag$  to 1 and  $\neg bb$  sets  $Py\_BytesWarningFlag$  to 2.

#### Py\_BytesWarningFlag

Issue a warning when comparing bytes or bytearray with str or bytes with int. Issue an error if greater or equal to 2.

Set by the -b option.

#### Py\_DebugFlag

Turn on parser debugging output (for expert only, depending on compilation options).

Set by the -d option and the PYTHONDEBUG environment variable.

## Py\_DontWriteBytecodeFlag

If set to non-zero, Python won't try to write .pyc files on the import of source modules.

Set by the -B option and the PYTHONDONTWRITEBYTECODE environment variable.

#### Py\_FrozenFlag

Suppress error messages when calculating the module search path in Py\_GetPath().

Private flag used by \_freeze\_importlib and frozenmain programs.

#### Py HashRandomizationFlag

Set to 1 if the PYTHONHASHSEED environment variable is set to a non-empty string.

If the flag is non-zero, read the PYTHONHASHSEED environment variable to initialize the secret hash seed.

#### Py\_IgnoreEnvironmentFlag

Ignore all PYTHON\* environment variables, e.g. PYTHONPATH and PYTHONHOME, that might be set.

Set by the -E and -I options.

### Py\_InspectFlag

When a script is passed as first argument or the -c option is used, enter interactive mode after executing the script or the command, even when sys.stdin does not appear to be a terminal.

Set by the -i option and the PYTHONINSPECT environment variable.

#### Py InteractiveFlag

Set by the -i option.

### Py\_IsolatedFlag

Run Python in isolated mode. In isolated mode sys.path contains neither the script's directory nor the user's site-packages directory.

Set by the -I option.

New in version 3.4.

### Py\_LegacyWindowsFSEncodingFlag

If the flag is non-zero, use the mbcs encoding instead of the UTF-8 encoding for the filesystem encoding.

Set to 1 if the PYTHONLEGACYWINDOWSF SENCODING environment variable is set to a non-empty string.

See PEP 529 for more details.

Availability: Windows.

### Py\_LegacyWindowsStdioFlag

If the flag is non-zero, use io.FileIO instead of WindowsConsoleIO for sys standard streams.

Set to 1 if the PYTHONLEGACYWINDOWSSTDIO environment variable is set to a non-empty string.

See PEP 528 for more details.

Availability: Windows.

### Py\_NoSiteFlag

Disable the import of the module site and the site-dependent manipulations of sys.path that it entails. Also disable these manipulations if site is explicitly imported later (call site.main() if you want them to be triggered).

Set by the -S option.

### Py\_NoUserSiteDirectory

Don't add the user site-packages directory to sys.path.

Set by the  $\neg$ s and  $\neg$ I options, and the PYTHONNOUSERSITE environment variable.

#### Py OptimizeFlag

Set by the -O option and the PYTHONOPTIMIZE environment variable.

#### Py QuietFlag

Don't display the copyright and version messages even in interactive mode.

Set by the -q option.

New in version 3.2.

#### Py UnbufferedStdioFlag

Force the stdout and stderr streams to be unbuffered.

Set by the -u option and the PYTHONUNBUFFERED environment variable.

### Py\_VerboseFlag

Print a message each time a module is initialized, showing the place (filename or built-in module) from which it is loaded. If greater or equal to 2, print a message for each file that is checked for when searching for a module. Also provides information on module cleanup at exit.

Set by the -v option and the PYTHONVERBOSE environment variable.

## 9.3 Initializing and finalizing the interpreter

### void Py\_Initialize()

Initialize the Python interpreter. In an application embedding Python, this should be called before using any other Python/C API functions; see *Before Python Initialization* for the few exceptions.

This initializes the table of loaded modules (sys.modules), and creates the fundamental modules builtins, \_\_main\_\_ and sys. It also initializes the module search path (sys.path). It does not set sys. argv; use PySys\_SetArgvEx() for that. This is a no-op when called for a second time (without calling Py\_FinalizeEx() first). There is no return value; it is a fatal error if the initialization fails.

**Note:** On Windows, changes the console mode from O\_TEXT to O\_BINARY, which will also affect non-Python uses of the console using the C Runtime.

### void Py\_InitializeEx (int initsigs)

This function works like  $Py\_Initialize()$  if *initsigs* is 1. If *initsigs* is 0, it skips initialization registration of signal handlers, which might be useful when Python is embedded.

#### int Py\_IsInitialized()

Return true (nonzero) when the Python interpreter has been initialized, false (zero) if not. After  $Py\_FinalizeEx$  () is called, this returns false until  $Py\_Initialize$  () is called again.

### int Py\_FinalizeEx()

Undo all initializations made by  $Py\_Initialize()$  and subsequent use of Python/C API functions, and destroy all sub-interpreters (see  $Py\_NewInterpreter()$  below) that were created and not yet destroyed since the last call to  $Py\_Initialize()$ . Ideally, this frees all memory allocated by the Python interpreter. This is a no-op when called for a second time (without calling  $Py\_Initialize()$ ) again first). Normally the return value is 0. If there were errors during finalization (flushing buffered data), -1 is returned.

This function is provided for a number of reasons. An embedding application might want to restart Python without having to restart the application itself. An application that has loaded the Python interpreter from a dynamically loadable library (or DLL) might want to free all memory allocated by Python before unloading the DLL. During a hunt for memory leaks in an application a developer might want to free all memory allocated by Python before exiting from the application.

**Bugs and caveats:** The destruction of modules and objects in modules is done in random order; this may cause destructors (\_\_del\_\_() methods) to fail when they depend on other objects (even functions) or modules. Dynamically loaded extension modules loaded by Python are not unloaded. Small amounts of memory allocated by the Python interpreter may not be freed (if you find a leak, please report it). Memory tied up in circular references between objects is not freed. Some memory allocated by extension modules may not be freed. Some extensions may not work properly if their initialization routine is called more than once; this can happen if an application calls Py\_Initialize() and Py\_FinalizeEx() more than once.

Raises an auditing event cpython.\_PySys\_ClearAuditHooks with no arguments.

New in version 3.6.

#### void Py Finalize()

This is a backwards-compatible version of Py FinalizeEx () that disregards the return value.

# 9.4 Process-wide parameters

### int Py\_SetStandardStreamEncoding (const char \*encoding, const char \*errors)

This function should be called before Py\_Initialize(), if it is called at all. It specifies which encoding and error handling to use with standard IO, with the same meanings as in str.encode().

It overrides PYTHONIOENCODING values, and allows embedding code to control IO encoding when the environment variable does not work.

encoding and/or errors may be NULL to use PYTHONIOENCODING and/or default values (depending on other settings).

Note that sys.stderr always uses the "backslashreplace" error handler, regardless of this (or any other) setting.

If  $Py\_FinalizeEx()$  is called, this function will need to be called again in order to affect subsequent calls to  $Py\_Initialize()$ .

Returns 0 if successful, a nonzero value on error (e.g. calling after the interpreter has already been initialized).

New in version 3.4.

### void Py\_SetProgramName (const wchar\_t \*name)

This function should be called before  $Py\_Initialize()$  is called for the first time, if it is called at all. It tells the interpreter the value of the argv[0] argument to the main() function of the program (converted to wide characters). This is used by  $Py\_GetPath()$  and some other functions below to find the Python run-time libraries relative to the interpreter executable. The default value is 'python'. The argument should point to a zero-terminated wide character string in static storage whose contents will not change for the duration of the program's execution. No code in the Python interpreter will change the contents of this storage.

Use Py\_DecodeLocale() to decode a bytes string to get a wchar\_\* string.

### wchar\* Py\_GetProgramName()

Return the program name set with  $Py\_SetProgramName()$ , or the default. The returned string points into static storage; the caller should not modify its value.

### wchar\_t\* Py\_GetPrefix()

Return the *prefix* for installed platform-independent files. This is derived through a number of complicated rules from the program name set with <code>Py\_SetProgramName()</code> and some environment variables; for example, if the program name is '/usr/local/bin/python', the prefix is '/usr/local'. The returned string points into static storage; the caller should not modify its value. This corresponds to the <code>prefix</code> variable in the top-level <code>Makefile</code> and the <code>--prefix</code> argument to the <code>configure</code> script at build time. The value is available to Python code as <code>sys.prefix</code>. It is only useful on Unix. See also the next function.

#### wchar t\* Py GetExecPrefix()

Return the *exec-prefix* for installed platform-*dependent* files. This is derived through a number of complicated rules from the program name set with  $Py\_SetProgramName()$  and some environment variables; for example, if the program name is '/usr/local/bin/python', the exec-prefix is '/usr/local'. The returned string points into static storage; the caller should not modify its value. This corresponds to the **exec\_prefix** variable in the top-level Makefile and the --exec-prefix argument to the **configure** script at build time. The value is available to Python code as sys.exec\_prefix. It is only useful on Unix.

Background: The exec-prefix differs from the prefix when platform dependent files (such as executables and shared libraries) are installed in a different directory tree. In a typical installation, platform dependent files may be installed in the /usr/local/plat subtree while platform independent may be installed in /usr/local.

Generally speaking, a platform is a combination of hardware and software families, e.g. Sparc machines running the Solaris 2.x operating system are considered the same platform, but Intel machines running Solaris 2.x are another platform, and Intel machines running Linux are yet another platform. Different major revisions of the same operating system generally also form different platforms. Non-Unix operating systems are a different story; the installation strategies on those systems are so different that the prefix and exec-prefix are meaningless, and set

to the empty string. Note that compiled Python bytecode files are platform independent (but not independent from the Python version by which they were compiled!).

System administrators will know how to configure the **mount** or **automount** programs to share /usr/local between platforms while having /usr/local/plat be a different filesystem for each platform.

### wchar\_t\* Py\_GetProgramFullPath()

Return the full program name of the Python executable; this is computed as a side-effect of deriving the default module search path from the program name (set by  $Py\_SetProgramName()$  above). The returned string points into static storage; the caller should not modify its value. The value is available to Python code as sys. executable.

### wchar\_t\* Py\_GetPath()

Return the default module search path; this is computed from the program name (set by  $Py\_SetProgramName()$  above) and some environment variables. The returned string consists of a series of directory names separated by a platform dependent delimiter character. The delimiter character is ':' on Unix and Mac OS X, ';' on Windows. The returned string points into static storage; the caller should not modify its value. The list sys.path is initialized with this value on interpreter startup; it can be (and usually is) modified later to change the search path for loading modules.

### void Py\_SetPath (const wchar\_t \*)

Set the default module search path. If this function is called before <code>Py\_Initialize()</code>, then <code>Py\_GetPath()</code> won't attempt to compute a default search path but uses the one provided instead. This is useful if Python is embedded by an application that has full knowledge of the location of all modules. The path components should be separated by the platform dependent delimiter character, which is ':' on Unix and Mac OS X, ';' on Windows.

This also causes sys.executable to be set to the program full path (see  $Py\_GetProgramFullPath()$ ) and for sys.prefix and sys.exec\_prefix to be empty. It is up to the caller to modify these if required after calling  $Py\_Initialize()$ .

Use Py\_DecodeLocale() to decode a bytes string to get a wchar\_\* string.

The path argument is copied internally, so the caller may free it after the call completes.

Changed in version 3.8: The program full path is now used for sys.executable, instead of the program name.

### const char\* Py\_GetVersion()

Return the version of this Python interpreter. This is a string that looks something like

```
"3.0a5+ (py3k:63103M, May 12 2008, 00:53:55) \n[GCC 4.2.3]"
```

The first word (up to the first space character) is the current Python version; the first three characters are the major and minor version separated by a period. The returned string points into static storage; the caller should not modify its value. The value is available to Python code as sys.version.

### const char\* Py\_GetPlatform()

Return the platform identifier for the current platform. On Unix, this is formed from the "official" name of the operating system, converted to lower case, followed by the major revision number; e.g., for Solaris 2.x, which is also known as SunOS 5.x, the value is 'sunos5'. On Mac OS X, it is 'darwin'. On Windows, it is 'win'. The returned string points into static storage; the caller should not modify its value. The value is available to Python code as sys.platform.

### const char\* Py\_GetCopyright()

Return the official copyright string for the current Python version, for example

```
'Copyright 1991-1995 Stichting Mathematisch Centrum, Amsterdam'
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as sys.copyright.

#### const char\* Py\_GetCompiler()

Return an indication of the compiler used to build the current Python version, in square brackets, for example:

```
"[GCC 2.7.2.2]"
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as part of the variable sys.version.

### const char\* Py\_GetBuildInfo()

Return information about the sequence number and build date and time of the current Python interpreter instance, for example

```
"#67, Aug 1 1997, 22:34:28"
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as part of the variable sys.version.

### void PySys\_SetArgvEx (int argc, wchar\_t \*\*argv, int updatepath)

Set sys.argv based on *argc* and *argv*. These parameters are similar to those passed to the program's main() function with the difference that the first entry should refer to the script file to be executed rather than the executable hosting the Python interpreter. If there isn't a script that will be run, the first entry in *argv* can be an empty string. If this function fails to initialize sys.argv, a fatal condition is signalled using <code>Py\_FatalError()</code>.

If *updatepath* is zero, this is all the function does. If *updatepath* is non-zero, the function also modifies sys.path according to the following algorithm:

- If the name of an existing script is passed in argv[0], the absolute path of the directory where the script is located is prepended to sys.path.
- Otherwise (that is, if *argc* is 0 or argv[0] doesn't point to an existing file name), an empty string is prepended to sys.path, which is the same as prepending the current working directory (".").

Use Py\_DecodeLocale() to decode a bytes string to get a wchar\_\* string.

**Note:** It is recommended that applications embedding the Python interpreter for purposes other than executing a single script pass 0 as *updatepath*, and update sys.path themselves if desired. See CVE-2008-5983.

On versions before 3.1.3, you can achieve the same effect by manually popping the first sys.path element after having called PvSys SetArgv(), for example using:

```
PyRun_SimpleString("import sys; sys.path.pop(0)\n");
```

New in version 3.1.3.

### void PySys\_SetArgv (int argc, wchar\_t \*\*argv)

This function works like  $PySys\_SetArgvEx$  () with *updatepath* set to 1 unless the **python** interpreter was started with the -I.

Use Py\_DecodeLocale() to decode a bytes string to get a wchar\_\* string.

Changed in version 3.4: The *updatepath* value depends on -I.

### void Py\_SetPythonHome (const wchar\_t \*home)

Set the default "home" directory, that is, the location of the standard Python libraries. See PYTHONHOME for the meaning of the argument string.

The argument should point to a zero-terminated character string in static storage whose contents will not change for the duration of the program's execution. No code in the Python interpreter will change the contents of this storage.

Use Py\_DecodeLocale() to decode a bytes string to get a wchar\_\* string.

```
w_char* Py_GetPythonHome ()
```

Return the default "home", that is, the value set by a previous call to Py\_SetPythonHome(), or the value of the PYTHONHOME environment variable if it is set.

## 9.5 Thread State and the Global Interpreter Lock

The Python interpreter is not fully thread-safe. In order to support multi-threaded Python programs, there's a global lock, called the *global interpreter lock* or *GIL*, that must be held by the current thread before it can safely access Python objects. Without the lock, even the simplest operations could cause problems in a multi-threaded program: for example, when two threads simultaneously increment the reference count of the same object, the reference count could end up being incremented only once instead of twice.

Therefore, the rule exists that only the thread that has acquired the *GIL* may operate on Python objects or call Python/C API functions. In order to emulate concurrency of execution, the interpreter regularly tries to switch threads (see sys.setswitchinterval()). The lock is also released around potentially blocking I/O operations like reading or writing a file, so that other Python threads can run in the meantime.

The Python interpreter keeps some thread-specific bookkeeping information inside a data structure called <code>PyThreadState</code>. There's also one global variable pointing to the current <code>PyThreadState</code>: it can be retrieved using <code>PyThreadState\_Get()</code>.

### 9.5.1 Releasing the GIL from extension code

Most extension code manipulating the *GIL* has the following simple structure:

```
Save the thread state in a local variable.
Release the global interpreter lock.
... Do some blocking I/O operation ...
Reacquire the global interpreter lock.
Restore the thread state from the local variable.
```

This is so common that a pair of macros exists to simplify it:

```
Py_BEGIN_ALLOW_THREADS
... Do some blocking I/O operation ...
Py_END_ALLOW_THREADS
```

The Py\_BEGIN\_ALLOW\_THREADS macro opens a new block and declares a hidden local variable; the Py\_END\_ALLOW\_THREADS macro closes the block.

The block above expands to the following code:

```
PyThreadState *_save;

_save = PyEval_SaveThread();
... Do some blocking I/O operation ...
PyEval_RestoreThread(_save);
```

Here is how these functions work: the global interpreter lock is used to protect the pointer to the current thread state. When releasing the lock and saving the thread state, the current thread state pointer must be retrieved before the lock is released (since another thread could immediately acquire the lock and store its own thread state in the global variable). Conversely, when acquiring the lock and restoring the thread state, the lock must be acquired before storing the thread state pointer.

**Note:** Calling system I/O functions is the most common use case for releasing the GIL, but it can also be useful before calling long-running computations which don't need access to Python objects, such as compression or cryptographic functions operating over memory buffers. For example, the standard zlib and hashlib modules release the GIL when compressing or hashing data.

## 9.5.2 Non-Python created threads

When threads are created using the dedicated Python APIs (such as the threading module), a thread state is automatically associated to them and the code showed above is therefore correct. However, when threads are created from C (for example by a third-party library with its own thread management), they don't hold the GIL, nor is there a thread state structure for them.

If you need to call Python code from these threads (often this will be part of a callback API provided by the aforementioned third-party library), you must first register these threads with the interpreter by creating a thread state data structure, then acquiring the GIL, and finally storing their thread state pointer, before you can start using the Python/C API. When you are done, you should reset the thread state pointer, release the GIL, and finally free the thread state data structure.

The PyGILState\_Ensure() and PyGILState\_Release() functions do all of the above automatically. The typical idiom for calling into Python from a C thread is:

```
PyGILState_STATE gstate;
gstate = PyGILState_Ensure();

/* Perform Python actions here. */
result = CallSomeFunction();
/* evaluate result or handle exception */

/* Release the thread. No Python API allowed beyond this point. */
PyGILState_Release(gstate);
```

Note that the PyGILState\_\*() functions assume there is only one global interpreter (created automatically by Py\_Initialize()). Python supports the creation of additional interpreters (using Py\_NewInterpreter()), but mixing multiple interpreters and the PyGILState\_\*() API is unsupported.

Another important thing to note about threads is their behaviour in the face of the  $C \, fork()$  call. On most systems with fork(), after a process forks only the thread that issued the fork will exist. That also means any locks held by other threads will never be released. Python solves this for os.fork() by acquiring the locks it uses internally before the fork, and releasing them afterwards. In addition, it resets any lock-objects in the child. When extending or embedding Python, there is no way to inform Python of additional (non-Python) locks that need to be acquired before or reset after a fork. OS facilities such as pthread\_atfork() would need to be used to accomplish the same thing. Additionally, when extending or embedding Python, calling fork() directly rather than through os.fork() (and returning to or calling into Python) may result in a deadlock by one of Python's internal locks being held by a thread that is defunct after the fork.  $PyOS_AfterFork_Child()$  tries to reset the necessary locks, but is not always able to.

## 9.5.3 High-level API

These are the most commonly used types and functions when writing C extension code, or when embedding the Python interpreter:

### PyInterpreterState

This data structure represents the state shared by a number of cooperating threads. Threads belonging to the same interpreter share their module administration and a few other internal items. There are no public members in this structure.

Threads belonging to different interpreters initially share nothing, except process state like available memory, open file descriptors and such. The global interpreter lock is also shared by all threads, regardless of to which interpreter they belong.

### PyThreadState

This data structure represents the state of a single thread. The only public data member is <code>PyInterpreterState \*interp</code>, which points to this thread's interpreter state.

#### void PyEval InitThreads()

Initialize and acquire the global interpreter lock. It should be called in the main thread before creating a second thread or engaging in any other thread operations such as PyEval\_ReleaseThread(tstate). It is not needed before calling PyEval\_SaveThread() or PyEval\_RestoreThread().

This is a no-op when called for a second time.

Changed in version 3.7: This function is now called by  $Py\_Initialize()$ , so you don't have to call it yourself anymore.

Changed in version 3.2: This function cannot be called before Py\_Initialize() anymore.

### int PyEval\_ThreadsInitialized()

Returns a non-zero value if PyEval\_InitThreads() has been called. This function can be called without holding the GIL, and therefore can be used to avoid calls to the locking API when running single-threaded.

Changed in version 3.7: The GIL is now initialized by Py\_Initialize().

### PyThreadState\* PyEval\_SaveThread()

Release the global interpreter lock (if it has been created) and reset the thread state to *NULL*, returning the previous thread state (which is not *NULL*). If the lock has been created, the current thread must have acquired it.

### void PyEval\_RestoreThread (PyThreadState \*tstate)

Acquire the global interpreter lock (if it has been created) and set the thread state to *tstate*, which must not be *NULL*. If the lock has been created, the current thread must not have acquired it, otherwise deadlock ensues.

**Note:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use <code>\_Py\_IsFinalizing()</code> or <code>sys.is\_finalizing()</code> to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

### PyThreadState\* PyThreadState\_Get ()

Return the current thread state. The global interpreter lock must be held. When the current thread state is *NULL*, this issues a fatal error (so that the caller needn't check for *NULL*).

### PyThreadState\* PyThreadState\_Swap (PyThreadState \*tstate)

Swap the current thread state with the thread state given by the argument *tstate*, which may be *NULL*. The global interpreter lock must be held and is not released.

The following functions use thread-local storage, and are not compatible with sub-interpreters:

### PyGILState\_STATE PyGILState\_Ensure()

Ensure that the current thread is ready to call the Python C API regardless of the current state of Python, or of the global interpreter lock. This may be called as many times as desired by a thread as long as each call is matched with a call to  $PyGILState_Release()$ . In general, other thread-related APIs may be used between  $PyGILState_Ensure()$  and  $PyGILState_Release()$  calls as long as the thread state is restored to its previous state before the Release(). For example, normal usage of the  $Py_BEGIN_ALLOW_THREADS$  and  $Py_END_ALLOW_THREADS$  macros is acceptable.

The return value is an opaque "handle" to the thread state when <code>PyGILState\_Ensure()</code> was called, and must be passed to <code>PyGILState\_Release()</code> to ensure Python is left in the same state. Even though recursive calls

are allowed, these handles cannot be shared - each unique call to  $PyGILState\_Ensure()$  must save the handle for its call to  $PyGILState\_Release()$ .

When the function returns, the current thread will hold the GIL and be able to call arbitrary Python code. Failure is a fatal error.

**Note:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use <code>\_Py\_IsFinalizing()</code> or <code>sys.is\_finalizing()</code> to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

### void PyGILState\_Release (PyGILState\_STATE)

Release any resources previously acquired. After this call, Python's state will be the same as it was prior to the corresponding <code>PyGILState\_Ensure()</code> call (but generally this state will be unknown to the caller, hence the use of the GILState API).

Every call to  $PyGILState\_Ensure()$  must be matched by a call to  $PyGILState\_Release()$  on the same thread.

### PyThreadState\* PyGILState\_GetThisThreadState()

Get the current thread state for this thread. May return NULL if no GILState API has been used on the current thread. Note that the main thread always has such a thread-state, even if no auto-thread-state call has been made on the main thread. This is mainly a helper/diagnostic function.

### int PyGILState\_Check()

Return 1 if the current thread is holding the GIL and 0 otherwise. This function can be called from any thread at any time. Only if it has had its Python thread state initialized and currently is holding the GIL will it return 1. This is mainly a helper/diagnostic function. It can be useful for example in callback contexts or memory allocation functions when knowing that the GIL is locked can allow the caller to perform sensitive actions or otherwise behave differently.

New in version 3.4.

The following macros are normally used without a trailing semicolon; look for example usage in the Python source distribution.

### Py\_BEGIN\_ALLOW\_THREADS

This macro expands to { PyThreadState \*\_save; \_save = PyEval\_SaveThread();. Note that it contains an opening brace; it must be matched with a following  $Py\_END\_ALLOW\_THREADS$  macro. See above for further discussion of this macro.

### Py END ALLOW THREADS

This macro expands to PyEval\_RestoreThread (\_save); }. Note that it contains a closing brace; it must be matched with an earlier Py\_BEGIN\_ALLOW\_THREADS macro. See above for further discussion of this macro.

### Py\_BLOCK\_THREADS

This macro expands to PyEval\_RestoreThread(\_save);: it is equivalent to Py\_END\_ALLOW\_THREADS without the closing brace.

### Py\_UNBLOCK\_THREADS

This macro expands to \_save = PyEval\_SaveThread();: it is equivalent to Py\_BEGIN\_ALLOW\_THREADS without the opening brace and variable declaration.

### 9.5.4 Low-level API

All of the following functions must be called after Py\_Initialize().

Changed in version 3.7: Py\_Initialize () now initializes the GIL.

### PyInterpreterState\* PyInterpreterState\_New()

Create a new interpreter state object. The global interpreter lock need not be held, but may be held if it is necessary to serialize calls to this function.

Raises an auditing event cpython.PyInterpreterState\_New with no arguments.

### void PyInterpreterState\_Clear (PyInterpreterState \*interp)

Reset all information in an interpreter state object. The global interpreter lock must be held.

Raises an auditing event cpython.PyInterpreterState Clear with no arguments.

### void PyInterpreterState\_Delete (PyInterpreterState \*interp)

Destroy an interpreter state object. The global interpreter lock need not be held. The interpreter state must have been reset with a previous call to <code>PyInterpreterState\_Clear()</code>.

### PyThreadState\* PyThreadState\_New (PyInterpreterState \*interp)

Create a new thread state object belonging to the given interpreter object. The global interpreter lock need not be held, but may be held if it is necessary to serialize calls to this function.

### void PyThreadState\_Clear (PyThreadState \*tstate)

Reset all information in a thread state object. The global interpreter lock must be held.

### void PyThreadState\_Delete (PyThreadState \*tstate)

Destroy a thread state object. The global interpreter lock need not be held. The thread state must have been reset with a previous call to <code>PyThreadState\_Clear()</code>.

### PY\_INT64\_T PyInterpreterState\_GetID (PyInterpreterState \*interp)

Return the interpreter's unique ID. If there was any error in doing so then -1 is returned and an error is set.

New in version 3.7.

### PyObject\* PyInterpreterState\_GetDict (PyInterpreterState \*interp)

Return a dictionary in which interpreter-specific data may be stored. If this function returns *NULL* then no exception has been raised and the caller should assume no interpreter-specific dict is available.

This is not a replacement for <code>PyModule\_GetState()</code>, which extensions should use to store interpreter-specific state information.

New in version 3.8.

#### PyObject\* PyThreadState\_GetDict()

Return value: Borrowed reference. Return a dictionary in which extensions can store thread-specific state information. Each extension should use a unique key to use to store state in the dictionary. It is okay to call this function when no current thread state is available. If this function returns NULL, no exception has been raised and the caller should assume no current thread state is available.

### int PyThreadState\_SetAsyncExc (unsigned long id, PyObject \*exc)

Asynchronously raise an exception in a thread. The *id* argument is the thread id of the target thread; *exc* is the exception object to be raised. This function does not steal any references to *exc*. To prevent naive misuse, you must write your own C extension to call this. Must be called with the GIL held. Returns the number of thread states modified; this is normally one, but will be zero if the thread id isn't found. If *exc* is NULL, the pending exception (if any) for the thread is cleared. This raises no exceptions.

Changed in version 3.7: The type of the *id* parameter changed from long to unsigned long.

#### void PyEval\_AcquireThread (PyThreadState \*tstate)

Acquire the global interpreter lock and set the current thread state to *tstate*, which should not be *NULL*. The lock must have been created earlier. If this thread already has the lock, deadlock ensues.

**Note:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use \_Py\_IsFinalizing() or sys.is\_finalizing() to

check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

Changed in version 3.8: Updated to be consistent with <code>PyEval\_RestoreThread()</code>, <code>Py\_END\_ALLOW\_THREADS()</code>, and <code>PyGILState\_Ensure()</code>, and terminate the current thread if called while the interpreter is finalizing.

PyEval\_RestoreThread() is a higher-level function which is always available (even when threads have not been initialized).

### void PyEval\_ReleaseThread (PyThreadState \*tstate)

Reset the current thread state to *NULL* and release the global interpreter lock. The lock must have been created earlier and must be held by the current thread. The *tstate* argument, which must not be *NULL*, is only used to check that it represents the current thread state — if it isn't, a fatal error is reported.

*PyEval\_SaveThread()* is a higher-level function which is always available (even when threads have not been initialized).

### void PyEval\_AcquireLock()

Acquire the global interpreter lock. The lock must have been created earlier. If this thread already has the lock, a deadlock ensues.

Deprecated since version 3.2: This function does not update the current thread state. Please use PyEval\_RestoreThread() or PyEval\_AcquireThread() instead.

**Note:** Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use <code>Py\_IsFinalizing()</code> or <code>sys.is\_finalizing()</code> to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

Changed in version 3.8: Updated to be consistent with  $PyEval\_RestoreThread()$ ,  $Py\_END\_ALLOW\_THREADS()$ , and  $PyGILState\_Ensure()$ , and terminate the current thread if called while the interpreter is finalizing.

### void PyEval\_ReleaseLock()

Release the global interpreter lock. The lock must have been created earlier.

Deprecated since version 3.2: This function does not update the current thread state. Please use PyEval\_SaveThread() or PyEval\_ReleaseThread() instead.

# 9.6 Sub-interpreter support

While in most uses, you will only embed a single Python interpreter, there are cases where you need to create several independent interpreters in the same process and perhaps even in the same thread. Sub-interpreters allow you to do that.

The "main" interpreter is the first one created when the runtime initializes. It is usually the only Python interpreter in a process. Unlike sub-interpreters, the main interpreter has unique process-global responsibilities like signal handling. It is also responsible for execution during runtime initialization and is usually the active interpreter during runtime finalization. The <code>PyInterpreterState\_Main()</code> funtion returns a pointer to its state.

You can switch between sub-interpreters using the PyThreadState\_Swap () function. You can create and destroy them using the following functions:

### PyThreadState\* Py\_NewInterpreter()

Create a new sub-interpreter. This is an (almost) totally separate environment for the execution of Python code. In particular, the new interpreter has separate, independent versions of all imported modules, including the fundamental modules builtins, \_\_main\_\_ and sys. The table of loaded modules (sys.modules) and the module search path (sys.path) are also separate. The new environment has no sys.argv variable. It has

new standard I/O stream file objects sys.stdin, sys.stdout and sys.stderr (however these refer to the same underlying file descriptors).

The return value points to the first thread state created in the new sub-interpreter. This thread state is made in the current thread state. Note that no actual thread is created; see the discussion of thread states below. If creation of the new interpreter is unsuccessful, *NULL* is returned; no exception is set since the exception state is stored in the current thread state and there may not be a current thread state. (Like all other Python/C API functions, the global interpreter lock must be held before calling this function and is still held when it returns; however, unlike most other Python/C API functions, there needn't be a current thread state on entry.)

Extension modules are shared between (sub-)interpreters as follows: the first time a particular extension is imported, it is initialized normally, and a (shallow) copy of its module's dictionary is squirreled away. When the same extension is imported by another (sub-)interpreter, a new module is initialized and filled with the contents of this copy; the extension's init function is not called. Note that this is different from what happens when an extension is imported after the interpreter has been completely re-initialized by calling  $Py_FinalizeEx()$  and  $Py_Initialize()$ ; in that case, the extension's initmodule function is called again.

### void Py\_EndInterpreter (PyThreadState \*tstate)

Destroy the (sub-)interpreter represented by the given thread state. The given thread state must be the current thread state. See the discussion of thread states below. When the call returns, the current thread state is NULL. All thread states associated with this interpreter are destroyed. (The global interpreter lock must be held before calling this function and is still held when it returns.)  $Py_FinalizeEx()$  will destroy all sub-interpreters that haven't been explicitly destroyed at that point.

### 9.6.1 Bugs and caveats

Because sub-interpreters (and the main interpreter) are part of the same process, the insulation between them isn't perfect — for example, using low-level file operations like os.close() they can (accidentally or maliciously) affect each other's open files. Because of the way extensions are shared between (sub-)interpreters, some extensions may not work properly; this is especially likely when the extension makes use of (static) global variables, or when the extension manipulates its module's dictionary after its initialization. It is possible to insert objects created in one sub-interpreter into a namespace of another sub-interpreter; this should be done with great care to avoid sharing user-defined functions, methods, instances or classes between sub-interpreters, since import operations executed by such objects may affect the wrong (sub-)interpreter's dictionary of loaded modules.

Also note that combining this functionality with PyGILState\_\*() APIs is delicate, because these APIs assume a bijection between Python thread states and OS-level threads, an assumption broken by the presence of sub-interpreters. It is highly recommended that you don't switch sub-interpreters between a pair of matching PyGILState\_Ensure() and PyGILState\_Release() calls. Furthermore, extensions (such as ctypes) using these APIs to allow calling of Python code from non-Python created threads will probably be broken when using sub-interpreters.

# 9.7 Asynchronous Notifications

A mechanism is provided to make asynchronous notifications to the main interpreter thread. These notifications take the form of a function pointer and a void pointer argument.

### int Py\_AddPendingCall (int (\*func)(void \*), void \*arg)

Schedule a function to be called from the main interpreter thread. On success, 0 is returned and *func* is queued for being called in the main thread. On failure, -1 is returned without setting any exception.

When successfully queued, *func* will be *eventually* called from the main interpreter thread with the argument *arg*. It will be called asynchronously with respect to normally running Python code, but with both these conditions met:

• on a *bytecode* boundary;

• with the main thread holding the *global interpreter lock* (func can therefore use the full C API).

func must return 0 on success, or -1 on failure with an exception set. func won't be interrupted to perform another asynchronous notification recursively, but it can still be interrupted to switch threads if the global interpreter lock is released.

This function doesn't need a current thread state to run, and it doesn't need the global interpreter lock.

**Warning:** This is a low-level function, only useful for very special cases. There is no guarantee that *func* will be called as quick as possible. If the main thread is busy executing a system call, *func* won't be called before the system call returns. This function is generally **not** suitable for calling Python code from arbitrary C threads. Instead, use the *PyGILState API*.

New in version 3.1.

# 9.8 Profiling and Tracing

The Python interpreter provides some low-level support for attaching profiling and execution tracing facilities. These are used for profiling, debugging, and coverage analysis tools.

This C interface allows the profiling or tracing code to avoid the overhead of calling through Python-level callable objects, making a direct C function call instead. The essential attributes of the facility have not changed; the interface allows trace functions to be installed per-thread, and the basic events reported to the trace function are the same as had been reported to the Python-level trace functions in previous versions.

### int (\*Py\_tracefunc) (PyObject \*obj, PyFrameObject \*frame, int what, PyObject \*arg)

The type of the trace function registered using <code>PyEval\_SetProfile()</code> and <code>PyEval\_SetTrace()</code>. The first parameter is the object passed to the registration function as <code>obj</code>, <code>frame</code> is the frame object to which the event pertains, <code>what</code> is one of the constants <code>PyTrace\_CALL</code>, <code>PyTrace\_EXCEPTION</code>, <code>PyTrace\_LINE</code>, <code>PyTrace\_RETURN</code>, <code>PyTrace\_C\_EXCEPTION</code>, <code>PyTrace\_C\_RETURN</code>, or <code>PyTrace\_OPCODE</code>, and <code>arg</code> depends on the value of <code>what</code>:

Value of what	Meaning of arg
PyTrace_CALL	Always Py_None.
PyTrace_EXCEPTION	Exception information as returned by sys.exc_info().
PyTrace_LINE	Always Py_None.
PyTrace_RETURN	Value being returned to the caller, or <i>NULL</i> if caused by an exception.
PyTrace_C_CALL	Function object being called.
PyTrace_C_EXCEPTION	Function object being called.
PyTrace_C_RETURN	Function object being called.
PyTrace_OPCODE	Always Py_None.

#### int PyTrace\_CALL

The value of the *what* parameter to a *Py\_tracefunc* function when a new call to a function or method is being reported, or a new entry into a generator. Note that the creation of the iterator for a generator function is not reported as there is no control transfer to the Python bytecode in the corresponding frame.

#### int PyTrace EXCEPTION

The value of the *what* parameter to a *Py\_tracefunc* function when an exception has been raised. The callback function is called with this value for *what* when after any bytecode is processed after which the exception becomes set within the frame being executed. The effect of this is that as exception propagation causes the Python stack to unwind, the callback is called upon return to each frame as the exception propagates. Only trace functions receives these events; they are not needed by the profiler.

#### int PyTrace LINE

The value passed as the *what* parameter to a  $Py\_tracefunc$  function (but not a profiling function) when a line-number event is being reported. It may be disabled for a frame by setting  $f\_trace\_lines$  to  $\theta$  on that frame.

### int PyTrace\_RETURN

The value for the *what* parameter to Py tracefunc functions when a call is about to return.

#### int PyTrace C CALL

The value for the *what* parameter to Py tracefunc functions when a C function is about to be called.

#### int PyTrace\_C\_EXCEPTION

The value for the *what* parameter to Py\_tracefunc functions when a C function has raised an exception.

### int PyTrace\_C\_RETURN

The value for the *what* parameter to Py\_tracefunc functions when a C function has returned.

### int PyTrace\_OPCODE

The value for the *what* parameter to  $Py\_tracefunc$  functions (but not profiling functions) when a new opcode is about to be executed. This event is not emitted by default: it must be explicitly requested by setting  $f\_trace\_opcodes$  to I on the frame.

### void PyEval\_SetProfile (Py\_tracefunc func, PyObject \*obj)

Set the profiler function to *func*. The *obj* parameter is passed to the function as its first parameter, and may be any Python object, or *NULL*. If the profile function needs to maintain state, using a different value for *obj* for each thread provides a convenient and thread-safe place to store it. The profile function is called for all monitored events except PyTrace LINE PyTrace OPCODE and PyTrace EXCEPTION.

### void PyEval SetTrace (Py tracefunc func, PyObject \*obj)

Set the tracing function to *func*. This is similar to *PyEval\_SetProfile()*, except the tracing function does receive line-number events and per-opcode events, but does not receive any event related to C function objects being called. Any trace function registered using *PyEval\_SetTrace()* will not receive PyTrace\_C\_CALL, PyTrace\_C\_EXCEPTION or PyTrace\_C\_RETURN as a value for the *what* parameter.

# 9.9 Advanced Debugger Support

These functions are only intended to be used by advanced debugging tools.

### PyInterpreterState\* PyInterpreterState\_Head()

Return the interpreter state object at the head of the list of all such objects.

### PyInterpreterState\* PyInterpreterState\_Main()

Return the main interpreter state object.

### PyInterpreterState\* PyInterpreterState\_Next (PyInterpreterState \*interp)

Return the next interpreter state object after *interp* from the list of all such objects.

### PyThreadState \* PyInterpreterState\_ThreadHead (PyInterpreterState \*interp)

Return the pointer to the first PyThreadState object in the list of threads associated with the interpreter interp.

### PyThreadState\* PyThreadState\_Next (PyThreadState \*tstate)

Return the next thread state object after *tstate* from the list of all such objects belonging to the same *PyInterpreterState* object.

# 9.10 Thread Local Storage Support

The Python interpreter provides low-level support for thread-local storage (TLS) which wraps the underlying native TLS implementation to support the Python-level thread local storage API (threading.local). The CPython C level APIs are similar to those offered by pthreads and Windows: use a thread key and functions to associate a void\* value per thread.

The GIL does *not* need to be held when calling these functions; they supply their own locking.

Note that Python.h does not include the declaration of the TLS APIs, you need to include pythread.h to use thread-local storage.

**Note:** None of these API functions handle memory management on behalf of the void\* values. You need to allocate and deallocate them yourself. If the void\* values happen to be *PyObject\**, these functions don't do refcount operations on them either.

### 9.10.1 Thread Specific Storage (TSS) API

TSS API is introduced to supersede the use of the existing TLS API within the CPython interpreter. This API uses a new type  $Py\_tss\_t$  instead of int to represent thread keys.

New in version 3.7.

#### See also:

"A New C-API for Thread-Local Storage in CPython" (PEP 539)

### Py\_tss\_t

This data structure represents the state of a thread key, the definition of which may depend on the underlying TLS implementation, and it has an internal field representing the key's initialization state. There are no public members in this structure.

When Py\_LIMITED\_API is not defined, static allocation of this type by Py\_tss\_NEEDS\_INIT is allowed.

### Py\_tss\_NEEDS\_INIT

This macro expands to the initializer for  $Py\_tss\_t$  variables. Note that this macro won't be defined with  $Py\_LIMITED\_API$ .

### **Dynamic Allocation**

Dynamic allocation of the  $Py\_tss\_t$ , required in extension modules built with  $Py\_LIMITED\_API$ , where static allocation of this type is not possible due to its implementation being opaque at build time.

### Py\_tss\_t\* PyThread\_tss\_alloc()

Return a value which is the same state as a value initialized with  $Py\_tss\_NEEDS\_INIT$ , or NULL in the case of dynamic allocation failure.

### void PyThread\_tss\_free (Py\_tss\_t \*key)

Free the given *key* allocated by *PyThread\_tss\_alloc()*, after first calling *PyThread\_tss\_delete()* to ensure any associated thread locals have been unassigned. This is a no-op if the *key* argument is *NULL*.

**Note:** A freed key becomes a dangling pointer, you should reset the key to *NULL*.

#### **Methods**

The parameter key of these functions must not be NULL. Moreover, the behaviors of  $PyThread\_tss\_set()$  and  $PyThread\_tss\_get()$  are undefined if the given  $Py\_tss\_t$  has not been initialized by  $PyThread\_tss\_create()$ .

```
int PyThread_tss_is_created (Py_tss_t *key)
```

Return a non-zero value if the given  $Py\_tss\_t$  has been initialized by  $PyThread\_tss\_create()$ .

```
int PyThread_tss_create (Py_tss_t *key)
```

Return a zero value on successful initialization of a TSS key. The behavior is undefined if the value pointed to by the *key* argument is not initialized by  $Py\_tss\_NEEDS\_INIT$ . This function can be called repeatedly on the same key – calling it on an already initialized key is a no-op and immediately returns success.

```
void PyThread_tss_delete (Py_tss_t *key)
```

Destroy a TSS key to forget the values associated with the key across all threads, and change the key's initialization state to uninitialized. A destroyed key is able to be initialized again by <code>PyThread\_tss\_create()</code>. This function can be called repeatedly on the same key – calling it on an already destroyed key is a no-op.

```
int PyThread_tss_set (Py_tss_t *key, void *value)
```

Return a zero value to indicate successfully associating a void\* value with a TSS key in the current thread. Each thread has a distinct mapping of the key to a void\* value.

```
void* PyThread_tss_get (Py_tss_t *key)
```

Return the void\* value associated with a TSS key in the current thread. This returns *NULL* if no value is associated with the key in the current thread.

### 9.10.2 Thread Local Storage (TLS) API

Deprecated since version 3.7: This API is superseded by *Thread Specific Storage (TSS) API*.

**Note:** This version of the API does not support platforms where the native TLS key is defined in a way that cannot be safely cast to int. On such platforms, <code>PyThread\_create\_key()</code> will return immediately with a failure status, and the other TLS functions will all be no-ops on such platforms.

Due to the compatibility problem noted above, this version of the API should not be used in new code.

```
int PyThread_create_key ()
void PyThread_delete_key (int key)
int PyThread_set_key_value (int key, void *value)
void* PyThread_get_key_value (int key)
void PyThread_delete_key_value (int key)
void PyThread_ReInitTLS()
```

## **PYTHON INITIALIZATION CONFIGURATION**

#### New in version 3.8.

#### Structures:

- PyConfig
- PyPreConfig
- PyStatus
- PyWideStringList

#### Functions:

- PyConfig\_Clear()
- PyConfig\_InitIsolatedConfig()
- PyConfig\_InitPythonConfig()
- PyConfig\_Read()
- PyConfig\_SetArgv()
- PyConfig\_SetBytesArgv()
- PyConfig\_SetBytesString()
- PyConfig\_SetString()
- PyConfig\_SetWideStringList()
- PyPreConfig\_InitIsolatedConfig()
- PyPreConfig\_InitPythonConfig()
- PyStatus\_Error()
- PyStatus\_Exception()
- PyStatus\_Exit()
- PyStatus\_IsError()
- PyStatus\_IsExit()
- PyStatus\_NoMemory()
- PyStatus\_Ok()
- PyWideStringList\_Append()
- PyWideStringList\_Insert()

- Py\_ExitStatusException()
- Py\_InitializeFromConfig()
- Py\_PreInitialize()
- Py\_PreInitializeFromArgs()
- Py\_PreInitializeFromBytesArgs()
- Py RunMain()

The preconfiguration (PyPreConfig type) is stored in \_PyRuntime.preconfig and the configuration (PyConfig type) is stored in PyInterpreterState.config.

See also Initialization, Finalization, and Threads.

#### See also:

PEP 587 "Python Initialization Configuration".

# 10.1 PyWideStringList

### PyWideStringList

List of wchar\_t\* strings.

If *length* is non-zero, *items* must be non-NULL and all strings must be non-NULL.

Methods:

```
PyStatus PyWideStringList_Append (PyWideStringList *list, const wchar_t *item)
```

Append item to list.

Python must be preinitialized to call this function.

```
PyStatus PyWideStringList_Insert (PyWideStringList *list, Py_ssize_t index, const wchar_t *item)
Insert item into list at index.
```

If *index* is greater than or equal to *list* length, append *item* to *list*.

index must be greater than or equal to 0.

Python must be preinitialized to call this function.

Structure fields:

```
Py_ssize_t length
List length.
wchar_t** items
List items.
```

# 10.2 PyStatus

### **PyStatus**

Structure to store an initialization function status: success, error or exit.

For an error, it can store the C function name which created the error.

Structure fields:

```
int exitcode
     Exit code. Argument passed to exit().
const char *err_msg
     Error message.
const char *func
     Name of the function which created an error, can be NULL.
Functions to create a status:
PyStatus PyStatus_Ok (void)
     Success.
PyStatus PyStatus_Error (const char *err_msg)
     Initialization error with a message.
PyStatus_NoMemory (void)
     Memory allocation failure (out of memory).
PyStatus PyStatus_Exit (int exitcode)
     Exit Python with the specified exit code.
Functions to handle a status:
int PyStatus_Exception (PyStatus status)
     Is the status an error or an exit?
                                              If true, the exception must be handled; by calling
     Py ExitStatusException() for example.
int PyStatus_IsError (PyStatus status)
    Is the result an error?
int PyStatus_IsExit (PyStatus status)
    Is the result an exit?
void Py_ExitStatusException (PyStatus status)
     Call exit (exitcode) if status is an exit. Print the error message and exit with a non-zero exit code if
```

**Note:** Internally, Python uses macros which set PyStatus.func, whereas functions to create a status set func to NULL.

status is an error. Must only be called if PyStatus\_Exception (status) is non-zero.

### Example:

```
PyStatus alloc(void **ptr, size_t size)
{
    *ptr = PyMem_RawMalloc(size);
    if (*ptr == NULL) {
        return PyStatus_NoMemory();
    }
    return PyStatus_Ok();
}

int main(int argc, char **argv)
{
    void *ptr;
    PyStatus status = alloc(&ptr, 16);
    if (PyStatus_Exception(status)) {
        Py_ExitStatusException(status);
    }
}
```

(continues on next page)

10.2. PyStatus 157

```
PyMem_Free(ptr);
return 0;
}
```

## 10.3 PyPreConfig

### PyPreConfig

Structure used to preinitialize Python:

- Set the Python memory allocator
- Configure the LC\_CTYPE locale
- Set the UTF-8 mode

Function to initialize a preconfiguration:

### void PyPreConfig\_InitIsolatedConfig (PyPreConfig \*preconfig)

Initialize the preconfiguration with *Python Configuration*.

### void PyPreConfig\_InitPythonConfig (PyPreConfig \*preconfig)

Initialize the preconfiguration with *Isolated Configuration*.

Structure fields:

#### int allocator

Name of the memory allocator:

- PYMEM\_ALLOCATOR\_NOT\_SET (0): don't change memory allocators (use defaults)
- PYMEM\_ALLOCATOR\_DEFAULT (1): default memory allocators
- PYMEM\_ALLOCATOR\_DEBUG (2): default memory allocators with debug hooks
- PYMEM\_ALLOCATOR\_MALLOC(3): force usage of malloc()
- PYMEM\_ALLOCATOR\_MALLOC\_DEBUG (4): force usage of malloc() with debug hooks
- PYMEM\_ALLOCATOR\_PYMALLOC (5): Python pymalloc memory allocator
- PYMEM\_ALLOCATOR\_PYMALLOC\_DEBUG (6): Python pymalloc memory allocator with debug hooks

PYMEM\_ALLOCATOR\_PYMALLOC and PYMEM\_ALLOCATOR\_PYMALLOC\_DEBUG are not supported if Python is configured using --without-pymalloc

See Memory Management.

### int configure\_locale

Set the LC\_CTYPE locale to the user preferred locale? If equals to 0, set <code>coerce\_c\_locale</code> and <code>coerce\_c\_locale\_warn</code> to 0.

### int coerce\_c\_locale

If equals to 2, coerce the C locale; if equals to 1, read the LC\_CTYPE locale to decide if it should be coerced.

### int coerce\_c\_locale\_warn

If non-zero, emit a warning if the C locale is coerced.

### int dev\_mode

See PyConfig.dev\_mode.

#### int isolated

See PyConfig.isolated.

### int legacy\_windows\_fs\_encoding (Windows only)

If non-zero, disable UTF-8 Mode, set the Python filesystem encoding to mbcs, set the filesystem error handler to replace.

Only available on Windows. #ifdef MS\_WINDOWS macro can be used for Windows specific code.

### int parse\_argv

If non-zero, Py\_PreInitializeFromArgs() and Py\_PreInitializeFromBytesArgs() parse their argv argument the same way the regular Python parses command line arguments: see Command Line Arguments.

#### int use\_environment

See PyConfig.use\_environment.

#### int utf8\_mode

If non-zero, enable the UTF-8 mode.

# 10.4 Preinitialization with PyPreConfig

Functions to preinitialize Python:

PyStatus Py\_PreInitialize (const PyPreConfig \*preconfig)
Preinitialize Python from preconfig preconfiguration.

*PyStatus* **Py\_PreInitializeFromBytesArgs** (const *PyPreConfig \*preconfig*, int *argc*, char \* const \**argv*) Preinitialize Python from *preconfig* preconfiguration and command line arguments (bytes strings).

PyStatus Py\_PreInitializeFromArgs (const PyPreConfig \*preconfig, int argc, wchar\_t \* const \* argv)
Preinitialize Python from preconfig preconfiguration and command line arguments (wide strings).

The caller is responsible to handle exceptions (error or exit) using  $PyStatus\_Exception()$  and  $Py\_ExitStatusException()$ .

For *Python Configuration* (*PyPreConfig\_InitPythonConfig()*), if Python is initialized with command line arguments, the command line arguments must also be passed to preinitialize Python, since they have an effect on the pre-configuration like encodings. For example, the -X utf8 command line option enables the UTF-8 Mode.

PyMem\_SetAllocator() can be called after Py\_PreInitialize() and before Py\_InitializeFromConfig() to install a custom memory allocator. It can be called before Py\_PreInitialize() if PyPreConfig.allocator is set to PYMEM\_ALLOCATOR\_NOT\_SET.

Python memory allocation functions like  $PyMem\_RawMalloc()$  must not be used before Python preinitialization, whereas calling directly malloc() and free() is always safe.  $Py\_DecodeLocale()$  must not be called before the preinitialization.

Example using the preinitialization to enable the UTF-8 Mode:

```
PyStatus status;
PyPreConfig preconfig;
PyPreConfig_InitPythonConfig(&preconfig);

preconfig.utf8_mode = 1;

status = Py_PreInitialize(&preconfig);
if (PyStatus_Exception(status)) {
    Py_ExitStatusException(status);
}
```

```
/* at this point, Python will speak UTF-8 */
Py_Initialize();
/* ... use Python API here ... */
Py_Finalize();
```

## 10.5 PyConfig

### PyConfig

Structure containing most parameters to configure Python.

Structure methods:

```
void PyConfig_InitPythonConfig (PyConfig *config)
```

Initialize configuration with Python Configuration.

```
void PyConfig_InitIsolatedConfig (PyConfig *config)
```

Initialize configuration with *Isolated Configuration*.

 $\textit{PyStatus} \ \textbf{PyConfig} \ *\textit{config}, \ \text{wchar\_t} *\textit{const} *\textit{config\_str}, \ \text{const} \ \text{wchar\_t} *\textit{str})$ 

Copy the wide character string str into \*config\_str.

Preinitialize Python if needed.

PyStatus PyConfig\_SetBytesString (PyConfig \*config, wchar\_t \* const \*config\_str, const char \*str)

Decode str using Py\_DecodeLocale() and set the result into \*config\_str.

Preinitialize Python if needed.

PyStatus PyConfig\_SetArgv (PyConfig \*config, int argc, wchar\_t \* const \*argv)

Set command line arguments from wide character strings.

Preinitialize Python if needed.

PyStatus PyConfig\_SetBytesArgv (PyConfig \*config, int argc, char \* const \*argv)

Set command line arguments: decode bytes using Py\_DecodeLocale().

Preinitialize Python if needed.

PyStatus PyConfig\_SetWideStringList (PyConfig \*config, PyWideStringList \*list,

Py\_ssize\_t *length*, wchar\_t \*\*items)

Set the list of wide strings *list* to *length* and *items*.

Preinitialize Python if needed.

PyStatus PyConfig\_Read (PyConfig \*config)

Read all Python configuration.

Fields which are already initialized are left unchanged.

Preinitialize Python if needed.

void PyConfig\_Clear (PyConfig \*config)

Release configuration memory.

Most PyConfig methods preinitialize Python if needed. In that case, the Python preinitialization configuration in based on the PyConfig. If configuration fields which are in common with PyPreConfig are tuned, they must be set before calling a PyConfig method:

• dev\_mode

- isolated
- parse\_argv
- use\_environment

Moreover, if PyConfig\_SetArgv() or PyConfig\_SetBytesArgv() is used, this method must be called first, before other methods, since the preinitialization configuration depends on command line arguments (if parse\_argv is non-zero).

The caller of these methods is responsible to handle exceptions (error or exit) using PyStatus\_Exception() and Py\_ExitStatusException().

### Structure fields:

### PyWideStringList argv

Command line arguments, sys.argv. See parse\_argv to parse argv the same way the regular Python parses Python command line arguments. If argv is empty, an empty string is added to ensure that sys. argv always exists and is never empty.

### wchar\_t\* base\_exec\_prefix

sys.base exec prefix.

#### wchar\_t\* base\_executable

sys.\_base\_executable: \_\_PYVENV\_LAUNCHER\_\_ environment variable value, or copy of PyConfig.executable.

### wchar\_t\* base\_prefix

sys.base\_prefix.

### int buffered\_stdio

If equals to 0, enable unbuffered mode, making the stdout and stderr streams unbuffered.

stdin is always opened in buffered mode.

### int bytes\_warning

If equals to 1, issue a warning when comparing bytes or bytearray with str, or comparing bytes with int. If equal or greater to 2, raise a BytesWarning exception.

### wchar\_t\* check\_hash\_pycs\_mode

Control the validation behavior of hash-based .pyc files (see PEP 552): --check-hash-based-pycs command line option value.

Valid values: always, never and default.

The default value is: default.

### int configure\_c\_stdio

If non-zero, configure C standard streams (stdio, stdout, stdout). For example, set their mode to O\_BINARY on Windows.

### int dev\_mode

Development mode: see -X dev.

### int dump\_refs

If non-zero, dump all objects which are still alive at exit.

Require a debug build of Python (Py\_REF\_DEBUG macro must be defined).

### wchar\_t\* exec\_prefix

sys.exec\_prefix.

### wchar t\* executable

sys.executable.

10.5. PyConfig 161

#### int faulthandler

If non-zero, call faulthandler.enable() at startup.

### wchar\_t\* filesystem\_encoding

Filesystem encoding, sys.getfilesystemencoding().

#### wchar t\* filesystem errors

Filesystem encoding errors, sys.getfilesystemencodeerrors().

### unsigned long hash\_seed

### int use\_hash\_seed

Randomized hash function seed.

If use\_hash\_seed is zero, a seed is chosen randomly at Pythonstartup, and hash\_seed is ignored.

#### wchar\_t\* home

Python home directory.

Initialized from PYTHONHOME environment variable value by default.

#### int import time

If non-zero, profile import time.

#### int inspect

Enter interactive mode after executing a script or a command.

#### int install\_signal\_handlers

Install signal handlers?

#### int interactive

Interactive mode.

### int isolated

If greater than 0, enable isolated mode:

- sys.path contains neither the script's directory (computed from argv[0] or the current directory) nor the user's site-packages directory.
- Python REPL doesn't import readline nor enable default readline configuration on interactive prompts.
- Set use\_environment and user\_site\_directory to 0.

### int legacy\_windows\_stdio

If non-zero, use io. File IO instead of io. Windows Console IO for sys. stdin, sys. stdout and sys. stderr.

Only available on Windows. #ifdef MS WINDOWS macro can be used for Windows specific code.

### int malloc\_stats

If non-zero, dump statistics on Python pymalloc memory allocator at exit.

The option is ignored if Python is built using --without-pymalloc.

### wchar\_t\* pythonpath\_env

Module search paths as a string separated by DELIM (os.path.pathsep).

Initialized from PYTHONPATH environment variable value by default.

### PyWideStringList module\_search\_paths

### int module\_search\_paths\_set

sys.path. If module\_search\_paths\_set is equal to 0, the module\_search\_paths is over-ridden by the function calculating the *Path Configuration*.

### int optimization\_level

Compilation optimization level:

- 0: Peephole optimizer (and \_\_\_debug\_\_\_ is set to True)
- 1: Remove assertions, set \_\_debug\_\_ to False
- 2: Strip docstrings

### int parse\_argv

If non-zero, parse *argv* the same way the regular Python command line arguments, and strip Python arguments from *argv*: see Command Line Arguments.

#### int parser\_debug

If non-zero, turn on parser debugging output (for expert only, depending on compilation options).

### int pathconfig\_warnings

If equal to 0, suppress warnings when calculating the *Path Configuration* (Unix only, Windows does not log any warning). Otherwise, warnings are written into stderr.

### wchar\_t\* prefix

```
sys.prefix.
```

#### wchar\_t\* program\_name

Program name. Used to initialize executable, and in early error messages.

### wchar\_t\* pycache\_prefix

```
sys.pycache_prefix: .pyc cache prefix.
```

```
If NULL, sys.pycache_prefix is set to None.
```

### int quiet

Quiet mode. For example, don't display the copyright and version messages in interactive mode.

### wchar\_t\* run\_command

```
python3 -c COMMAND argument. Used by Py_RunMain().
```

### wchar\_t\* run\_filename

```
python3 FILENAME argument. Used by Py_RunMain().
```

### wchar\_t\* run\_module

```
python3 -m MODULE argument. Used by Py_RunMain().
```

### int show\_alloc\_count

Show allocation counts at exit?

Set to 1 by -X showalloccount command line option.

Need a special Python build with COUNT ALLOCS macro defined.

#### int show\_ref\_count

Show total reference count at exit?

Set to 1 by -X showrefcount command line option.

Need a debug build of Python (Py\_REF\_DEBUG macro must be defined).

#### int site\_import

Import the site module at startup?

### int skip\_source\_first\_line

Skip the first line of the source?

### wchar\_t\* stdio\_encoding

10.5. PyConfig 163

#### wchar t\* stdio errors

Encoding and encoding errors of sys.stdin, sys.stdout and sys.stderr.

#### int tracemalloc

If non-zero, call tracemalloc.start() at startup.

#### int use\_environment

If greater than 0, use environment variables.

#### intuser site directory

If non-zero, add user site directory to sys.path.

#### int verbose

If non-zero, enable verbose mode.

### PyWideStringList warnoptions

sys.warnoptions: options of the warnings module to build warnings filters: lowest to highest priority.

The warnings module adds sys.warnoptions in the reverse order: the last *PyConfig.* warnoptions item becomes the first item of warnings.filters which is checked first (highest priority).

### int write\_bytecode

If non-zero, write .pyc files.

sys.dont\_write\_bytecode is initialized to the inverted value of write\_bytecode.

### PyWideStringList xoptions

```
sys._xoptions.
```

If parse\_argv is non-zero, argv arguments are parsed the same way the regular Python parses command line arguments, and Python arguments are stripped from argv: see Command Line Arguments.

The xoptions options are parsed to set other options: see -X option.

# 10.6 Initialization with PyConfig

Function to initialize Python:

```
PyStatus Py_InitializeFromConfig (const PyConfig *config)
```

Initialize Python from *config* configuration.

The caller is responsible to handle exceptions (error or exit) using  $PyStatus\_Exception()$  and  $Py\_ExitStatusException()$ .

 $If \ {\tt PyImport\_FrozenModules, PyImport\_AppendInittab()} \ or \ {\tt PyImport\_ExtendInittab()} \ are used, they must be set or called after Python preinitialization and before the Python initialization.$ 

Example setting the program name:

```
if (PyStatus_Exception(status)) {
    goto fail;
}

status = Py_InitializeFromConfig(&config);
if (PyStatus_Exception(status)) {
    goto fail;
}
PyConfig_Clear(&config);
return;

fail:
    PyConfig_Clear(&config);
    Py_ExitStatusException(status);
}
```

More complete example modifying the default configuration, read the configuration, and then override some parameters:

```
PyStatus init_python(const char *program_name)
   PyStatus status;
   PyConfig config;
   PyConfig_InitPythonConfig(&config);
   /* Set the program name before reading the configuration
       (decode byte string from the locale encoding).
       Implicitly preinitialize Python. */
   status = PyConfig_SetBytesString(&config, &config.program_name,
                                  program_name);
   if (PyStatus_Exception(status)) {
       goto done;
    /* Read all configuration at once */
   status = PyConfig_Read(&config);
   if (PyStatus_Exception(status)) {
       goto done;
    /* Append our custom search path to sys.path */
   status = PyWideStringList_Append(&config.module_search_paths,
                                     L"/path/to/more/modules");
   if (PyStatus_Exception(status)) {
        goto done;
    /* Override executable computed by PyConfig_Read() */
   status = PyConfig_SetString(&config, &config.executable,
                                L"/path/to/my_executable");
   if (PyStatus_Exception(status)) {
       goto done;
    status = Py_InitializeFromConfig(&config);
```

```
done:
    PyConfig_Clear(&config);
    return status;
}
```

## 10.7 Isolated Configuration

PyPreConfig\_InitIsolatedConfig() and PyConfig\_InitIsolatedConfig() functions create a configuration to isolate Python from the system. For example, to embed Python into an application.

This configuration ignores global configuration variables, environments variables, command line arguments (PyConfig. argv is not parsed) and user site directory. The C standard streams (ex: stdout) and the LC\_CTYPE locale are left unchanged. Signal handlers are not installed.

Configuration files are still used with this configuration. Set the *Path Configuration* ("output fields") to ignore these configuration files and avoid the function computing the default path configuration.

# 10.8 Python Configuration

PyPreConfig\_InitPythonConfig() and PyConfig\_InitPythonConfig() functions create a configuration to build a customized Python which behaves as the regular Python.

Environments variables and command line arguments are used to configure Python, whereas global configuration variables are ignored.

This function enables C locale coercion (PEP 538) and UTF-8 Mode (PEP 540) depending on the LC\_CTYPE locale, PYTHONUTF 8 and PYTHONCOERCECLOCALE environment variables.

Example of customized Python always running in isolated mode:

```
int main(int argc, char **argv)
{
    PyStatus status;

    PyConfig config;
    PyConfig_InitPythonConfig(&config);
    config.isolated = 1;

    /* Decode command line arguments.
        Implicitly preinitialize Python (in isolated mode). */
    status = PyConfig_SetBytesArgv(&config, argc, argv);
    if (PyStatus_Exception(status)) {
        goto fail;
    }

    status = Py_InitializeFromConfig(&config);
    if (PyStatus_Exception(status)) {
        goto fail;
    }
    PyConfig_Clear(&config);
    return Py_RunMain();
```

```
fail:
    PyConfig_Clear(&config);
    if (PyStatus_IsExit(status)) {
        return status.exitcode;
    }
    /* Display the error message and exit the process with
        non-zero exit code */
    Py_ExitStatusException(status);
}
```

# 10.9 Path Configuration

*PyConfiq* contains multiple fields for the path configuration:

- Path configuration inputs:
  - PyConfig.home
  - PyConfig.pathconfig\_warnings
  - PyConfig.program\_name
  - PyConfig.pythonpath\_env
  - current working directory: to get absolute paths
  - PATH environment variable to get the program full path (from PyConfig.program\_name)
  - PYVENV\_LAUNCHER\_\_ environment variable
  - (Windows only) Application paths in the registry under "SoftwarePythonPythonCoreX.YPythonPath" of HKEY\_CURRENT\_USER and HKEY\_LOCAL\_MACHINE (where X.Y is the Python version).
- Path configuration output fields:
  - PyConfig.base exec prefix
  - PyConfig.base\_executable
  - PyConfig.base\_prefix
  - PyConfig.exec\_prefix
  - PyConfig.executable
  - PyConfig.module\_search\_paths\_set, PyConfig.module\_search\_paths
  - PyConfig.prefix

If at least one "output field" is not set, Python calculates the path configuration to fill unset fields. If  $module\_search\_paths\_set$  is equal to 0,  $module\_search\_paths$  is overridden and  $module\_search\_paths\_set$  is set to 1.

It is possible to completely ignore the function calculating the default path configuration by setting explicitly all path configuration output fields listed above. A string is considered as set even if it is non-empty. module\_search\_paths is considered as set if module\_search\_paths\_set is set to 1. In this case, path configuration input fields are ignored as well.

Set pathconfig\_warnings to 0 to suppress warnings when calculating the path configuration (Unix only, Windows does not log any warning).

If base\_prefix or base\_exec\_prefix fields are not set, they inherit their value from prefix and exec\_prefix respectively.

Py\_RunMain() and Py\_Main() modify sys.path:

- If run\_filename is set and is a directory which contains a \_\_main\_\_.py script, prepend run\_filename to sys.path.
- If isolated is zero:
  - If run\_module is set, prepend the current directory to sys.path. Do nothing if the current directory cannot be read.
  - If run\_filename is set, prepend the directory of the filename to sys.path.
  - Otherwise, prepend an empty string to sys.path.

If <code>site\_import</code> is non-zero, <code>sys.path</code> can be modified by the <code>site</code> module. If <code>user\_site\_directory</code> is non-zero and the user's site-package directory exists, the <code>site</code> module appends the user's site-package directory to <code>sys.path</code>.

The following configuration files are used by the path configuration:

- pyvenv.cfg
- python.\_pth (Windows only)
- pybuilddir.txt (Unix only)

The \_\_PYVENV\_LAUNCHER\_\_ environment variable is used to set PyConfig.base\_executable

# 10.10 Py\_RunMain()

int Py\_RunMain (void)

Execute the command (PyConfig.run\_command), the script (PyConfig.run\_filename) or the module (PyConfig.run module) specified on the command line or in the configuration.

By default and when if -i option is used, run the REPL.

Finally, finalizes Python and returns an exit status that can be passed to the exit () function.

See Python Configuration for an example of customized Python always running in isolated mode using Py\_RunMain().

## 10.11 Multi-Phase Initialization Private Provisional API

This section is a private provisional API introducing multi-phase initialization, the core feature of the PEP 432:

- "Core" initialization phase, "bare minimum Python":
  - Builtin types;
  - Builtin exceptions;
  - Builtin and frozen modules;
  - The sys module is only partially initialized (ex: sys.path doesn't exist yet).
- "Main" initialization phase, Python is fully initialized:
  - Install and configure importlib;
  - Apply the Path Configuration;

- Install signal handlers;
- Finish sys module initialization (ex: create sys.stdout and sys.path);
- Enable optional features like faulthandler and tracemalloc;
- Import the site module;
- etc.

#### Private provisional API:

• PyConfig.\_init\_main: if set to 0, Py\_InitializeFromConfig() stops at the "Core" initialization phase.

### PyStatus \_Py\_InitializeMain (void)

Move to the "Main" initialization phase, finish the Python initialization.

No module is imported during the "Core" phase and the importlib module is not configured: the *Path Configuration* is only applied during the "Main" phase. It may allow to customize Python in Python to override or tune the *Path Configuration*, maybe install a custom sys.meta\_path importer or an import hook, etc.

It may become possible to calculatin the *Path Configuration* in Python, after the Core phase and before the Main phase, which is one of the **PEP 432** motivation.

The "Core" phase is not properly defined: what should be and what should not be available at this phase is not specified yet. The API is marked as private and provisional: the API can be modified or even be removed anytime until a proper public API is designed.

Example running Python code between "Core" and "Main" initialization phases:

```
void init_python(void)
   PyStatus status;
   PyConfig config;
   PyConfig_InitPythonConfig(&config);
   config._init_main = 0;
   /* ... customize 'config' configuration ... */
   status = Py_InitializeFromConfig(&config);
   PyConfig_Clear(&config);
   if (PyStatus_Exception(status)) {
       Py_ExitStatusException(status);
   /* Use sys.stderr because sys.stdout is only created
      by _Py_InitializeMain() */
   int res = PyRun_SimpleString(
       "import sys; "
       "print('Run Python code before _Py_InitializeMain', "
               "file=sys.stderr)");
   if (res < 0) {
       exit(1);
   /* ... put more configuration code here ... */
   status = _Py_InitializeMain();
   if (PyStatus_Exception(status)) {
```

```
Py_ExitStatusException(status);
}
```

**CHAPTER** 

**ELEVEN** 

### MEMORY MANAGEMENT

### 11.1 Overview

Memory management in Python involves a private heap containing all Python objects and data structures. The management of this private heap is ensured internally by the *Python memory manager*. The Python memory manager has different components which deal with various dynamic storage management aspects, like sharing, segmentation, preallocation or caching.

At the lowest level, a raw memory allocator ensures that there is enough room in the private heap for storing all Python-related data by interacting with the memory manager of the operating system. On top of the raw memory allocator, several object-specific allocators operate on the same heap and implement distinct memory management policies adapted to the peculiarities of every object type. For example, integer objects are managed differently within the heap than strings, tuples or dictionaries because integers imply different storage requirements and speed/space tradeoffs. The Python memory manager thus delegates some of the work to the object-specific allocators, but ensures that the latter operate within the bounds of the private heap.

It is important to understand that the management of the Python heap is performed by the interpreter itself and that the user has no control over it, even if they regularly manipulate object pointers to memory blocks inside that heap. The allocation of heap space for Python objects and other internal buffers is performed on demand by the Python memory manager through the Python/C API functions listed in this document.

To avoid memory corruption, extension writers should never try to operate on Python objects with the functions exported by the C library: malloc(), calloc(), realloc() and free(). This will result in mixed calls between the C allocator and the Python memory manager with fatal consequences, because they implement different algorithms and operate on different heaps. However, one may safely allocate and release memory blocks with the C library allocator for individual purposes, as shown in the following example:

```
PyObject *res;
char *buf = (char *) malloc(BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
...Do some I/O operation involving buf...
res = PyBytes_FromString(buf);
free(buf); /* malloc'ed */
return res;
```

In this example, the memory request for the I/O buffer is handled by the C library allocator. The Python memory manager is involved only in the allocation of the bytes object returned as a result.

In most situations, however, it is recommended to allocate memory from the Python heap specifically because the latter is under control of the Python memory manager. For example, this is required when the interpreter is extended with new object types written in C. Another reason for using the Python heap is the desire to *inform* the Python memory manager about the memory needs of the extension module. Even when the requested memory is used exclusively for internal,

highly-specific purposes, delegating all memory requests to the Python memory manager causes the interpreter to have a more accurate image of its memory footprint as a whole. Consequently, under certain circumstances, the Python memory manager may or may not trigger appropriate actions, like garbage collection, memory compaction or other preventive procedures. Note that by using the C library allocator as shown in the previous example, the allocated memory for the I/O buffer escapes completely the Python memory manager.

### See also:

The PYTHONMALLOC environment variable can be used to configure the memory allocators used by Python.

The PYTHONMALLOCSTATS environment variable can be used to print statistics of the *pymalloc memory allocator* every time a new pymalloc object arena is created, and on shutdown.

## 11.2 Raw Memory Interface

The following function sets are wrappers to the system allocator. These functions are thread-safe, the *GIL* does not need to be held.

The *default raw memory allocator* uses the following functions: malloc(), calloc(), realloc() and free(); call malloc(1) (or calloc(1, 1)) when requesting zero bytes.

New in version 3.4.

### void\* PyMem\_RawMalloc (size\_t n)

Allocates n bytes and returns a pointer of type void\* to the allocated memory, or NULL if the request fails.

Requesting zero bytes returns a distinct non-NULL pointer if possible, as if PyMem\_RawMalloc(1) had been called instead. The memory will not have been initialized in any way.

#### void\* PyMem\_RawCalloc (size\_t nelem, size\_t elsize)

Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type void\* to the allocated memory, or *NULL* if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-NULL pointer if possible, as if PyMem RawCalloc(1, 1) had been called instead.

New in version 3.5.

### void\* PyMem\_RawRealloc (void \*p, size\_t n)

Resizes the memory block pointed to by p to n bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If p is NULL, the call is equivalent to PyMem\_RawMalloc(n); else if n is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-NULL.

Unless p is NULL, it must have been returned by a previous call to  $PyMem_RawMalloc()$ ,  $PyMem_RawRealloc()$  or  $PyMem_RawCalloc()$ .

If the request fails,  $PyMem_RawRealloc()$  returns NULL and p remains a valid pointer to the previous memory area.

### $void PyMem_RawFree (void *p)$

Frees the memory block pointed to by p, which must have been returned by a previous call to PyMem\_RawMalloc(), PyMem\_RawRealloc() or PyMem\_RawCalloc(). Otherwise, or if PyMem RawFree(p) has been called before, undefined behavior occurs.

If *p* is *NULL*, no operation is performed.

# 11.3 Memory Interface

The following function sets, modeled after the ANSI C standard, but specifying behavior when requesting zero bytes, are available for allocating and releasing memory from the Python heap.

The default memory allocator uses the pymalloc memory allocator.

Warning: The GIL must be held when using these functions.

Changed in version 3.6: The default allocator is now pymalloc instead of system malloc().

### void\* PyMem\_Malloc (size\_t n)

Allocates n bytes and returns a pointer of type void\* to the allocated memory, or NULL if the request fails.

Requesting zero bytes returns a distinct non-NULL pointer if possible, as if PyMem\_Malloc(1) had been called instead. The memory will not have been initialized in any way.

### void\* PyMem\_Calloc (size\_t nelem, size\_t elsize)

Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type void\* to the allocated memory, or *NULL* if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-NULL pointer if possible, as if PyMem\_Calloc(1, 1) had been called instead.

New in version 3.5.

### void\* **PyMem\_Realloc** (void \*p, size\_t n)

Resizes the memory block pointed to by p to n bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If p is NULL, the call is equivalent to PyMem\_Malloc(n); else if n is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-NULL.

Unless p is NULL, it must have been returned by a previous call to  $PyMem\_Malloc()$ ,  $PyMem\_Realloc()$  or  $PyMem\_Calloc()$ .

If the request fails,  $PyMem_Realloc()$  returns NULL and p remains a valid pointer to the previous memory area.

#### void **PyMem\_Free** (void \*p)

Frees the memory block pointed to by p, which must have been returned by a previous call to  $PyMem\_Malloc()$ ,  $PyMem\_Realloc()$  or  $PyMem\_Calloc()$ . Otherwise, or if  $PyMem\_Free(p)$  has been called before, undefined behavior occurs.

If *p* is *NULL*, no operation is performed.

The following type-oriented macros are provided for convenience. Note that TYPE refers to any C type.

### TYPE\* **PyMem\_New** (TYPE, size\_t *n*)

Same as  $PyMem\_Malloc()$ , but allocates (n \* sizeof(TYPE)) bytes of memory. Returns a pointer cast to TYPE\*. The memory will not have been initialized in any way.

### TYPE\* **PyMem** Resize (void \*p, TYPE, size t n)

Same as  $PyMem_Realloc()$ , but the memory block is resized to (n \* sizeof(TYPE)) bytes. Returns a pointer cast to TYPE\*. On return, p will be a pointer to the new memory area, or NULL in the event of failure.

This is a C preprocessor macro; p is always reassigned. Save the original value of p to avoid losing memory when handling errors.

```
void PyMem_Del (void *p)
Same as PyMem_Free().
```

In addition, the following macro sets are provided for calling the Python memory allocator directly, without involving the C API functions listed above. However, note that their use does not preserve binary compatibility across Python versions and is therefore deprecated in extension modules.

- PyMem\_MALLOC(size)
- PyMem NEW(type, size)
- PyMem\_REALLOC(ptr, size)
- PyMem\_RESIZE(ptr, type, size)
- PyMem\_FREE (ptr)
- PyMem\_DEL(ptr)

## 11.4 Object allocators

The following function sets, modeled after the ANSI C standard, but specifying behavior when requesting zero bytes, are available for allocating and releasing memory from the Python heap.

The default object allocator uses the pymalloc memory allocator.

**Warning:** The *GIL* must be held when using these functions.

### void\* PyObject Malloc (size t n)

Allocates n bytes and returns a pointer of type void\* to the allocated memory, or NULL if the request fails.

Requesting zero bytes returns a distinct non-NULL pointer if possible, as if PyObject\_Malloc(1) had been called instead. The memory will not have been initialized in any way.

```
void* PyObject_Calloc (size_t nelem, size_t elsize)
```

Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type void\* to the allocated memory, or *NULL* if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-NULL pointer if possible, as if PyObject\_Calloc(1, 1) had been called instead.

New in version 3.5.

### void\* PyObject\_Realloc (void\*p, $size_t n$ )

Resizes the memory block pointed to by p to n bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If p is NULL, the call is equivalent to PyObject\_Malloc(n); else if n is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-NULL.

Unless p is NULL, it must have been returned by a previous call to  $PyObject\_Malloc()$ ,  $PyObject\_Realloc()$  or  $PyObject\_Calloc()$ .

If the request fails,  $PyObject\_Realloc()$  returns NULL and p remains a valid pointer to the previous memory area.

#### void PyObject\_Free (void \*p)

Frees the memory block pointed to by p, which must have been returned by a previous call to

PyObject\_Malloc(), PyObject\_Realloc() or PyObject\_Calloc(). Otherwise, or if PyObject\_Free(p) has been called before, undefined behavior occurs.

If *p* is *NULL*, no operation is performed.

# 11.5 Default Memory Allocators

Default memory allocators:

Configuration	Name	PyMem_RawMallo	cPyMem_Malloc	PyOb- ject_Malloc
Release build	"pymalloc"	malloc	pymalloc	pymalloc
Debug build	"pymalloc_debug	"malloc + debug	pymalloc+de- bug	pymalloc+de- bug
Release build, without py- malloc	"malloc"	malloc	malloc	malloc
Debug build, without py-malloc	"malloc_debug"	malloc + debug	malloc + debug	malloc + debug

## Legend:

- Name: value for PYTHONMALLOC environment variable
- malloc: system allocators from the standard C library, C functions: malloc(), calloc(), realloc() and free()
- pymalloc: pymalloc memory allocator
- "+ debug": with debug hooks installed by PyMem\_SetupDebugHooks()

# 11.6 Customize Memory Allocators

New in version 3.4.

## PyMemAllocatorEx

Structure used to describe a memory block allocator. The structure has four fields:

Field	Meaning
void *ctx	user context passed as first argument
<pre>void* malloc(void *ctx, size_t size)</pre>	allocate a memory block
<pre>void* calloc(void *ctx, size_t nelem, size_t</pre>	allocate a memory block initialized with
elsize)	zeros
<pre>void* realloc(void *ctx, void *ptr, size_t</pre>	allocate or resize a memory block
new_size)	
<pre>void free(void *ctx, void *ptr)</pre>	free a memory block

Changed in version 3.5: The PyMemAllocator structure was renamed to PyMemAllocatorEx and a new calloc field was added.

## PyMemAllocatorDomain

Enum used to identify an allocator domain. Domains:

#### PYMEM DOMAIN RAW

#### Functions:

- PyMem\_RawMalloc()
- PyMem\_RawRealloc()
- PyMem\_RawCalloc()
- PyMem RawFree()

## PYMEM DOMAIN MEM

#### Functions:

- PyMem\_Malloc(),
- PyMem\_Realloc()
- PyMem\_Calloc()
- PyMem\_Free()

## PYMEM\_DOMAIN\_OBJ

#### Functions:

- PyObject\_Malloc()
- PyObject\_Realloc()
- PyObject\_Calloc()
- PyObject Free()

 $void \ \textbf{PyMem\_GetAllocator} \ (\textit{PyMemAllocatorDomain domain}, \textit{PyMemAllocatorEx} \ * allocator)$ 

Get the memory block allocator of the specified domain.

void PyMem\_SetAllocator (PyMemAllocatorDomain domain, PyMemAllocatorEx \*allocator)

Set the memory block allocator of the specified domain.

The new allocator must return a distinct non-NULL pointer when requesting zero bytes.

For the PYMEM\_DOMAIN\_RAW domain, the allocator must be thread-safe: the GIL is not held when the allocator is called.

If the new allocator is not a hook (does not call the previous allocator), the <code>PyMem\_SetupDebugHooks()</code> function must be called to reinstall the debug hooks on top on the new allocator.

## void PyMem\_SetupDebugHooks (void)

Setup hooks to detect bugs in the Python memory allocator functions.

Newly allocated memory is filled with the byte 0xDD (CLEANBYTE), freed memory is filled with the byte 0xDD (DEADBYTE). Memory blocks are surrounded by "forbidden bytes" (FORBIDDENBYTE: byte 0xFD).

## Runtime checks:

- Detect API violations, ex: PyObject\_Free() called on a buffer allocated by PyMem\_Malloc()
- Detect write before the start of the buffer (buffer underflow)
- Detect write after the end of the buffer (buffer overflow)
- Check that the *GIL* is held when allocator functions of *PYMEM\_DOMAIN\_OBJ* (ex: *PyObject\_Malloc()*) and *PYMEM\_DOMAIN\_MEM* (ex: *PyMem\_Malloc()*) domains are called

On error, the debug hooks use the tracemalloc module to get the traceback where a memory block was allocated. The traceback is only displayed if tracemalloc is tracing Python memory allocations and the memory block was traced.

These hooks are *installed by default* if Python is compiled in debug mode. The PYTHONMALLOC environment variable can be used to install debug hooks on a Python compiled in release mode.

Changed in version 3.6: This function now also works on Python compiled in release mode. On error, the debug hooks now use tracemalloc to get the traceback where a memory block was allocated. The debug hooks now also check if the GIL is held when functions of <code>PYMEM\_DOMAIN\_OBJ</code> and <code>PYMEM\_DOMAIN\_MEM</code> domains are called.

Changed in version 3.8: Byte patterns  $0 \times CB$  (CLEANBYTE),  $0 \times DB$  (DEADBYTE) and  $0 \times FB$  (FORBIDDENBYTE) have been replaced with  $0 \times CD$ ,  $0 \times DD$  and  $0 \times FD$  to use the same values than Windows CRT debug malloc() and free().

# 11.7 The pymalloc allocator

Python has a *pymalloc* allocator optimized for small objects (smaller or equal to 512 bytes) with a short lifetime. It uses memory mappings called "arenas" with a fixed size of 256 KiB. It falls back to <code>PyMem\_RawMalloc()</code> and <code>PyMem\_RawRealloc()</code> for allocations larger than 512 bytes.

pymalloc is the default allocator of the PYMEM\_DOMAIN\_MEM (ex: PyMem\_Malloc()) and PYMEM\_DOMAIN\_OBJ (ex: PyObject\_Malloc()) domains.

The arena allocator uses the following functions:

- VirtualAlloc() and VirtualFree() on Windows,
- mmap() and munmap() if available,
- malloc() and free() otherwise.

# 11.7.1 Customize pymalloc Arena Allocator

New in version 3.4.

#### PyObjectArenaAllocator

Structure used to describe an arena allocator. The structure has three fields:

Field	Meaning
void *ctx	user context passed as first argument
<pre>void* alloc(void *ctx, size_t size)</pre>	allocate an arena of size bytes
<pre>void free(void *ctx, size_t size, void *ptr)</pre>	free an arena

PyObject\_GetArenaAllocator (PyObjectArenaAllocator \*allocator)

Get the arena allocator.

PyObject\_SetArenaAllocator (PyObjectArenaAllocator \*allocator)

Set the arena allocator.

## 11.8 tracemalloc C API

New in version 3.7.

# 11.9 Examples

Here is the example from section *Overview*, rewritten so that the I/O buffer is allocated from the Python heap by using the first function set:

```
PyObject *res;
char *buf = (char *) PyMem_Malloc(BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
/* ...Do some I/O operation involving buf... */
res = PyBytes_FromString(buf);
PyMem_Free(buf); /* allocated with PyMem_Malloc */
return res;
```

The same code using the type-oriented function set:

```
PyObject *res;
char *buf = PyMem_New(char, BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
/* ...Do some I/O operation involving buf... */
res = PyBytes_FromString(buf);
PyMem_Del(buf); /* allocated with PyMem_New */
return res;
```

Note that in the two examples above, the buffer is always manipulated via functions belonging to the same set. Indeed, it is required to use the same memory API family for a given memory block, so that the risk of mixing different allocators is reduced to a minimum. The following code sequence contains two errors, one of which is labeled as *fatal* because it mixes two different allocators operating on different heaps.

```
char *buf1 = PyMem_New(char, BUFSIZ);
char *buf2 = (char *) malloc(BUFSIZ);
char *buf3 = (char *) PyMem_Malloc(BUFSIZ);
...
PyMem_Del(buf3); /* Wrong -- should be PyMem_Free() */
free(buf2); /* Right -- allocated via malloc() */
free(buf1); /* Fatal -- should be PyMem_Del() */
```

In addition to the functions aimed at handling raw memory blocks from the Python heap, objects in Python are allocated and released with  $PyObject\_New()$ ,  $PyObject\_NewVar()$  and  $PyObject\_Del()$ .

These will be explained in the next chapter on defining and implementing new object types in C.

## **OBJECT IMPLEMENTATION SUPPORT**

This chapter describes the functions, types, and macros used when defining new object types.

# 12.1 Allocating Objects on the Heap

```
PyObject* _PyObject_New (PyTypeObject *type)
```

Return value: New reference.

PyVarObject\* \_PyObject\_NewVar (PyTypeObject \*type, Py\_ssize\_t size)

Return value: New reference.

## PyObject\* PyObject\_Init (PyObject \*op, PyTypeObject \*type)

Return value: Borrowed reference. Initialize a newly-allocated object op with its type and initial reference. Returns the initialized object. If type indicates that the object participates in the cyclic garbage detector, it is added to the detector's set of observed objects. Other fields of the object are not affected.

## PyVarObject\* PyObject\_InitVar (PyVarObject \*op, PyTypeObject \*type, Py\_ssize\_t size)

*Return value: Borrowed reference.* This does everything *PyObject\_Init()* does, and also initializes the length information for a variable-size object.

## TYPE\* PyObject\_New (TYPE, PyTypeObject \*type)

Return value: New reference. Allocate a new Python object using the C structure type TYPE and the Python type object type. Fields not defined by the Python object header are not initialized; the object's reference count will be one. The size of the memory allocation is determined from the tp\_basicsize field of the type object.

## TYPE\* PyObject\_NewVar (TYPE, PyTypeObject \*type, Py\_ssize\_t size)

Return value: New reference. Allocate a new Python object using the C structure type TYPE and the Python type object type. Fields not defined by the Python object header are not initialized. The allocated memory allows for the TYPE structure plus size fields of the size given by the  $tp\_itemsize$  field of type. This is useful for implementing objects like tuples, which are able to determine their size at construction time. Embedding the array of fields into the same allocation decreases the number of allocations, improving the memory management efficiency.

## void PyObject\_Del (void \*op)

Releases memory allocated to an object using  $PyObject\_New()$  or  $PyObject\_NewVar()$ . This is normally called from the  $tp\_dealloc$  handler specified in the object's type. The fields of the object should not be accessed after this call as the memory is no longer a valid Python object.

## PyObject \_Py\_NoneStruct

Object which is visible in Python as None. This should only be accessed using the  $Py\_None$  macro, which evaluates to a pointer to this object.

#### See also:

PyModule\_Create() To allocate and create extension modules.

# 12.2 Common Object Structures

There are a large number of structures which are used in the definition of object types for Python. This section describes these structures and how they are used.

All Python objects ultimately share a small number of fields at the beginning of the object's representation in memory. These are represented by the *PyObject* and *PyVarObject* types, which are defined, in turn, by the expansions of some macros also used, whether directly or indirectly, in the definition of all other Python objects.

### PyObject |

All object types are extensions of this type. This is a type which contains the information Python needs to treat a pointer to an object as an object. In a normal "release" build, it contains only the object's reference count and a pointer to the corresponding type object. Nothing is actually declared to be a PyObject, but every pointer to a Python object can be cast to a PyObject\*. Access to the members must be done by using the macros Py\_REFCNT and Py\_TYPE.

### PyVarObject

This is an extension of *PyObject* that adds the ob\_size field. This is only used for objects that have some notion of *length*. This type does not often appear in the Python/C API. Access to the members must be done by using the macros *Py\_REFCNT*, *Py\_TYPE*, and *Py\_SIZE*.

## PyObject\_HEAD

This is a macro used when declaring new types which represent objects without a varying length. The PyObject\_HEAD macro expands to:

```
PyObject ob_base;
```

See documentation of PyObject above.

## PyObject\_VAR\_HEAD

This is a macro used when declaring new types which represent objects with a length that varies from instance to instance. The PyObject\_VAR\_HEAD macro expands to:

```
PyVarObject ob_base;
```

See documentation of PyVarObject above.

## Py\_TYPE (o)

This macro is used to access the ob\_type member of a Python object. It expands to:

```
(((PyObject*)(o))->ob_type)
```

## Py\_REFCNT (o)

This macro is used to access the ob\_refent member of a Python object. It expands to:

```
(((PyObject*)(o))->ob_refcnt)
```

#### Py\_SIZE (o)

This macro is used to access the ob\_size member of a Python object. It expands to:

```
((((PyVarObject*)(o))->ob_size)
```

#### PyObject HEAD INIT (type)

This is a macro which expands to initialization values for a new PyObject type. This macro expands to:

```
_PyObject_EXTRA_INIT
1, type,
```

## PyVarObject\_HEAD\_INIT (type, size)

This is a macro which expands to initialization values for a new PyVarObject type, including the ob\_size field. This macro expands to:

```
_PyObject_EXTRA_INIT
1, type, size,
```

## PyCFunction

Type of the functions used to implement most Python callables in C. Functions of this type take two PyObject\* parameters and return one such value. If the return value is NULL, an exception shall have been set. If not NULL, the return value is interpreted as the return value of the function as exposed in Python. The function must return a new reference.

## PyCFunctionWithKeywords

Type of the functions used to implement Python callables in C with signature <code>METH\_VARARGS</code> | <code>METH\_KEYWORDS</code>.

### \_PyCFunctionFast

Type of the functions used to implement Python callables in C with signature METH\_FASTCALL.

## \_PyCFunctionFastWithKeywords

Type of the functions used to implement Python callables in C with signature <code>METH\_FASTCALL</code> | <code>METH\_KEYWORDS</code>.

#### PyMethodDef

Structure used to describe a method of an extension type. This structure has four fields:

Field	С Туре	Meaning	
ml_name	const char *	name of the method	
ml_meth	PyCFunction	pointer to the C implementation	
ml_flags	int	flag bits indicating how the call should be constructed	
ml_doc	const char *	points to the contents of the docstring	

The ml\_meth is a C function pointer. The functions may be of different types, but they always return PyObject\*. If the function is not of the PyCFunction, the compiler will require a cast in the method table. Even though PyCFunction defines the first parameter as PyObject\*, it is common that the method implementation uses the specific C type of the self object.

The ml\_flags field is a bitfield which can include the following flags. The individual flags indicate either a calling convention or a binding convention.

There are four basic calling conventions for positional arguments and two of them can be combined with METH\_KEYWORDS to support also keyword arguments. So there are a total of 6 calling conventions:

#### METH VARARGS

This is the typical calling convention, where the methods have the type PyCFunction. The function expects two PyObject\* values. The first one is the *self* object for methods; for module functions, it is the module object. The second parameter (often called *args*) is a tuple object representing all arguments. This parameter is typically processed using  $PyArg\_ParseTuple()$  or  $PyArg\_UnpackTuple()$ .

## METH\_VARARGS | METH\_KEYWORDS

Methods with these flags must be of type *PyCFunctionWithKeywords*. The function expects three parameters: *self*, *args*, *kwargs* where *kwargs* is a dictionary of all the keyword arguments or possibly *NULL* if there are no keyword arguments. The parameters are typically processed using *PyArg\_ParseTupleAndKeywords*().

## METH\_FASTCALL

Fast calling convention supporting only positional arguments. The methods have the type \_PyCFunctionFast.

The first parameter is *self*, the second parameter is a C array of *PyObject\** values indicating the arguments and the third parameter is the number of arguments (the length of the array).

This is not part of the *limited API*.

New in version 3.7.

### METH\_FASTCALL | METH\_KEYWORDS

Extension of METH\_FASTCALL supporting also keyword arguments, with methods of type \_PyCFunctionFastWithKeywords. Keyword arguments are passed the same way as in the vector-call protocol: there is an additional fourth PyObject\* parameter which is a tuple representing the names of the keyword arguments or possibly NULL if there are no keywords. The values of the keyword arguments are stored in the args array, after the positional arguments.

This is not part of the limited API.

New in version 3.7.

### METH\_NOARGS

Methods without parameters don't need to check whether arguments are given if they are listed with the METH\_NOARGS flag. They need to be of type PyCFunction. The first parameter is typically named self and will hold a reference to the module or object instance. In all cases the second parameter will be NULL.

#### METH O

Methods with a single object argument can be listed with the METH\_O flag, instead of invoking PyArg\_ParseTuple() with a "O" argument. They have the type PyCFunction, with the self parameter, and a PyObject\* parameter representing the single argument.

These two constants are not used to indicate the calling convention but the binding when use with methods of classes. These may not be used for functions defined for modules. At most one of these flags may be set for any given method.

## METH\_CLASS

The method will be passed the type object as the first parameter rather than an instance of the type. This is used to create *class methods*, similar to what is created when using the classmethod() built-in function.

#### METH STATIC

The method will be passed *NULL* as the first parameter rather than an instance of the type. This is used to create *static methods*, similar to what is created when using the staticmethod() built-in function.

One other constant controls whether a method is loaded in place of another definition with the same method name.

## METH\_COEXIST

The method will be loaded in place of existing definitions. Without *METH\_COEXIST*, the default is to skip repeated definitions. Since slot wrappers are loaded before the method table, the existence of a *sq\_contains* slot, for example, would generate a wrapped method named \_\_contains\_\_() and preclude the loading of a corresponding PyCFunction with the same name. With the flag defined, the PyCFunction will be loaded in place of the wrapper object and will co-exist with the slot. This is helpful because calls to PyCFunctions are optimized more than wrapper object calls.

## PvMemberDef

Structure which describes an attribute of a type which corresponds to a C struct member. Its fields are:

Field	C Type	Meaning	
name	const char *	name of the member	
type	int	the type of the member in the C struct	
offset	Py_ssize_t	the offset in bytes that the member is located on the type's object struct	
flags	int	flag bits indicating if the field should be read-only or writable	
doc	const char *	points to the contents of the docstring	

type can be one of many T macros corresponding to various C types. When the member is accessed in Python, it will be converted to the equivalent Python type.

Macro name	C type
T_SHORT	short
T_INT	int
T_LONG	long
T_FLOAT	float
T_DOUBLE	double
T_STRING	const char *
T_OBJECT	PyObject *
T_OBJECT_EX	PyObject *
T_CHAR	char
T_BYTE	char
T_UBYTE	unsigned char
T_UINT	unsigned int
T_USHORT	unsigned short
T_ULONG	unsigned long
T_BOOL	char
T_LONGLONG	long long
T_ULONGLONG	unsigned long long
T_PYSSIZET	Py_ssize_t

T\_OBJECT and T\_OBJECT\_EX differ in that T\_OBJECT returns None if the member is *NULL* and T\_OBJECT\_EX raises an AttributeError. Try to use T\_OBJECT\_EX over T\_OBJECT because T\_OBJECT\_EX handles use of the del statement on that attribute more correctly than T\_OBJECT.

flags can be 0 for write and read access or READONLY for read-only access. Using T\_STRING for type implies READONLY. T\_STRING data is interpreted as UTF-8. Only T\_OBJECT and T\_OBJECT\_EX members can be deleted. (They are set to *NULL*).

## PyGetSetDef

Structure to define property-like access for a type. See also description of the  $PyTypeObject.tp\_getset$  slot

Field	С Туре	Meaning
name	const char *	attribute name
get	getter	C Function to get the attribute
set	setter	optional C function to set or delete the attribute, if omitted the attribute is readonly
doc	const char *	optional docstring
closure	void *	optional function pointer, providing additional data for getter and setter

The get function takes one *PyObject\** parameter (the instance) and a function pointer (the associated closure):

```
typedef PyObject *(*getter)(PyObject *, void *);
```

It should return a new reference on success or NULL with a set exception on failure.

set functions take two PyObject\* parameters (the instance and the value to be set) and a function pointer (the associated closure):

```
typedef int (*setter)(PyObject *, PyObject *, void *);
```

In case the attribute should be deleted the second parameter is NULL. Should return 0 on success or -1 with a set exception on failure.

# 12.3 Type Objects

Perhaps one of the most important structures of the Python object system is the structure that defines a new type: the PyTypeObject structure. Type objects can be handled using any of the  $PyObject_*$  () or  $PyType_*$  () functions, but do not offer much that's interesting to most Python applications. These objects are fundamental to how objects behave, so they are very important to the interpreter itself and to any extension module that implements new types.

Type objects are fairly large compared to most of the standard types. The reason for the size is that each type object stores a large number of values, mostly C function pointers, each of which implements a small part of the type's functionality. The fields of the type object are examined in detail in this section. The fields will be described in the order in which they occur in the structure.

In addition to the following quick reference, the *Examples* section provides at-a-glance insight into the meaning and use of *PyTypeObject*.

## 12.3.1 Quick Reference

## "tp slots"

PyTypeObject Slot <sup>1</sup>	Туре	special methods/attrs		Info	2
			Ο.	ΓΕ	) [
<r> tp_name</r>	const char *	name	X	X	
tp_basicsize	Py_ssize_t		X	X	X
tp_itemsize	Py_ssize_t		2	X	X
tp_dealloc	destructor		X	X	X
tp_vectorcall_offset	Py_ssize_t				?
(tp_getattr)	getattrfunc	getattribute,getattr			G
(tp_setattr)	setattrfunc	setattr,delattr			G
tp_as_async	PyAsyncMethods*	sub-slots			%
tp_repr	reprfunc	repr	X	X	X
tp_as_number	PyNumberMethods*	sub-slots			%
tp_as_sequence	PySequenceMethods*	sub-slots			%
tp_as_mapping	PyMappingMethods*	sub-slots			%
tp_hash	hashfunc	hash	X		G
tp_call	ternaryfunc	call	2	X	X
tp_str	reprfunc	str	X		X
tp_getattro	getattrofunc	getattribute,getattr	X	X	G
tp_setattro	setattrofunc	setattr,delattr	X	X	G
tp_as_buffer	PyBufferProcs*				%
tp_flags	unsigned long		X	X	?
tp_doc	const char *	doc	X	X	
tp_traverse	traverseproc		2	X	G
tp_clear	inquiry			X	G
tp_richcompare	richcmpfunc	lt,le,eq,ne,	X		G
		gt,ge			
tp_weaklistoffset	Py_ssize_t		1	X	?

Continued on next page

PyTypeObject Slot <sup>1</sup>	Туре	special methods/attrs		nfo	)2
			0 7	ΓΕ	) T
tp_iter	getiterfunc	iter			X
tp_iternext	iternextfunc	next			X
tp_methods	PyMethodDef[]		XΣ	X.	
tp_members	PyMemberDef[]		7	X.	
tp_getset	PyGetSetDef[]		XΣ	X.	
tp_base	PyTypeObject*	base		Σ	<b>4</b>
tp_dict	PyObject*	dict		?	<u>'</u>
tp_descr_get	descrgetfunc	get			X
tp_descr_set	descrsetfunc	set,delete			X
tp_dictoffset	Py_ssize_t		7	X.	?
tp_init	initproc	init	XX	X.	X
tp_alloc	allocfunc		X	?	? ?
tp_new	newfunc	new	XX	?	? ?
tp_free	freefunc		XX	?	•
tp_is_gc	inquiry		7	X.	X
<tp_bases></tp_bases>	PyObject*	bases		~	-
<tp_mro></tp_mro>	PyObject*	mro		~	-
[tp_cache]	PyObject*				
[tp_subclasses]	PyObject*	subclasses			
[tp_weaklist]	PyObject*				
(tp_del)	destructor				
[tp_version_tag]	unsigned int				
tp_finalize	destructor	del			X

Table 1 - continued from previous page

If COUNT\_ALLOCS is defined then the following (internal-only) fields exist as well:

- tp\_allocs
- tp\_frees
- tp\_maxalloc
- tp\_prev
- tp\_next

Also see the inheritance column ("I").

#### "I": inheritance

```
{\tt X} - type slot is inherited via *PyType_Ready* if defined with a *NULL* value
```

Note that some slots are effectively inherited through the normal attribute lookup chain.

<sup>&</sup>lt;sup>1</sup> A slot name in parentheses indicates it is (effectively) deprecated. Names in angle brackets should be treated as read-only. Names in square brackets are for internal use only. "<R>" (as a prefix) means the field is required (must be non-*NULL*).

<sup>&</sup>lt;sup>2</sup> Columns:

<sup>&</sup>quot;O": set on PyBaseObject\_Type

<sup>&</sup>quot;T": set on PyType\_Type

**<sup>&</sup>quot;D"**: default (if slot is set to *NULL*)

X - \*PyType\_Ready\* sets this value if it is \*NULL\*

 $<sup>{\</sup>scriptstyle \sim}$  - \*PyType\_Ready\* always sets this value (it should be \*NULL\*)

<sup>? - \*</sup>PyType\_Ready\* may set this value depending on other slots

<sup>%</sup> - the slots of the sub-struct are inherited individually

G - inherited, but only in combination with other slots; see the slot's description

<sup>? -</sup> it's complicated; see the slot's description

## sub-slots

Slot	Туре	special methods
am_await	unaryfunc	await
am_aiter	unaryfunc	aiter
am_anext	unaryfunc	anext
_	1	— — —
nb_add	binaryfunc	addradd
nb_inplace_add	binaryfunc	iadd
nb_subtract	binaryfunc	sub rsub
nb_inplace_subtract	binaryfunc	sub
nb_multiply	binaryfunc	rmul
nb_inplace_multiply	binaryfunc	mul
nb_remainder	binaryfunc	
nb_inplace_remainder	binaryfunc	mod
nb_divmod	binaryfunc	divmod rdiv-
		mod
nb_power	ternaryfunc	
nb_inplace_power	ternaryfunc	pow
nb_negative	unaryfunc	neg
nb_positive	unaryfunc	pos
nb_absolute	unaryfunc	abs
nb_bool	inquiry	bool
nb_invert	unaryfunc	invert
nb_lshift	binaryfunc	lshiftrlshift
nb_inplace_lshift	binaryfunc	lshift
nb_rshift	binaryfunc	rshiftrrshift
nb_inplace_rshift	binaryfunc	rshift
nb_and	binaryfunc	andrand
nb_inplace_and	binaryfunc	and
nb_xor	binaryfunc	xorrxor
nb_inplace_xor	binaryfunc	xor
nb_or	binaryfunc	orror
nb_inplace_or	binaryfunc	or
nb_int	unaryfunc	int
nb_reserved	void *	
nb_float	unaryfunc	float
nb_floor_divide	binaryfunc	floordiv
nb_inplace_floor_divide	binaryfunc	floordiv
nb_true_divide	binaryfunc	truediv
nb_inplace_true_divide	binaryfunc	truediv
nb_index	unaryfunc	index
nb_matrix_multiply	binaryfunc	matmulrmat-
		mul
nb_inplace_matrix_multiply	binaryfunc	matmul
mp_length	lenfunc	len
mp_subscript	binaryfunc	getitem
mp_ass_subscript	objobjargproc	setitem,
		delitem

Continued on next page

Table 2 - continued from previous page

Slot	Type	special methods
sq_length	lenfunc	len
sq_concat	binaryfunc	add
sq_repeat	ssizeargfunc	mul
sq_item	ssizeargfunc	getitem
sq_ass_item	ssizeobjargproc	setitem
		delitem
sq_contains	objobjproc	contains
sq_inplace_concat	binaryfunc	iadd
sq_inplace_repeat	ssizeargfunc	imul
bf_getbuffer	getbufferproc()	
bf_releasebuffer	releasebufferproc()	

# slot typedefs

typedef	Parameter Types	Return Type
allocfunc		PyObject*
	PyTypeObject*	
	Py_ssize_t	
	1 y_5512C_t	
destructor	void *	void
freefunc	void *	void
traverseproc		int
	void *	
	visitproc	
	void *	
	Void	
newfunc		PyObject*
	PyObject*	
	PyObject*	
	PyObject*	
initproc		int
	PyObject*	
	PyObject*	
	PyObject*	
	D-06 - 04 *	DesObicat *
reprfunc getattrfunc	PyObject*	PyObject* PyObject*
getattiiunc		Pyobject
	PyObject*	
	const char *	
setattrfunc		int
setattriunc		int
	PyObject*	
	const char *	
	PyObject*	
getattrofunc		PyObject*
	PyObject *	
	PyObject *	
setattrofunc		int
	PyObject*	
	PyObject*	
	PyObject*	
descrgetfunc		PyObject*
	PyObject*	
	PyObject*	
	PyObject*	
188		oter 12 Object Implementation Suppor
descrsetfunc	Cnap	oter 12. Object Implementation Suppor
	PyObject*	
	PyObject*	
	ryobject.	

See *Slot Type typedefs* below for more detail.

## 12.3.2 PyTypeObject Definition

The structure definition for PyTypeObject can be found in Include/object.h. For convenience of reference, this repeats the definition found there:

```
typedef struct _typeobject {
   PyObject_VAR_HEAD
   const char *tp_name; /* For printing, in format "<module>.<name>" */
   Py_ssize_t tp_basicsize, tp_itemsize; /* For allocation */
   /* Methods to implement standard operations */
   destructor tp_dealloc;
   Py_ssize_t tp_vectorcall_offset;
   getattrfunc tp_getattr;
   setattrfunc tp_setattr;
   PyAsyncMethods *tp_as_async; /* formerly known as tp_compare (Python 2)
                                    or tp_reserved (Python 3) */
   reprfunc tp_repr;
   /* Method suites for standard classes */
   PyNumberMethods *tp_as_number;
   PySequenceMethods *tp_as_sequence;
   PyMappingMethods *tp_as_mapping;
   /* More standard operations (here for binary compatibility) */
   hashfunc tp_hash;
   ternaryfunc tp_call;
   reprfunc tp_str;
   getattrofunc tp_getattro;
   setattrofunc tp_setattro;
   /* Functions to access object as input/output buffer */
   PyBufferProcs *tp_as_buffer;
   /* Flags to define presence of optional/expanded features */
   unsigned long tp_flags;
   const char *tp_doc; /* Documentation string */
   /* call function for all accessible objects */
   traverseproc tp_traverse;
   /* delete references to contained objects */
   inquiry tp_clear;
   /* rich comparisons */
   richcmpfunc tp_richcompare;
   /* weak reference enabler */
   Py_ssize_t tp_weaklistoffset;
    /* Iterators */
```

(continues on next page)

(continued from previous page)

```
getiterfunc tp_iter;
   iternextfunc tp_iternext;
   /* Attribute descriptor and subclassing stuff */
   struct PyMethodDef *tp_methods;
   struct PyMemberDef *tp_members;
   struct PyGetSetDef *tp_getset;
   struct _typeobject *tp_base;
   PyObject *tp_dict;
   descrgetfunc tp_descr_get;
   descrsetfunc tp_descr_set;
   Py_ssize_t tp_dictoffset;
   initproc tp_init;
   allocfunc tp_alloc;
   newfunc tp_new;
   freefunc tp_free; /* Low-level free-memory routine */
   inquiry tp_is_gc; /* For PyObject_IS_GC */
   PyObject *tp_bases;
   PyObject *tp_mro; /* method resolution order */
   PyObject *tp_cache;
   PyObject *tp_subclasses;
   PyObject *tp_weaklist;
   destructor tp_del;
   /* Type attribute cache version tag. Added in version 2.6 */
   unsigned int tp_version_tag;
   destructor tp_finalize;
} PyTypeObject;
```

## 12.3.3 PyObject Slots

The type object structure extends the <code>PyVarObject</code> structure. The <code>ob\_size</code> field is used for dynamic types (created by <code>type\_new()</code>, usually called from a class statement). Note that <code>PyType\_Type</code> (the metatype) initializes <code>tp\_itemsize</code>, which means that its instances (i.e. type objects) <code>must</code> have the <code>ob\_size</code> field.

```
PyObject* PyObject._ob_next
PyObject* PyObject._ob_prev
```

These fields are only present when the macro Py\_TRACE\_REFS is defined. Their initialization to *NULL* is taken care of by the PyObject\_HEAD\_INIT macro. For statically allocated objects, these fields always remain *NULL*. For dynamically allocated objects, these two fields are used to link the object into a doubly-linked list of *all* live objects on the heap. This could be used for various debugging purposes; currently the only use is to print the objects that are still alive at the end of a run when the environment variable PYTHONDUMPREFS is set.

#### Inheritance:

These fields are not inherited by subtypes.

## Py\_ssize\_t PyObject.ob\_refcnt

This is the type object's reference count, initialized to 1 by the PyObject\_HEAD\_INIT macro. Note that for statically allocated type objects, the type's instances (objects whose ob\_type points back to the type) do *not* count as references. But for dynamically allocated type objects, the instances *do* count as references.

#### Inheritance:

This field is not inherited by subtypes.

## PyTypeObject\* PyObject.ob\_type

This is the type's type, in other words its metatype. It is initialized by the argument to the PyObject\_HEAD\_INIT macro, and its value should normally be &PyType\_Type. However, for dynamically loadable extension modules that must be usable on Windows (at least), the compiler complains that this is not a valid initializer. Therefore, the convention is to pass *NULL* to the PyObject\_HEAD\_INIT macro and to initialize this field explicitly at the start of the module's initialization function, before doing anything else. This is typically done like this:

```
Foo_Type.ob_type = &PyType_Type;
```

This should be done before any instances of the type are created.  $PyType\_Ready()$  checks if ob\_type is NULL, and if so, initializes it to the ob\_type field of the base class.  $PyType\_Ready()$  will not change this field if it is non-zero.

#### Inheritance:

This field is inherited by subtypes.

## 12.3.4 PyVarObject Slots

## Py\_ssize\_t PyVarObject.ob\_size

For statically allocated type objects, this should be initialized to zero. For dynamically allocated type objects, this field has a special internal meaning.

#### Inheritance:

This field is not inherited by subtypes.

# 12.3.5 PyTypeObject Slots

Each slot has a section describing inheritance. If  $PyType\_Ready()$  may set a value when the field is set to NULL then there will also be a "Default" section. (Note that many fields set on  $PyBaseObject\_Type$  and  $PyType\_Type$  effectively act as defaults.)

## const char\* PyTypeObject.tp\_name

Pointer to a NUL-terminated string containing the name of the type. For types that are accessible as module globals, the string should be the full module name, followed by a dot, followed by the type name; for built-in types, it should be just the type name. If the module is a submodule of a package, the full package name is part of the full module name. For example, a type named T defined in module M in subpackage Q in package P should have the  $tp\_name$  initializer "P.Q.M.T".

For dynamically allocated type objects, this should just be the type name, and the module name explicitly stored in the type dict as the value for key 'module'.

For statically allocated type objects, the tp\_name field should contain a dot. Everything before the last dot is made accessible as the \_\_module\_\_ attribute, and everything after the last dot is made accessible as the \_\_name\_\_ attribute.

If no dot is present, the entire <code>tp\_name</code> field is made accessible as the <code>\_\_name\_\_</code> attribute, and the <code>\_\_module\_\_</code> attribute is undefined (unless explicitly set in the dictionary, as explained above). This means your type will be impossible to pickle. Additionally, it will not be listed in module documentations created with pydoc.

This field must not be NULL. It is the only required field in PyTypeObject() (other than potentially  $tp\_itemsize$ ).

## Inheritance:

This field is not inherited by subtypes.

```
Py_ssize_t PyTypeObject.tp_basicsize
Py_ssize_t PyTypeObject.tp_itemsize
```

These fields allow calculating the size in bytes of instances of the type.

There are two kinds of types: types with fixed-length instances have a zero  $tp\_itemsize$  field, types with variable-length instances have a non-zero  $tp\_itemsize$  field. For a type with fixed-length instances, all instances have the same size, given in  $tp\_basicsize$ .

For a type with variable-length instances, the instances must have an ob\_size field, and the instance size is  $tp\_basicsize$  plus N times  $tp\_itemsize$ , where N is the "length" of the object. The value of N is typically stored in the instance's ob\_size field. There are exceptions: for example, ints use a negative ob\_size to indicate a negative number, and N is abs(ob\_size) there. Also, the presence of an ob\_size field in the instance layout doesn't mean that the instance structure is variable-length (for example, the structure for the list type has fixed-length instances, yet those instances have a meaningful ob\_size field).

The basic size includes the fields in the instance declared by the macro <code>PyObject\_HEAD</code> or <code>PyObject\_VAR\_HEAD</code> (whichever is used to declare the instance struct) and this in turn includes the <code>\_ob\_prev</code> and <code>\_ob\_next</code> fields if they are present. This means that the only correct way to get an initializer for the <code>tp\_basicsize</code> is to use the <code>sizeof</code> operator on the struct used to declare the instance layout. The basic size does not include the GC header size.

A note about alignment: if the variable items require a particular alignment, this should be taken care of by the value of  $tp\_basicsize$ . Example: suppose a type implements an array of double.  $tp\_itemsize$  is sizeof(double). It is the programmer's responsibility that  $tp\_basicsize$  is a multiple of sizeof(double) (assuming this is the alignment requirement for double).

For any type with variable-length instances, this field must not be *NULL*.

#### **Inheritance:**

These fields are inherited separately by subtypes. If the base type has a non-zero  $tp\_itemsize$ , it is generally not safe to set  $tp\_itemsize$  to a different non-zero value in a subtype (though this depends on the implementation of the base type).

#### destructor PyTypeObject.tp\_dealloc

A pointer to the instance destructor function. This function must be defined unless the type guarantees that its instances will never be deallocated (as is the case for the singletons None and Ellipsis). The function signature is:

```
void tp_dealloc(PyObject *self);
```

The destructor function is called by the  $Py\_DECREF()$  and  $Py\_XDECREF()$  macros when the new reference count is zero. At this point, the instance is still in existence, but there are no references to it. The destructor function should free all references which the instance owns, free all memory buffers owned by the instance (using the freeing function corresponding to the allocation function used to allocate the buffer), and call the type's  $tp\_free$  function. If the type is not subtypable (doesn't have the  $Py\_TPFLAGS\_BASETYPE$  flag bit set), it is permissible to call the object deallocator directly instead of via  $tp\_free$ . The object deallocator should be the one used to allocate the instance; this is normally  $PyObject\_Del()$  if the instance was allocated using  $PyObject\_New()$  or  $PyObject\_VarNew()$ , or  $PyObject\_GC\_Del()$  if the instance was allocated using  $PyObject\_GC\_New()$  or  $PyObject\_GC\_NewVar()$ .

Finally, if the type is heap allocated ( $Py\_TPFLAGS\_HEAPTYPE$ ), the deallocator should decrement the reference count for its type object after calling the type deallocator. In order to avoid dangling pointers, the recommended way to achieve this is:

```
static void foo_dealloc(foo_object *self) {
    PyTypeObject *tp = Py_TYPE(self);
```

(continues on next page)

(continued from previous page)

```
// free references and buffers here
tp->tp_free(self);
Py_DECREF(tp);
}
```

#### Inheritance:

This field is inherited by subtypes.

## Py\_ssize\_t PyTypeObject.tp\_vectorcall\_offset

An optional offset to a per-instance function that implements calling the object using the *vectorcall* protocol, a more efficient alternative of the simpler  $tp\_call$ .

This field is only used if the flag \_Py\_TPFLAGS\_HAVE\_VECTORCALL is set. If so, this must be a positive integer containing the offset in the instance of a vectorcallfunc pointer. The signature is the same as for \_PyObject\_Vectorcall():

```
PyObject *vectorcallfunc(PyObject *callable, PyObject *const *args, size_t nargsf, 
PyObject *kwnames)
```

The *vectorcallfunc* pointer may be zero, in which case the instance behaves as if \_Py\_TPFLAGS\_HAVE\_VECTORCALL was not set: calling the instance falls back to tp\_call.

Any class that sets  $_{PY\_TPFLAGS\_HAVE\_VECTORCALL}$  must also set  $_{tp\_call}$  and make sure its behaviour is consistent with the *vectorcallfunc* function. This can be done by setting  $_{tp\_call}$  to  $_{tp\_call}$ 

```
PyObject *PyVectorcall_Call (PyObject *callable, PyObject *tuple, PyObject *dict)
```

Call callable's vectorcallfunc with positional and keyword arguments given in a tuple and dict, respectively.

This function is intended to be used in the tp\_call slot. It does not fall back to tp\_call and it currently does not check the  $_{Py\_TPFLAGS\_HAVE\_VECTORCALL}$  flag. To call an object, use one of the  $_{PyObject\_Call}$  functions instead.

**Note:** It is not recommended for *heap types* to implement the vectorcall protocol. When a user sets \_\_call\_ in Python code, only tp\_call is updated, possibly making it inconsistent with the vectorcall function.

**Note:** The semantics of the tp\_vectorcall\_offset slot are provisional and expected to be finalized in Python 3.9. If you use vectorcall, plan for updating your code for Python 3.9.

Changed in version 3.8: This slot was used for print formatting in Python 2.x. In Python 3.0 to 3.7, it was reserved and named tp print.

#### Inheritance:

This field is inherited by subtypes together with  $tp\_call$ : a subtype inherits  $tp\_vectorcall\_offset$  from its base type when the subtype's  $tp\_call$  is NULL.

Note that *heap types* (including subclasses defined in Python) do not inherit the \_Py\_TPFLAGS\_HAVE\_VECTORCALL flag.

## getattrfunc PyTypeObject.tp\_getattr

An optional pointer to the get-attribute-string function.

This field is deprecated. When it is defined, it should point to a function that acts the same as the  $tp\_getattro$  function, but taking a C string instead of a Python string object to give the attribute name.

#### Inheritance:

```
Group: tp_getattr, tp_getattro
```

This field is inherited by subtypes together with  $tp\_getattro$ : a subtype inherits both  $tp\_getattr$  and  $tp\_getattro$  from its base type when the subtype's  $tp\_getattr$  and  $tp\_getattro$  are both NULL.

## setattrfunc PyTypeObject.tp\_setattr

An optional pointer to the function for setting and deleting attributes.

This field is deprecated. When it is defined, it should point to a function that acts the same as the  $tp\_setattro$  function, but taking a C string instead of a Python string object to give the attribute name.

#### **Inheritance:**

```
Group: tp_setattr, tp_setattro
```

This field is inherited by subtypes together with  $tp\_setattro$ : a subtype inherits both  $tp\_setattr$  and  $tp\_setattro$  from its base type when the subtype's  $tp\_setattr$  and  $tp\_setattro$  are both NULL.

## PyAsyncMethods\* PyTypeObject.tp\_as\_async

Pointer to an additional structure that contains fields relevant only to objects which implement *awaitable* and *asynchronous iterator* protocols at the C-level. See *Async Object Structures* for details.

New in version 3.5: Formerly known as tp\_compare and tp\_reserved.

#### Inheritance:

The tp as async field is not inherited, but the contained fields are inherited individually.

### reprfunc PyTypeObject.tp\_repr

An optional pointer to a function that implements the built-in function repr ().

The signature is the same as for PyObject Repr():

```
PyObject *tp_repr(PyObject *self);
```

The function must return a string or a Unicode object. Ideally, this function should return a string that, when passed to eval(), given a suitable environment, returns an object with the same value. If this is not feasible, it should return a string starting with '<' and ending with '>' from which both the type and the value of the object can be deduced.

## **Inheritance:**

This field is inherited by subtypes.

#### **Default:**

When this field is not set, a string of the form <%s object at %p> is returned, where %s is replaced by the type name, and %p by the object's memory address.

## PyNumberMethods\* PyTypeObject.tp\_as\_number

Pointer to an additional structure that contains fields relevant only to objects which implement the number protocol. These fields are documented in *Number Object Structures*.

### **Inheritance:**

The tp\_as\_number field is not inherited, but the contained fields are inherited individually.

## PySequenceMethods\* PyTypeObject.tp\_as\_sequence

Pointer to an additional structure that contains fields relevant only to objects which implement the sequence protocol. These fields are documented in *Sequence Object Structures*.

## Inheritance:

The tp as sequence field is not inherited, but the contained fields are inherited individually.

### PyMappingMethods\* PyTypeObject.tp\_as\_mapping

Pointer to an additional structure that contains fields relevant only to objects which implement the mapping protocol. These fields are documented in *Mapping Object Structures*.

#### **Inheritance:**

The  $tp\_as\_mapping$  field is not inherited, but the contained fields are inherited individually.

## hashfunc PyTypeObject.tp\_hash

An optional pointer to a function that implements the built-in function hash ().

The signature is the same as for PyObject\_Hash():

```
Py_hash_t tp_hash(PyObject *);
```

The value -1 should not be returned as a normal return value; when an error occurs during the computation of the hash value, the function should set an exception and return -1.

When this field is not set (and tp\_richcompare is not set), an attempt to take the hash of the object raises TypeError. This is the same as setting it to PyObject\_HashNotImplemented().

This field can be set explicitly to <code>PyObject\_HashNotImplemented()</code> to block inheritance of the hash method from a parent type. This is interpreted as the equivalent of <code>\_\_hash\_\_ = None</code> at the Python level, causing <code>isinstance(o, collections.Hashable)</code> to correctly return <code>False</code>. Note that the converse is also true - setting <code>\_\_hash\_\_ = None</code> on a class at the Python level will result in the <code>tp\_hash</code> slot being set to <code>PyObject\_HashNotImplemented()</code>.

#### **Inheritance:**

Group: tp\_hash, tp\_richcompare

This field is inherited by subtypes together with  $tp\_richcompare$ : a subtype inherits both of  $tp\_richcompare$  and  $tp\_hash$ , when the subtype's  $tp\_richcompare$  and  $tp\_hash$  are both NULL.

## ternaryfunc PyTypeObject.tp\_call

An optional pointer to a function that implements calling the object. This should be NULL if the object is not callable. The signature is the same as for  $PyObject\_Call()$ :

```
PyObject *tp_call(PyObject *self, PyObject *args, PyObject *kwargs);
```

## **Inheritance:**

This field is inherited by subtypes.

## reprfunc PyTypeObject.tp\_str

An optional pointer to a function that implements the built-in operation str(). (Note that str is a type now, and str() calls the constructor for that type. This constructor calls PyObject\_Str() to do the actual work, and PyObject\_Str() will call this handler.)

The signature is the same as for PyObject\_Str():

```
PyObject *tp_str(PyObject *self);
```

The function must return a string or a Unicode object. It should be a "friendly" string representation of the object, as this is the representation that will be used, among other things, by the print () function.

## **Inheritance:**

This field is inherited by subtypes.

#### **Default:**

When this field is not set, PyObject\_Repr() is called to return a string representation.

## getattrofunc PyTypeObject.tp\_getattro

An optional pointer to the get-attribute function.

The signature is the same as for PyObject\_GetAttr():

```
PyObject *tp_getattro(PyObject *self, PyObject *attr);
```

It is usually convenient to set this field to PyObject\_GenericGetAttr(), which implements the normal way of looking for object attributes.

#### **Inheritance:**

Group: tp\_getattr, tp\_getattro

This field is inherited by subtypes together with  $tp\_getattr$ : a subtype inherits both  $tp\_getattr$  and  $tp\_getattro$  from its base type when the subtype's  $tp\_getattr$  and  $tp\_getattro$  are both NULL.

#### **Default:**

PyBaseObject\_Type uses PyObject\_GenericGetAttr().

## setattrofunc PyTypeObject.tp\_setattro

An optional pointer to the function for setting and deleting attributes.

The signature is the same as for PyObject\_SetAttr():

```
PyObject *tp_setattro(PyObject *self, PyObject *attr, PyObject *value);
```

In addition, setting *value* to *NULL* to delete an attribute must be supported. It is usually convenient to set this field to *PyObject\_GenericSetAttr()*, which implements the normal way of setting object attributes.

#### Inheritance:

Group: tp\_setattr, tp\_setattro

This field is inherited by subtypes together with  $tp\_setattr$ : a subtype inherits both  $tp\_setattr$  and  $tp\_setattr$  from its base type when the subtype's  $tp\_setattr$  and  $tp\_setattr$  are both NULL.

#### **Default:**

PyBaseObject\_Type uses PyObject\_GenericSetAttr().

## PyBufferProcs\* PyTypeObject.tp\_as\_buffer

Pointer to an additional structure that contains fields relevant only to objects which implement the buffer interface. These fields are documented in *Buffer Object Structures*.

#### **Inheritance:**

The tp\_as\_buffer field is not inherited, but the contained fields are inherited individually.

### unsigned long PyTypeObject.tp\_flags

This field is a bit mask of various flags. Some flags indicate variant semantics for certain situations; others are used to indicate that certain fields in the type object (or in the extension structures referenced via  $tp\_as\_number$ ,  $tp\_as\_sequence$ ,  $tp\_as\_mapping$ , and  $tp\_as\_buffer$ ) that were historically not always present are valid; if such a flag bit is clear, the type fields it guards must not be accessed and must be considered to have a zero or NULL value instead.

## **Inheritance:**

Inheritance of this field is complicated. Most flag bits are inherited individually, i.e. if the base type has a flag bit set, the subtype inherits this flag bit. The flag bits that pertain to extension structures are strictly inherited if the extension structure is inherited, i.e. the base type's value of the flag bit is copied into the subtype together with a pointer to the extension structure. The <code>Py\_TPFLAGS\_HAVE\_GC</code> flag bit is inherited together with the

tp\_traverse and tp\_clear fields, i.e. if the Py\_TPFLAGS\_HAVE\_GC flag bit is clear in the subtype and the tp\_traverse and tp\_clear fields in the subtype exist and have NULL values.

#### **Default:**

PyBaseObject\_Type uses Py\_TPFLAGS\_DEFAULT | Py\_TPFLAGS\_BASETYPE.

#### **Bit Masks:**

The following bit masks are currently defined; these can be ORed together using the | operator to form the value of the  $tp\_flags$  field. The macro  $PyType\_HasFeature()$  takes a type and a flags value, tp and f, and checks whether  $tp->tp\_flags$  & f is non-zero.

## Py\_TPFLAGS\_HEAPTYPE

This bit is set when the type object itself is allocated on the heap, for example, types created dynamically using  $PyType\_FromSpec()$ . In this case, the ob\_type field of its instances is considered a reference to the type, and the type object is INCREF'ed when a new instance is created, and DECREF'ed when an instance is destroyed (this does not apply to instances of subtypes; only the type referenced by the instance's ob\_type gets INCREF'ed or DECREF'ed).

#### **Inheritance:**

???

## Py\_TPFLAGS\_BASETYPE

This bit is set when the type can be used as the base type of another type. If this bit is clear, the type cannot be subtyped (similar to a "final" class in Java).

#### Inheritance:

???

## Py\_TPFLAGS\_READY

This bit is set when the type object has been fully initialized by PyType\_Ready().

### **Inheritance:**

???

## Py\_TPFLAGS\_READYING

This bit is set while PyType\_Ready () is in the process of initializing the type object.

## **Inheritance:**

???

### Py TPFLAGS HAVE GC

This bit is set when the object supports garbage collection. If this bit is set, instances must be created using  $PyObject\_GC\_New()$  and destroyed using  $PyObject\_GC\_Del()$ . More information in section Supporting Cyclic Garbage Collection. This bit also implies that the GC-related fields  $tp\_traverse$  and  $tp\_clear$  are present in the type object.

## **Inheritance:**

```
Group: Py_TPFLAGS_HAVE_GC, tp_traverse, tp_clear
```

The  $Py\_TPFLAGS\_HAVE\_GC$  flag bit is inherited together with the tp\_traverse and tp\_clear fields, i.e. if the  $Py\_TPFLAGS\_HAVE\_GC$  flag bit is clear in the subtype and the tp\_traverse and tp\_clear fields in the subtype exist and have NULL values.

## Py\_TPFLAGS\_DEFAULT

This is a bitmask of all the bits that pertain to the existence of certain fields in the type object and its extension structures. Currently, it includes the following bits: Py\_TPFLAGS\_HAVE\_STACKLESS\_EXTENSION, Py\_TPFLAGS\_HAVE\_VERSION\_TAG.

#### **Inheritance:**

???

## Py\_TPFLAGS\_METHOD\_DESCRIPTOR

This bit indicates that objects behave like unbound methods.

If this flag is set for type (meth), then:

- meth.\_\_get\_\_(obj, cls) (\*args, \*\*kwds) (with obj not None) must be equivalent to meth(obj, \*args, \*\*kwds).
- meth.\_\_get\_\_(None, cls)(\*args, \*\*kwds) must be equivalent to meth(\*args, \*\*kwds).

This flag enables an optimization for typical method calls like obj.meth(): it avoids creating a temporary "bound method" object for obj.meth.

New in version 3.8.

#### **Inheritance:**

This flag is never inherited by heap types. For extension types, it is inherited whenever  $tp\_descr\_get$  is inherited.

```
Py_TPFLAGS_LONG_SUBCLASS
```

Py\_TPFLAGS\_LIST\_SUBCLASS

Py\_TPFLAGS\_TUPLE\_SUBCLASS

Py TPFLAGS BYTES SUBCLASS

Py\_TPFLAGS\_UNICODE\_SUBCLASS

Py\_TPFLAGS\_DICT\_SUBCLASS

Py\_TPFLAGS\_BASE\_EXC\_SUBCLASS

## Py\_TPFLAGS\_TYPE\_SUBCLASS

These flags are used by functions such as  $PyLong\_Check$  () to quickly determine if a type is a subclass of a built-in type; such specific checks are faster than a generic check, like  $PyObject\_IsInstance$  (). Custom types that inherit from built-ins should have their  $tp\_flags$  set appropriately, or the code that interacts with such types will behave differently depending on what kind of check is used.

## Py TPFLAGS HAVE FINALIZE

This bit is set when the  $tp\_finalize$  slot is present in the type structure.

New in version 3.4.

Deprecated since version 3.8: This flag isn't necessary anymore, as the interpreter assumes the  $tp\_finalize$  slot is always present in the type structure.

## Py\_TPFLAGS\_HAVE\_VECTORCALL

This bit is set when the class implements the vectorcall protocol. See tp\_vectorcall\_offset for details.

#### **Inheritance:**

This bit is set on *static* subtypes if  $tp\_flags$  is not overridden: a subtype inherits  $_py\_tpflags\_have\_vectorcall$  from its base type when the subtype's  $tp\_call$  is NULL and the subtype's  $py\_tpflags\_heaptype$  is not set.

*Heap types* do not inherit \_Py\_TPFLAGS\_HAVE\_VECTORCALL.

**Note:** This flag is provisional and expected to become public in Python 3.9, with a different name and, possibly, changed semantics. If you use vectorcall, plan for updating your code for Python 3.9.

New in version 3.8.

## const char\* PyTypeObject.tp\_doc

An optional pointer to a NUL-terminated C string giving the docstring for this type object. This is exposed as the \_\_doc\_\_ attribute on the type and instances of the type.

#### Inheritance:

This field is *not* inherited by subtypes.

#### traverseproc PyTypeObject.tp\_traverse

An optional pointer to a traversal function for the garbage collector. This is only used if the Py\_TPFLAGS\_HAVE\_GC flag bit is set. The signature is:

```
int tp_traverse(PyObject *self, visitproc visit, void *arg);
```

More information about Python's garbage collection scheme can be found in section Supporting Cyclic Garbage Collection.

The  $tp\_traverse$  pointer is used by the garbage collector to detect reference cycles. A typical implementation of a  $tp\_traverse$  function simply calls  $Py\_VISIT()$  on each of the instance's members that are Python objects. For example, this is function local\_traverse() from the \_thread extension module:

```
static int
local_traverse(localobject *self, visitproc visit, void *arg)
{
    Py_VISIT(self->args);
    Py_VISIT(self->kw);
    Py_VISIT(self->dict);
    return 0;
}
```

Note that  $Py\_VISIT()$  is called only on those members that can participate in reference cycles. Although there is also a self->key member, it can only be NULL or a Python string and therefore cannot be part of a reference cycle.

On the other hand, even if you know a member can never be part of a cycle, as a debugging aid you may want to visit it anyway just so the gc module's get\_referents() function will include it.

Note that  $Py\_VISIT()$  requires the *visit* and *arg* parameters to local\_traverse() to have these specific names; don't name them just anything.

#### Inheritance:

```
Group: Py_TPFLAGS_HAVE_GC, tp_traverse, tp_clear
```

This field is inherited by subtypes together with  $tp\_clear$  and the  $Py\_TPFLAGS\_HAVE\_GC$  flag bit: the flag bit,  $tp\_traverse$ , and  $tp\_clear$  are all inherited from the base type if they are all zero in the subtype.

## inquiry PyTypeObject.tp\_clear

An optional pointer to a clear function for the garbage collector. This is only used if the *Py\_TPFLAGS\_HAVE\_GC* flag bit is set. The signature is:

```
int tp_clear(PyObject *);
```

The  $tp\_clear$  member function is used to break reference cycles in cyclic garbage detected by the garbage collector. Taken together, all  $tp\_clear$  functions in the system must combine to break all reference cycles. This is subtle, and if in any doubt supply a  $tp\_clear$  function. For example, the tuple type does not implement a  $tp\_clear$  function, because it's possible to prove that no reference cycle can be composed entirely of tuples. Therefore the  $tp\_clear$  functions of other types must be sufficient to break any cycle containing a tuple. This isn't immediately obvious, and there's rarely a good reason to avoid implementing  $tp\_clear$ .

Implementations of  $tp\_clear$  should drop the instance's references to those of its members that may be Python objects, and set its pointers to those members to *NULL*, as in the following example:

```
static int
local_clear(localobject *self)
{
    Py_CLEAR(self->key);
    Py_CLEAR(self->args);
    Py_CLEAR(self->kw);
    Py_CLEAR(self->kw);
    return 0;
}
```

The  $Py\_CLEAR()$  macro should be used, because clearing references is delicate: the reference to the contained object must not be decremented until after the pointer to the contained object is set to NULL. This is because decrementing the reference count may cause the contained object to become trash, triggering a chain of reclamation activity that may include invoking arbitrary Python code (due to finalizers, or weakref callbacks, associated with the contained object). If it's possible for such code to reference self again, it's important that the pointer to the contained object be NULL at that time, so that self knows the contained object can no longer be used. The  $Py\_CLEAR()$  macro performs the operations in a safe order.

Because the goal of  $tp\_clear$  functions is to break reference cycles, it's not necessary to clear contained objects like Python strings or Python integers, which can't participate in reference cycles. On the other hand, it may be convenient to clear all contained Python objects, and write the type's  $tp\_dealloc$  function to invoke  $tp\_clear$ .

More information about Python's garbage collection scheme can be found in section *Supporting Cyclic Garbage Collection*.

## Inheritance:

```
Group: Py_TPFLAGS_HAVE_GC, tp_traverse, tp_clear
```

This field is inherited by subtypes together with  $tp\_traverse$  and the  $Py\_TPFLAGS\_HAVE\_GC$  flag bit: the flag bit,  $tp\_traverse$ , and  $tp\_clear$  are all inherited from the base type if they are all zero in the subtype.

## richcmpfunc PyTypeObject.tp\_richcompare

An optional pointer to the rich comparison function, whose signature is:

```
PyObject *tp_richcompare(PyObject *self, PyObject *other, int op);
```

The first parameter is guaranteed to be an instance of the type that is defined by PyTypeObject.

The function should return the result of the comparison (usually Py\_True or Py\_False). If the comparison is undefined, it must return Py\_NotImplemented, if another error occurred it must return NULL and set an exception condition.

The following constants are defined to be used as the third argument for  $tp\_richcompare$  and for  $PyObject\_RichCompare$ ():

Constant	Comparison
Py_LT	<
Py_LE	<=
Py_EQ	==
Py_NE	!=
Py_GT	>
Py_GE	>=

The following macro is defined to ease writing rich comparison functions:

## PyObject \*Py\_RETURN\_RICHCOMPARE (VAL\_A, VAL\_B, int op)

Return Py\_True or Py\_False from the function, depending on the result of a comparison. VAL\_A and VAL\_B must be orderable by C comparison operators (for example, they may be C ints or floats). The third argument specifies the requested operation, as for  $PyObject\_RichCompare()$ .

The return value's reference count is properly incremented.

On error, sets an exception and returns NULL from the function.

New in version 3.7.

#### Inheritance:

Group: tp\_hash, tp\_richcompare

This field is inherited by subtypes together with  $tp\_hash$ : a subtype inherits  $tp\_richcompare$  and  $tp\_hash$  when the subtype's  $tp\_richcompare$  and  $tp\_hash$  are both NULL.

#### **Default:**

PyBaseObject\_Type provides a tp\_richcompare implementation, which may be inherited. However, if only tp\_hash is defined, not even the inherited function is used and instances of the type will not be able to participate in any comparisons.

## Py\_ssize\_t PyTypeObject.tp\_weaklistoffset

If the instances of this type are weakly referenceable, this field is greater than zero and contains the offset in the instance structure of the weak reference list head (ignoring the GC header, if present); this offset is used by PyObject\_ClearWeakRefs() and the PyWeakref\_\*() functions. The instance structure needs to include a field of type PyObject\* which is initialized to NULL.

Do not confuse this field with  $tp\_weaklist$ ; that is the list head for weak references to the type object itself.

#### Inheritance:

This field is inherited by subtypes, but see the rules listed below. A subtype may override this offset; this means that the subtype uses a different weak reference list head than the base type. Since the list head is always found via <code>tp\_weaklistoffset</code>, this should not be a problem.

When a type defined by a class statement has no  $\_slots\_$  declaration, and none of its base types are weakly referenceable, the type is made weakly referenceable by adding a weak reference list head slot to the instance layout and setting the  $tp\_weaklistoffset$  of that slot's offset.

When a type's \_\_slots\_\_ declaration contains a slot named \_\_weakref\_\_, that slot becomes the weak reference list head for instances of the type, and the slot's offset is stored in the type's tp\_weaklistoffset.

When a type's \_\_slots\_\_ declaration does not contain a slot named \_\_weakref\_\_, the type inherits its tp\_weaklistoffset from its base type.

## getiterfunc PyTypeObject.tp\_iter

An optional pointer to a function that returns an iterator for the object. Its presence normally signals that the instances of this type are iterable (although sequences may be iterable without this function).

This function has the same signature as PyObject\_GetIter():

```
PyObject *tp_iter(PyObject *self);
```

#### Inheritance:

This field is inherited by subtypes.

## iternextfunc PyTypeObject.tp\_iternext

An optional pointer to a function that returns the next item in an iterator. The signature is:

```
PyObject *tp_iternext(PyObject *self);
```

When the iterator is exhausted, it must return *NULL*; a StopIteration exception may or may not be set. When another error occurs, it must return *NULL* too. Its presence signals that the instances of this type are iterators.

Iterator types should also define the  $tp\_iter$  function, and that function should return the iterator instance itself (not a new iterator instance).

This function has the same signature as PyIter\_Next().

#### **Inheritance:**

This field is inherited by subtypes.

### struct PyMethodDef\* PyTypeObject.tp\_methods

An optional pointer to a static *NULL*-terminated array of *PyMethodDef* structures, declaring regular methods of this type.

For each entry in the array, an entry is added to the type's dictionary (see  $tp\_dict$  below) containing a method descriptor.

### Inheritance:

This field is not inherited by subtypes (methods are inherited through a different mechanism).

## struct PyMemberDef\* PyTypeObject.tp\_members

An optional pointer to a static *NULL*-terminated array of *PyMemberDef* structures, declaring regular data members (fields or slots) of instances of this type.

For each entry in the array, an entry is added to the type's dictionary (see  $tp\_dict$  below) containing a member descriptor.

#### **Inheritance:**

This field is not inherited by subtypes (members are inherited through a different mechanism).

## struct PyGetSetDef\* PyTypeObject.tp\_getset

An optional pointer to a static NULL-terminated array of PyGetSetDef structures, declaring computed attributes of instances of this type.

For each entry in the array, an entry is added to the type's dictionary (see  $tp\_dict$  below) containing a getset descriptor.

### **Inheritance:**

This field is not inherited by subtypes (computed attributes are inherited through a different mechanism).

## PyTypeObject\* PyTypeObject.tp\_base

An optional pointer to a base type from which type properties are inherited. At this level, only single inheritance is supported; multiple inheritance require dynamically creating a type object by calling the metatype.

**Note:** Slot initialization is subject to the rules of initializing globals. C99 requires the initializers to be "address constants". Function designators like <code>PyType\_GenericNew()</code>, with implicit conversion to a pointer, are valid C99 address constants.

However, the unary '&' operator applied to a non-static variable like PyBaseObject\_Type() is not required to produce an address constant. Compilers may support this (gcc does), MSVC does not. Both compilers are strictly standard conforming in this particular behavior.

Consequently, tp base should be set in the extension module's init function.

#### **Inheritance:**

This field is not inherited by subtypes (obviously).

#### **Default:**

This field defaults to &PyBaseObject\_Type (which to Python programmers is known as the type object).

## PyObject\* PyTypeObject.tp\_dict

The type's dictionary is stored here by PyType\_Ready ().

This field should normally be initialized to *NULL* before PyType\_Ready is called; it may also be initialized to a dictionary containing initial attributes for the type. Once *PyType\_Ready()* has initialized the type, extra attributes for the type may be added to this dictionary only if they don't correspond to overloaded operations (like \_\_add\_\_()).

#### Inheritance:

This field is not inherited by subtypes (though the attributes defined in here are inherited through a different mechanism).

#### **Default:**

If this field is *NULL*, *PyType\_Ready()* will assign a new dictionary to it.

**Warning:** It is not safe to use  $PyDict\_SetItem()$  on or otherwise modify  $tp\_dict$  with the dictionary C-API.

## descreetfunc PyTypeObject.tp\_descr\_get

An optional pointer to a "descriptor get" function.

The function signature is:

```
PyObject * tp_descr_get(PyObject *self, PyObject *obj, PyObject *type);
```

### **Inheritance:**

This field is inherited by subtypes.

## descrsetfunc PyTypeObject.tp\_descr\_set

An optional pointer to a function for setting and deleting a descriptor's value.

The function signature is:

```
int tp_descr_set(PyObject *self, PyObject *obj, PyObject *value);
```

The *value* argument is set to *NULL* to delete the value.

#### **Inheritance:**

This field is inherited by subtypes.

## Py\_ssize\_t PyTypeObject.tp\_dictoffset

If the instances of this type have a dictionary containing instance variables, this field is non-zero and contains the offset in the instances of the type of the instance variable dictionary; this offset is used by <code>PyObject\_GenericGetAttr()</code>.

Do not confuse this field with tp dict; that is the dictionary for attributes of the type object itself.

If the value of this field is greater than zero, it specifies the offset from the start of the instance structure. If the value is less than zero, it specifies the offset from the end of the instance structure. A negative offset is more expensive to use, and should only be used when the instance structure contains a variable-length part. This is used for example to add an instance variable dictionary to subtypes of str or tuple. Note that the  $tp\_basicsize$  field should account for the dictionary added to the end in that case, even though the dictionary is not included in the basic object layout. On a system with a pointer size of 4 bytes,  $tp\_dictoffset$  should be set to -4 to indicate that the dictionary is at the very end of the structure.

The real dictionary offset in an instance can be computed from a negative tp\_dictoffset as follows:

```
dictoffset = tp_basicsize + abs(ob_size)*tp_itemsize + tp_dictoffset
if dictoffset is not aligned on sizeof(void*):
    round up to sizeof(void*)
```

where  $tp\_basicsize$ ,  $tp\_itemsize$  and  $tp\_dictoffset$  are taken from the type object, and ob\_size is taken from the instance. The absolute value is taken because ints use the sign of ob\_size to store the sign of the number. (There's never a need to do this calculation yourself; it is done for you by \_PyObject\_GetDictPtr().)

#### Inheritance:

This field is inherited by subtypes, but see the rules listed below. A subtype may override this offset; this means that the subtype instances store the dictionary at a difference offset than the base type. Since the dictionary is always found via tp\_dictoffset, this should not be a problem.

When a type defined by a class statement has no  $\_slots\_$  declaration, and none of its base types has an instance variable dictionary, a dictionary slot is added to the instance layout and the  $tp\_dictoffset$  is set to that slot's offset.

When a type defined by a class statement has a  $\__slots\__$  declaration, the type inherits its  $tp\_dictoffset$  from its base type.

(Adding a slot named \_\_dict\_\_ to the \_\_slots\_\_ declaration does not have the expected effect, it just causes confusion. Maybe this should be added as a feature just like \_\_weakref\_\_ though.)

#### **Default:**

This slot has no default. For static types, if the field is NULL then no \_\_\_dict\_\_ gets created for instances.

## initproc PyTypeObject.tp\_init

An optional pointer to an instance initialization function.

This function corresponds to the \_\_init\_\_() method of classes. Like \_\_init\_\_(), it is possible to create an instance without calling \_\_init\_\_(), and it is possible to reinitialize an instance by calling its \_\_init\_\_() method again.

The function signature is:

```
int tp_init(PyObject *self, PyObject *args, PyObject *kwds);
```

The self argument is the instance to be initialized; the *args* and *kwds* arguments represent positional and keyword arguments of the call to \_\_init\_\_().

The  $tp\_init$  function, if not NULL, is called when an instance is created normally by calling its type, after the type's  $tp\_new$  function has returned an instance of the type. If the  $tp\_new$  function returns an instance of some other type that is not a subtype of the original type, no  $tp\_init$  function is called; if  $tp\_new$  returns an instance of a subtype of the original type, the subtype's  $tp\_init$  is called.

Returns 0 on success, -1 and sets an exception on error.

#### Inheritance:

This field is inherited by subtypes.

#### **Default:**

For static types this field does not have a default.

## allocfunc PyTypeObject.tp\_alloc

An optional pointer to an instance allocation function.

The function signature is:

```
PyObject *tp_alloc(PyTypeObject *self, Py_ssize_t nitems);
```

#### Inheritance:

This field is inherited by static subtypes, but not by dynamic subtypes (subtypes created by a class statement).

#### **Default**:

For dynamic subtypes, this field is always set to  $PyType\_GenericAlloc()$ , to force a standard heap allocation strategy.

For static subtypes, PyBaseObject\_Type uses PyType\_GenericAlloc(). That is the recommended value for all statically defined types.

## newfunc PyTypeObject.tp\_new

An optional pointer to an instance creation function.

The function signature is:

```
PyObject *tp_new(PyTypeObject *subtype, PyObject *args, PyObject *kwds);
```

The subtype argument is the type of the object being created; the *args* and *kwds* arguments represent positional and keyword arguments of the call to the type. Note that subtype doesn't have to equal the type whose  $tp\_new$  function is called; it may be a subtype of that type (but not an unrelated type).

The  $tp\_new$  function should call subtype->tp\_alloc(subtype, nitems) to allocate space for the object, and then do only as much further initialization as is absolutely necessary. Initialization that can safely be ignored or repeated should be placed in the  $tp\_init$  handler. A good rule of thumb is that for immutable types, all initialization should take place in  $tp\_new$ , while for mutable types, most initialization should be deferred to  $tp\_init$ .

#### Inheritance:

This field is inherited by subtypes, except it is not inherited by static types whose  $tp\_base$  is NULL or &PyBaseObject\_Type.

## **Default:**

For static types this field has no default. This means if the slot is defined as *NULL*, the type cannot be called to create new instances; presumably there is some other way to create instances, like a factory function.

## freefunc PyTypeObject.tp\_free

An optional pointer to an instance deallocation function. Its signature is:

```
void tp_free(void *self);
```

An initializer that is compatible with this signature is <code>PyObject\_Free()</code>.

#### Inheritance:

This field is inherited by static subtypes, but not by dynamic subtypes (subtypes created by a class statement)

#### Default:

In dynamic subtypes, this field is set to a deallocator suitable to match  $PyType\_GenericAlloc()$  and the value of the  $Py\_TPFLAGS\_HAVE\_GC$  flag bit.

For static subtypes, PyBaseObject\_Type uses PyObject\_Del.

### inquiry PyTypeObject.tp\_is\_gc

An optional pointer to a function called by the garbage collector.

The garbage collector needs to know whether a particular object is collectible or not. Normally, it is sufficient to look at the object's type's  $tp\_flags$  field, and check the  $Py\_TPFLAGS\_HAVE\_GC$  flag bit. But some types have a mixture of statically and dynamically allocated instances, and the statically allocated instances are not collectible. Such types should define this function; it should return 1 for a collectible instance, and 0 for a non-collectible instance. The signature is:

```
int tp_is_gc(PyObject *self);
```

(The only example of this are types themselves. The metatype,  $P_YType\_Type$ , defines this function to distinguish between statically and dynamically allocated types.)

#### Inheritance:

This field is inherited by subtypes.

#### **Default:**

This slot has no default. If this field is NULL, Py\_TPFLAGS\_HAVE\_GC is used as the functional equivalent.

#### PyObject\* PyTypeObject.tp bases

Tuple of base types.

This is set for types created by a class statement. It should be *NULL* for statically defined types.

#### Inheritance:

This field is not inherited.

### PyObject\* PyTypeObject.tp\_mro

Tuple containing the expanded set of base types, starting with the type itself and ending with object, in Method Resolution Order.

## Inheritance:

This field is not inherited; it is calculated fresh by PyType Ready ().

## PyObject\* PyTypeObject.tp\_cache

Unused. Internal use only.

### **Inheritance:**

This field is not inherited.

## PyObject\* PyTypeObject.tp\_subclasses

List of weak references to subclasses. Internal use only.

#### **Inheritance:**

This field is not inherited.

## PyObject\* PyTypeObject.tp\_weaklist

Weak reference list head, for weak references to this type object. Not inherited. Internal use only.

#### Inheritance:

This field is not inherited.

### destructor PyTypeObject.tp\_del

This field is deprecated. Use  $tp\_finalize$  instead.

## unsigned int PyTypeObject.tp\_version\_tag

Used to index into the method cache. Internal use only.

#### Inheritance:

This field is not inherited.

## destructor PyTypeObject.tp\_finalize

An optional pointer to an instance finalization function. Its signature is:

```
void tp_finalize(PyObject *self);
```

If  $tp\_finalize$  is set, the interpreter calls it once when finalizing an instance. It is called either from the garbage collector (if the instance is part of an isolated reference cycle) or just before the object is deallocated. Either way, it is guaranteed to be called before attempting to break reference cycles, ensuring that it finds the object in a sane state.

tp\_finalize should not mutate the current exception status; therefore, a recommended way to write a non-trivial finalizer is:

```
static void
local_finalize(PyObject *self)
{
    PyObject *error_type, *error_value, *error_traceback;

    /* Save the current exception, if any. */
    PyErr_Fetch(&error_type, &error_value, &error_traceback);

    /* ... */

    /* Restore the saved exception. */
    PyErr_Restore(error_type, error_value, error_traceback);
}
```

For this field to be taken into account (even through inheritance), you must also set the Py\_TPFLAGS\_HAVE\_FINALIZE flags bit.

#### Inheritance:

This field is inherited by subtypes.

New in version 3.4.

## See also:

"Safe object finalization" (PEP 442)

The remaining fields are only defined if the feature test macro COUNT\_ALLOCS is defined, and are for internal use only. They are documented here for completeness. None of these fields are inherited by subtypes.

```
Py_ssize_t PyTypeObject.tp_allocs
```

Number of allocations.

```
Py_ssize_t PyTypeObject.tp_frees
Number of frees.
```

```
Py_ssize_t PyTypeObject.tp_maxalloc
```

Maximum simultaneously allocated objects.

```
PyTypeObject* PyTypeObject.tp_prev
```

Pointer to the previous type object with a non-zero tp\_allocs field.

```
PyTypeObject* PyTypeObject.tp next
```

Pointer to the next type object with a non-zero tp\_allocs field.

Also, note that, in a garbage collected Python,  $tp\_dealloc$  may be called from any Python thread, not just the thread which created the object (if the object becomes part of a refcount cycle, that cycle might be collected by a garbage collection on any thread). This is not a problem for Python API calls, since the thread on which tp\_dealloc is called will own the Global Interpreter Lock (GIL). However, if the object being destroyed in turn destroys objects from some other C or C++ library, care should be taken to ensure that destroying those objects on the thread which called tp\_dealloc will not violate any assumptions of the library.

## 12.3.6 Heap Types

Traditionally, types defined in C code are *static*, that is, a static PyTypeObject structure is defined directly in code and initialized using  $PyType\_Ready()$ .

This results in types that are limited relative to types defined in Python:

- Static types are limited to one base, i.e. they cannot use multiple inheritance.
- Static type objects (but not necessarily their instances) are immutable. It is not possible to add or modify the type object's attributes from Python.
- Static type objects are shared across *sub-interpreters*, so they should not include any subinterpreter-specific state.

Also, since *PyTypeObject* is not part of the *stable ABI*, any extension modules using static types must be compiled for a specific Python minor version.

An alternative to static types is *heap-allocated types*, or *heap types* for short, which correspond closely to classes created by Python's class statement.

This is done by filling a PyType\_Spec structure and calling PyType\_FromSpecWithBases().

# 12.4 Number Object Structures

## PyNumberMethods

This structure holds pointers to the functions which an object uses to implement the number protocol. Each function is used by the function of similar name documented in the *Number Protocol* section.

Here is the structure definition:

```
typedef struct {
   binaryfunc nb_add;
   binaryfunc nb_subtract;
   binaryfunc nb_multiply;
   binaryfunc nb_remainder;
   binaryfunc nb_divmod;
   ternaryfunc nb_power;
   unaryfunc nb_negative;
```

(continues on next page)

(continued from previous page)

```
unaryfunc nb_positive;
    unaryfunc nb_absolute;
    inquiry nb_bool;
    unaryfunc nb_invert;
    binaryfunc nb_lshift;
    binaryfunc nb_rshift;
    binaryfunc nb_and;
    binaryfunc nb_xor;
    binaryfunc nb_or;
    unaryfunc nb_int;
    void *nb_reserved;
    unaryfunc nb_float;
    binaryfunc nb_inplace_add;
    binaryfunc nb_inplace_subtract;
    binaryfunc nb_inplace_multiply;
    binaryfunc nb_inplace_remainder;
    ternaryfunc nb_inplace_power;
    binaryfunc nb_inplace_lshift;
    binaryfunc nb_inplace_rshift;
    binaryfunc nb_inplace_and;
    binaryfunc nb_inplace_xor;
    binaryfunc nb_inplace_or;
    binaryfunc nb_floor_divide;
    binaryfunc nb_true_divide;
    binaryfunc nb_inplace_floor_divide;
    binaryfunc nb_inplace_true_divide;
    unaryfunc nb_index;
    binaryfunc nb_matrix_multiply;
    binaryfunc nb_inplace_matrix_multiply;
} PyNumberMethods;
```

**Note:** Binary and ternary functions must check the type of all their operands, and implement the necessary conversions (at least one of the operands is an instance of the defined type). If the operation is not defined for the given operands, binary and ternary functions must return Py\_NotImplemented, if another error occurred they must return *NULL* and set an exception.

**Note:** The nb\_reserved field should always be *NULL*. It was previously called nb\_long, and was renamed in Python 3.0.1.

```
binaryfunc PyNumberMethods.nb_add
binaryfunc PyNumberMethods.nb_subtract
binaryfunc PyNumberMethods.nb_multiply
binaryfunc PyNumberMethods.nb_remainder
binaryfunc PyNumberMethods.nb_divmod
ternaryfunc PyNumberMethods.nb power
```

```
unaryfunc PyNumberMethods.nb_negative
unaryfunc PyNumberMethods.nb_positive
unaryfunc PyNumberMethods.nb_absolute
inquiry PyNumberMethods.nb_bool
unaryfunc PyNumberMethods.nb invert
binaryfunc PyNumberMethods.nb lshift
binaryfunc PyNumberMethods.nb_rshift
binaryfunc PyNumberMethods.nb_and
binaryfunc PyNumberMethods.nb_xor
binaryfunc PyNumberMethods.nb_or
unaryfunc PyNumberMethods.nb_int
void *PyNumberMethods.nb_reserved
unaryfunc PyNumberMethods.nb_float
binaryfunc PyNumberMethods.nb_inplace_add
binaryfunc PyNumberMethods.nb_inplace_subtract
binaryfunc PyNumberMethods.nb inplace multiply
binaryfunc PyNumberMethods.nb_inplace_remainder
ternaryfunc PyNumberMethods.nb_inplace_power
binaryfunc PyNumberMethods.nb_inplace_lshift
binaryfunc PyNumberMethods.nb_inplace_rshift
binaryfunc PyNumberMethods.nb_inplace_and
binaryfunc PyNumberMethods.nb_inplace_xor
binaryfunc PyNumberMethods.nb_inplace_or
binaryfunc PyNumberMethods.nb_floor_divide
binaryfunc PyNumberMethods.nb_true_divide
binaryfunc PyNumberMethods.nb_inplace_floor_divide
binaryfunc PyNumberMethods.nb_inplace_true_divide
unaryfunc PyNumberMethods.nb_index
binaryfunc PyNumberMethods.nb_matrix_multiply
binaryfunc PyNumberMethods.nb_inplace_matrix_multiply
```

# 12.5 Mapping Object Structures

## PyMappingMethods

This structure holds pointers to the functions which an object uses to implement the mapping protocol. It has three members:

#### lenfunc PyMappingMethods.mp\_length

This function is used by PyMapping\_Size () and PyObject\_Size (), and has the same signature. This slot may be set to NULL if the object has no defined length.

## binaryfunc PyMappingMethods.mp\_subscript

This function is used by  $PyObject\_GetItem()$  and  $PySequence\_GetSlice()$ , and has the same signature as  $PyObject\_GetItem()$ . This slot must be filled for the  $PyMapping\_Check()$  function to return 1, it can be NULL otherwise.

### objobjargproc PyMappingMethods.mp\_ass\_subscript

This function is used by <code>PyObject\_SetItem()</code>, <code>PyObject\_DelItem()</code>, <code>PyObject\_SetSlice()</code> and <code>PyObject\_DelSlice()</code>. It has the same signature as <code>PyObject\_SetItem()</code>, but <code>v</code> can also be set to <code>NULL</code> to delete an item. If this slot is <code>NULL</code>, the object does not support item assignment and deletion.

# 12.6 Sequence Object Structures

#### PySequenceMethods

This structure holds pointers to the functions which an object uses to implement the sequence protocol.

## lenfunc PySequenceMethods.sq\_length

This function is used by  $PySequence\_Size()$  and  $PyObject\_Size()$ , and has the same signature. It is also used for handling negative indices via the  $sq\_item$  and the  $sq\_ass\_item$  slots.

#### binaryfunc PySequenceMethods.sq\_concat

This function is used by  $PySequence\_Concat$  () and has the same signature. It is also used by the + operator, after trying the numeric addition via the  $nb\_add$  slot.

#### ssizeargfunc PySequenceMethods.sq\_repeat

This function is used by PySequence\_Repeat () and has the same signature. It is also used by the \* operator, after trying numeric multiplication via the nb\_multiply slot.

#### ssizeargfunc PySequenceMethods.sq\_item

This function is used by  $PySequence\_GetItem()$  and has the same signature. It is also used by  $PyObject\_GetItem()$ , after trying the subscription via the  $mp\_subscript$  slot. This slot must be filled for the  $PySequence\_Check()$  function to return 1, it can be NULL otherwise.

Negative indexes are handled as follows: if the sq\_length slot is filled, it is called and the sequence length is used to compute a positive index which is passed to sq\_item. If sq\_length is *NULL*, the index is passed as is to the function.

#### ssizeobjargproc PySequenceMethods.sq ass item

This function is used by  $PySequence\_SetItem()$  and has the same signature. It is also used by  $PyObject\_SetItem()$  and  $PyObject\_DelItem()$ , after trying the item assignment and deletion via the  $mp\_ass\_subscript$  slot. This slot may be left to NULL if the object does not support item assignment and deletion.

## $objobjproc \ {\tt PySequenceMethods.sq\_contains}$

This function may be used by *PySequence\_Contains* () and has the same signature. This slot may be left to *NULL*, in this case *PySequence\_Contains* () simply traverses the sequence until it finds a match.

### binaryfunc PySequenceMethods.sq\_inplace\_concat

This function is used by  $PySequence\_InPlaceConcat()$  and has the same signature. It should modify its first operand, and return it. This slot may be left to NULL, in this case  $PySequence\_InPlaceConcat()$  will fall back to  $PySequence\_Concat()$ . It is also used by the augmented assignment +=, after trying numeric in-place addition via the  $nb\_inplace\_add$  slot.

#### ssizeargfunc PySequenceMethods.sq\_inplace\_repeat

This function is used by PySequence\_InPlaceRepeat () and has the same signature. It should modify its

first operand, and return it. This slot may be left to *NULL*, in this case PySequence\_InPlaceRepeat () will fall back to *PySequence\_Repeat* (). It is also used by the augmented assignment \*=, after trying numeric in-place multiplication via the *nb\_inplace\_multiply* slot.

## 12.7 Buffer Object Structures

### PyBufferProcs

This structure holds pointers to the functions required by the *Buffer protocol*. The protocol defines how an exporter object can expose its internal data to consumer objects.

### getbufferproc PyBufferProcs.bf\_getbuffer

The signature of this function is:

```
int (PyObject *exporter, Py_buffer *view, int flags);
```

Handle a request to *exporter* to fill in *view* as specified by *flags*. Except for point (3), an implementation of this function MUST take these steps:

- (1) Check if the request can be met. If not, raise PyExc\_BufferError, set view->obj to *NULL* and return -1.
- (2) Fill in the requested fields.
- (3) Increment an internal counter for the number of exports.
- (4) Set view->obj to exporter and increment view->obj.
- (5) Return 0.

If exporter is part of a chain or tree of buffer providers, two main schemes can be used:

- Re-export: Each member of the tree acts as the exporting object and sets view->obj to a new reference to
  itself.
- Redirect: The buffer request is redirected to the root object of the tree. Here, view->obj will be a new reference to the root object.

The individual fields of *view* are described in section *Buffer structure*, the rules how an exporter must react to specific requests are in section *Buffer request types*.

All memory pointed to in the *Py\_buffer* structure belongs to the exporter and must remain valid until there are no consumers left. *format*, *shape*, *strides*, *suboffsets* and *internal* are read-only for the consumer.

*PyBuffer\_FillInfo()* provides an easy way of exposing a simple bytes buffer while dealing correctly with all request types.

PyObject\_GetBuffer() is the interface for the consumer that wraps this function.

#### releasebufferproc PyBufferProcs.bf\_releasebuffer

The signature of this function is:

```
void (PyObject *exporter, Py_buffer *view);
```

Handle a request to release the resources of the buffer. If no resources need to be released, <code>PyBufferProcs.bf\_releasebuffer</code> may be <code>NULL</code>. Otherwise, a standard implementation of this function will take these optional steps:

- (1) Decrement an internal counter for the number of exports.
- (2) If the counter is 0, free all memory associated with *view*.

The exporter MUST use the *internal* field to keep track of buffer-specific resources. This field is guaranteed to remain constant, while a consumer MAY pass a copy of the original buffer as the *view* argument.

This function MUST NOT decrement view->obj, since that is done automatically in PyBuffer\_Release() (this scheme is useful for breaking reference cycles).

*PyBuffer\_Release()* is the interface for the consumer that wraps this function.

## 12.8 Async Object Structures

New in version 3.5.

### PyAsyncMethods

This structure holds pointers to the functions required to implement awaitable and asynchronous iterator objects.

Here is the structure definition:

```
typedef struct {
    unaryfunc am_await;
    unaryfunc am_aiter;
    unaryfunc am_anext;
} PyAsyncMethods;
```

#### unaryfunc PyAsyncMethods.am\_await

The signature of this function is:

```
PyObject *am_await(PyObject *self);
```

The returned object must be an iterator, i.e. PyIter\_Check () must return 1 for it.

This slot may be set to NULL if an object is not an awaitable.

#### unaryfunc PyAsyncMethods.am\_aiter

The signature of this function is:

```
PyObject *am_aiter(PyObject *self);
```

Must return an *awaitable* object. See \_\_anext\_\_() for details.

This slot may be set to NULL if an object does not implement asynchronous iteration protocol.

#### unaryfunc PyAsyncMethods.am\_anext

The signature of this function is:

```
PyObject *am_anext(PyObject *self);
```

Must return an *awaitable* object. See anext () for details. This slot may be set to *NULL*.

# 12.9 Slot Type typedefs

```
PyObject * (*allocfunc) (PyTypeObject *cls, Py_ssize_t nitems)
```

The purpose of this function is to separate memory allocation from memory initialization. It should return a pointer to a block of memory of adequate length for the instance, suitably aligned, and initialized to zeros, but with ob\_refent set to 1 and ob\_type set to the type argument. If the type's tp\_itemsize is non-zero, the object's ob\_size field should be initialized to *nitems* and the length of the allocated memory block should

```
This function should not do any other instance initialization, not even to allocate additional memory; that should be
     done by tp_new.
void (*destructor) (PyObject *)
PyObject * (*vectorcallfunc) (PyObject *callable, PyObject *const *args, size_t nargsf, PyObject *kw-
     See tp vectorcall offset.
     Arguments to vectorcall func are the same as for _PyObject_Vectorcall().
     New in version 3.8.
void (*freefunc) (void *)
     See tp free.
PyObject * (*newfunc) (PyObject *, PyObject *, PyObject *)
     See tp_new.
int (*initproc) (PyObject *, PyObject *, PyObject *)
     See tp init.
PyObject * (*reprfunc) (PyObject *)
     See tp_repr.
PyObject * (*getattrfunc) (PyObject *self, char *attr)
     Return the value of the named attribute for the object.
int (*setattrfunc) (PyObject *self, char *attr, PyObject *value)
     Set the value of the named attribute for the object. The value argument is set to NULL to delete the attribute.
PyObject * (*getattrofunc) (PyObject *self, PyObject *attr)
     Return the value of the named attribute for the object.
     See tp_getattro.
int (*setattrofunc) (PyObject *self, PyObject *attr, PyObject *value)
     Set the value of the named attribute for the object. The value argument is set to NULL to delete the attribute.
     See tp_setattro.
PyObject * (*descrgetfunc) (PyObject *, PyObject *, PyObject *)
     See tp descraet.
int (*descrsetfunc) (PyObject *, PyObject *, PyObject *)
     See tp_descrset.
Py_hash_t (*hashfunc) (PyObject *)
     See tp hash.
PyObject * (*richcmpfunc) (PyObject *, PyObject *, int)
     See tp_richcompare.
PyObject * (*getiterfunc) (PyObject *)
     See tp_iter.
PyObject * (*iternextfunc) (PyObject *)
     See tp iternext.
Py_ssize_t (*lenfunc) (PyObject *)
int (*getbufferproc) (PyObject *, Py_buffer *, int)
```

be tp\_basicsize + nitems\*tp\_itemsize, rounded up to a multiple of size of (void\*); otherwise,

*nitems* is not used and the length of the block should be tp basicsize.

```
void (*releasebufferproc) (PyObject *, Py_buffer *)
PyObject * (*unaryfunc) (PyObject *)
PyObject * (*binaryfunc) (PyObject *, PyObject *)
PyObject * (*ternaryfunc) (PyObject *, PyObject *, PyObject *)
PyObject * (*ssizeargfunc) (PyObject *, Py_ssize_t)
int (*ssizeobjargproc) (PyObject *, Py_ssize_t)
int (*objobjproc) (PyObject *, PyObject *)
int (*objobjargproc) (PyObject *, PyObject *, PyObject *)
```

## 12.10 Examples

The following are simple examples of Python type definitions. They include common usage you may encounter. Some demonstrate tricky corner cases. For more examples, practical info, and a tutorial, see defining-new-types and new-types-topics.

A basic static type:

```
typedef struct {
    PyObject_HEAD
    const char *data;
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject),
    .tp_doc = "My objects",
    .tp_new = myobj_new,
    .tp_dealloc = (destructor)myobj_dealloc,
    .tp_repr = (reprfunc)myobj_repr,
};
```

You may also find older code (especially in the CPython code base) with a more verbose initializer:

```
static PyTypeObject MyObject_Type = {
   PyVarObject_HEAD_INIT(NULL, 0)
                                    /* tp_name */
    "mymod.MyObject",
                                    /* tp_basicsize */
    sizeof(MyObject),
                                    /* tp_itemsize */
                                    /* tp_dealloc */
    (destructor)myobj_dealloc,
                                    /* tp_vectorcall_offset */
    0,
    0,
                                    /* tp_getattr */
                                    /* tp_setattr */
    0,
                                    /* tp_as_async */
    0.
                                    /* tp_repr */
    (reprfunc) myobj_repr,
                                     /* tp_as_number */
    0,
                                     /* tp_as_sequence */
    0,
                                     /* tp_as_mapping */
    0,
                                     /* tp_hash */
                                     /* tp_call */
    0,
                                     /* tp_str */
    0,
```

(continues on next page)

12.10. Examples 215

```
/* tp_getattro */
    0,
    0,
                                      /* tp_setattro */
                                      /* tp_as_buffer */
    0,
                                      /* tp_flags */
    0,
                                      /* tp_doc */
    "My objects",
                                      /* tp_traverse */
    0,
                                      /* tp_clear */
    0,
                                      /* tp_richcompare */
    0,
                                      /* tp_weaklistoffset */
    0,
    Ο,
                                      /* tp_iter */
    0,
                                      /* tp_iternext */
                                      /* tp_methods */
    0,
    0,
                                      /* tp_members */
    0,
                                      /* tp_getset */
    0,
                                      /* tp_base */
    Ο,
                                      /* tp_dict */
                                      /* tp_descr_get */
    0,
                                      /* tp_descr_set */
    0,
    0,
                                      /* tp_dictoffset */
    0,
                                      /* tp_init */
    0,
                                      /* tp_alloc */
                                      /* tp_new */
   myobj_new,
};
```

A type that supports weakrefs, instance dicts, and hashing:

```
typedef struct {
   PyObject_HEAD
   const char *data;
   PyObject *inst_dict;
    PyObject *weakreflist;
} MyObject;
static PyTypeObject MyObject_Type = {
   PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject),
    .tp_doc = "My objects",
    .tp_weaklistoffset = offsetof(MyObject, weakreflist),
    .tp_dictoffset = offsetof(MyObject, inst_dict),
    .tp_flags = Py_TPFLAGS_DEFAULT | Py_TPFLAGS_BASETYPE | Py_TPFLAGS_HAVE_GC,
    .tp_new = myobj_new,
    .tp_traverse = (traverseproc)myobj_traverse,
    .tp_clear = (inquiry)myobj_clear,
    .tp_alloc = PyType_GenericNew,
    .tp_dealloc = (destructor)myobj_dealloc,
    .tp_repr = (reprfunc)myobj_repr,
    .tp_hash = (hashfunc)myobj_hash,
    .tp_richcompare = PyBaseObject_Type.tp_richcompare,
};
```

A str subclass that cannot be subclassed and cannot be called to create instances (e.g. uses a separate factory func):

```
typedef struct {
    PyUnicodeObject raw;
    char *extra;
} MyStr;
```

```
static PyTypeObject MyStr_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyStr",
    .tp_basicsize = sizeof(MyStr),
    .tp_base = NULL, // set to &PyUnicode_Type in module init
    .tp_doc = "my custom str",
    .tp_flags = Py_TPFLAGS_DEFAULT,
    .tp_new = NULL,
    .tp_repr = (reprfunc)myobj_repr,
};
```

The simplest static type (with fixed-length instances):

```
typedef struct {
    PyObject_HEAD
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
};
```

The simplest static type (with variable-length instances):

```
typedef struct {
    PyObject_VAR_HEAD
    const char *data[1];
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject) - sizeof(char *),
    .tp_itemsize = sizeof(char *),
};
```

# 12.11 Supporting Cyclic Garbage Collection

Python's support for detecting and collecting garbage which involves circular references requires support from object types which are "containers" for other objects which may also be containers. Types which do not store references to other objects, or which only store references to atomic types (such as numbers or strings), do not need to provide any explicit support for garbage collection.

To create a container type, the  $tp\_flags$  field of the type object must include the  $Py\_TPFLAGS\_HAVE\_GC$  and provide an implementation of the  $tp\_traverse$  handler. If instances of the type are mutable, a  $tp\_clear$  implementation must also be provided.

## Py\_TPFLAGS\_HAVE\_GC

Objects with a type with this flag set must conform with the rules documented here. For convenience these objects will be referred to as container objects.

Constructors for container types must conform to two rules:

1. The memory for the object must be allocated using PyObject\_GC\_New() or PyObject\_GC\_NewVar().

2. Once all the fields which may contain references to other containers are initialized, it must call <code>PyObject\_GC\_Track()</code>.

### TYPE\* PyObject\_GC\_New (TYPE, PyTypeObject \*type)

Analogous to PyObject\_New() but for container objects with the Py\_TPFLAGS\_HAVE\_GC flag set.

### TYPE\* PyObject\_GC\_NewVar (TYPE, PyTypeObject \*type, Py\_ssize\_t size)

Analogous to PyObject\_NewVar() but for container objects with the Py\_TPFLAGS\_HAVE\_GC flag set.

#### TYPE\* PyObject GC Resize (TYPE, PyVarObject \*op, Py ssize t newsize)

Resize an object allocated by  $PyObject_NewVar()$ . Returns the resized object or NULL on failure. op must not be tracked by the collector yet.

```
void PyObject_GC_Track (PyObject *op)
```

Adds the object op to the set of container objects tracked by the collector. The collector can run at unexpected times so objects must be valid while being tracked. This should be called once all the fields followed by the  $tp\_traverse$  handler become valid, usually near the end of the constructor.

Similarly, the deallocator for the object must conform to a similar pair of rules:

- 1. Before fields which refer to other containers are invalidated, PyObject GC UnTrack() must be called.
- 2. The object's memory must be deallocated using PyObject\_GC\_Del().

```
void PyObject_GC_Del (void *op)
```

Releases memory allocated to an object using PyObject\_GC\_New() or PyObject\_GC\_NewVar().

```
void PyObject_GC_UnTrack (void *op)
```

Remove the object op from the set of container objects tracked by the collector. Note that  $PyObject\_GC\_Track()$  can be called again on this object to add it back to the set of tracked objects. The deal-locator ( $tp\_dealloc$  handler) should call this for the object before any of the fields used by the  $tp\_traverse$  handler become invalid.

Changed in version 3.8: The \_PyObject\_GC\_TRACK() and \_PyObject\_GC\_UNTRACK() macros have been removed from the public C API.

The tp\_traverse handler accepts a function parameter of this type:

```
int (*visitproc) (PyObject *object, void *arg)
```

Type of the visitor function passed to the  $tp\_traverse$  handler. The function should be called with an object to traverse as *object* and the third parameter to the  $tp\_traverse$  handler as arg. The Python core uses several visitor functions to implement cyclic garbage detection; it's not expected that users will need to write their own visitor functions.

The tp\_traverse handler must have the following type:

```
int (*traverseproc) (PyObject *self, visitproc visit, void *arg)
```

Traversal function for a container object. Implementations must call the *visit* function for each object directly contained by *self*, with the parameters to *visit* being the contained object and the *arg* value passed to the handler. The *visit* function must not be called with a *NULL* object argument. If *visit* returns a non-zero value that value should be returned immediately.

To simplify writing  $tp\_traverse$  handlers, a  $Py\_VISIT()$  macro is provided. In order to use this macro, the  $tp\_traverse$  implementation must name its arguments exactly visit and arg:

```
void Py_VISIT (PyObject *o)
```

If o is not NULL, call the visit callback, with arguments o and arg. If visit returns a non-zero value, then return it. Using this macro,  $tp\_traverse$  handlers look like:

```
static int
my_traverse(Noddy *self, visitproc visit, void *arg)
```

```
{
    Py_VISIT(self->foo);
    Py_VISIT(self->bar);
    return 0;
}
```

The tp\_clear handler must be of the inquiry type, or NULL if the object is immutable.

### int (\*inquiry) (PyObject \*self)

Drop references that may have created reference cycles. Immutable objects do not have to define this method since they can never directly create reference cycles. Note that the object must still be valid after calling this method (don't just call  $Py\_DECREF()$ ) on a reference). The collector will call this method if it detects that this object is involved in a reference cycle.

## **THIRTEEN**

## **API AND ABI VERSIONING**

PY\_VERSION\_HEX is the Python version number encoded in a single integer.

For example if the PY\_VERSION\_HEX is set to 0x030401a2, the underlying version information can be found by treating it as a 32 bit number in the following manner:

Bytes Bits (big en-		Meaning		
	dian order)			
1	1-8	PY_MAJOR_VERSION (the 3 in 3.4.1a2)		
2	9-16	PY_MINOR_VERSION (the 4 in 3.4.1a2)		
3	17-24	PY_MICRO_VERSION (the 1 in 3.4.1a2)		
4	25-28	PY_RELEASE_LEVEL (0xA for alpha, 0xB for beta, 0xC for release candi-		
		date and $0xF$ for final), in this case it is alpha.		
	29-32	PY_RELEASE_SERIAL (the 2 in 3.4.1a2, zero for final releases)		

Thus 3.4.1a2 is hexversion 0x030401a2.

All the given macros are defined in Include/patchlevel.h.

Α

## **GLOSSARY**

- >>> The default Python prompt of the interactive shell. Often seen for code examples which can be executed interactively in the interpreter.
- ... Can refer to:
  - The default Python prompt of the interactive shell when entering the code for an indented code block, when within a pair of matching left and right delimiters (parentheses, square brackets, curly braces or triple quotes), or after specifying a decorator.
  - The Ellipsis built-in constant.
- **2to3** A tool that tries to convert Python 2.x code to Python 3.x code by handling most of the incompatibilities which can be detected by parsing the source and traversing the parse tree.

2to3 is available in the standard library as lib2to3; a standalone entry point is provided as Tools/scripts/2to3. See 2to3-reference.

- abstract base class Abstract base classes complement *duck-typing* by providing a way to define interfaces when other techniques like hasattr() would be clumsy or subtly wrong (for example with magic methods). ABCs introduce virtual subclasses, which are classes that don't inherit from a class but are still recognized by isinstance() and issubclass(); see the abc module documentation. Python comes with many built-in ABCs for data structures (in the collections.abc module), numbers (in the numbers module), streams (in the io module), import finders and loaders (in the importlib.abc module). You can create your own ABCs with the abc module.
- **annotation** A label associated with a variable, a class attribute or a function parameter or return value, used by convention as a *type hint*.

Annotations of local variables cannot be accessed at runtime, but annotations of global variables, class attributes, and functions are stored in the \_\_annotations\_\_ special attribute of modules, classes, and functions, respectively.

See variable annotation, function annotation, PEP 484 and PEP 526, which describe this functionality.

argument A value passed to a function (or method) when calling the function. There are two kinds of argument:

• *keyword argument*: an argument preceded by an identifier (e.g. name=) in a function call or passed as a value in a dictionary preceded by \*\*. For example, 3 and 5 are both keyword arguments in the following calls to complex():

```
complex(real=3, imag=5)
complex(**{'real': 3, 'imag': 5})
```

• *positional argument*: an argument that is not a keyword argument. Positional arguments can appear at the beginning of an argument list and/or be passed as elements of an *iterable* preceded by \*. For example, 3 and 5 are both positional arguments in the following calls:

```
complex(3, 5)
complex(*(3, 5))
```

Arguments are assigned to the named local variables in a function body. See the calls section for the rules governing this assignment. Syntactically, any expression can be used to represent an argument; the evaluated value is assigned to the local variable.

See also the *parameter* glossary entry, the FAQ question on the difference between arguments and parameters, and **PEP 362**.

- asynchronous context manager An object which controls the environment seen in an async with statement by defining \_\_aenter\_\_() and \_\_aexit\_\_() methods. Introduced by PEP 492.
- **asynchronous generator** A function which returns an *asynchronous generator iterator*. It looks like a coroutine function defined with async def except that it contains yield expressions for producing a series of values usable in an async for loop.

Usually refers to an asynchronous generator function, but may refer to an *asynchronous generator iterator* in some contexts. In cases where the intended meaning isn't clear, using the full terms avoids ambiguity.

An asynchronous generator function may contain await expressions as well as async for, and async with statements.

**asynchronous generator iterator** An object created by a *asynchronous generator* function.

This is an *asynchronous iterator* which when called using the \_\_anext\_\_() method returns an awaitable object which will execute the body of the asynchronous generator function until the next yield expression.

Each yield temporarily suspends processing, remembering the location execution state (including local variables and pending try-statements). When the *asynchronous generator iterator* effectively resumes with another awaitable returned by \_\_anext\_\_ (), it picks up where it left off. See PEP 492 and PEP 525.

- **asynchronous iterable** An object, that can be used in an async for statement. Must return an *asynchronous iterator* from its \_\_aiter\_\_() method. Introduced by **PEP 492**.
- asynchronous iterator An object that implements the \_\_aiter\_\_() and \_\_anext\_\_() methods. \_\_anext\_\_
  must return an awaitable object. async for resolves the awaitables returned by an asynchronous iterator's
  \_\_anext\_\_() method until it raises a StopAsyncIteration exception. Introduced by PEP 492.
- **attribute** A value associated with an object which is referenced by name using dotted expressions. For example, if an object o has an attribute a it would be referenced as o.a.
- **awaitable** An object that can be used in an await expression. Can be a *coroutine* or an object with an \_\_await\_\_() method. See also **PEP 492**.
- BDFL Benevolent Dictator For Life, a.k.a. Guido van Rossum, Python's creator.
- binary file A *file object* able to read and write *bytes-like objects*. Examples of binary files are files opened in binary mode ('rb', 'wb' or 'rb+'), sys.stdin.buffer, sys.stdout.buffer, and instances of io.BytesIO and gzip.GzipFile.

See also *text file* for a file object able to read and write str objects.

bytes-like object An object that supports the *Buffer Protocol* and can export a C-contiguous buffer. This includes all bytes, bytearray, and array.array objects, as well as many common memoryview objects. Bytes-like objects can be used for various operations that work with binary data; these include compression, saving to a binary file, and sending over a socket.

Some operations need the binary data to be mutable. The documentation often refers to these as "read-write bytes-like objects". Example mutable buffer objects include bytearray and a memoryview of a bytearray. Other operations require the binary data to be stored in immutable objects ("read-only bytes-like objects"); examples of these include bytes and a memoryview of a bytes object.

bytecode Python source code is compiled into bytecode, the internal representation of a Python program in the CPython interpreter. The bytecode is also cached in .pyc files so that executing the same file is faster the second time (recompilation from source to bytecode can be avoided). This "intermediate language" is said to run on a *virtual machine* that executes the machine code corresponding to each bytecode. Do note that bytecodes are not expected to work between different Python virtual machines, nor to be stable between Python releases.

A list of bytecode instructions can be found in the documentation for the dis module.

- **class** A template for creating user-defined objects. Class definitions normally contain method definitions which operate on instances of the class.
- **class variable** A variable defined in a class and intended to be modified only at class level (i.e., not in an instance of the class).
- coercion The implicit conversion of an instance of one type to another during an operation which involves two arguments of the same type. For example, int (3.15) converts the floating point number to the integer 3, but in 3+4.5, each argument is of a different type (one int, one float), and both must be converted to the same type before they can be added or it will raise a TypeError. Without coercion, all arguments of even compatible types would have to be normalized to the same value by the programmer, e.g., float (3)+4.5 rather than just 3+4.5.
- complex number An extension of the familiar real number system in which all numbers are expressed as a sum of a real part and an imaginary part. Imaginary numbers are real multiples of the imaginary unit (the square root of -1), often written i in mathematics or j in engineering. Python has built-in support for complex numbers, which are written with this latter notation; the imaginary part is written with a j suffix, e.g., 3+1j. To get access to complex equivalents of the math module, use cmath. Use of complex numbers is a fairly advanced mathematical feature. If you're not aware of a need for them, it's almost certain you can safely ignore them.
- **context manager** An object which controls the environment seen in a with statement by defining \_\_enter\_\_() and exit () methods. See PEP 343.
- **context variable** A variable which can have different values depending on its context. This is similar to Thread-Local Storage in which each execution thread may have a different value for a variable. However, with context variables, there may be several contexts in one execution thread and the main usage for context variables is to keep track of variables in concurrent asynchronous tasks. See contextvars.
- **contiguous** A buffer is considered contiguous exactly if it is either *C-contiguous* or *Fortran contiguous*. Zero-dimensional buffers are C and Fortran contiguous. In one-dimensional arrays, the items must be laid out in memory next to each other, in order of increasing indexes starting from zero. In multidimensional C-contiguous arrays, the last index varies the fastest when visiting items in order of memory address. However, in Fortran contiguous arrays, the first index varies the fastest.
- **coroutine** Coroutines are a more generalized form of subroutines. Subroutines are entered at one point and exited at another point. Coroutines can be entered, exited, and resumed at many different points. They can be implemented with the async def statement. See also **PEP 492**.
- coroutine function A function which returns a *coroutine* object. A coroutine function may be defined with the async def statement, and may contain await, async for, and async with keywords. These were introduced by **PEP 492**.
- **CPython** The canonical implementation of the Python programming language, as distributed on python.org. The term "CPython" is used when necessary to distinguish this implementation from others such as Jython or IronPython.
- **decorator** A function returning another function, usually applied as a function transformation using the @wrapper syntax. Common examples for decorators are classmethod() and staticmethod().

The decorator syntax is merely syntactic sugar, the following two function definitions are semantically equivalent:

```
def f(...):
    ...
f = staticmethod(f)
```

```
@staticmethod
def f(...):
    ...
```

The same concept exists for classes, but is less commonly used there. See the documentation for function definitions and class definitions for more about decorators.

**descriptor** Any object which defines the methods \_\_get\_\_(), \_\_set\_\_(), or \_\_delete\_\_(). When a class attribute is a descriptor, its special binding behavior is triggered upon attribute lookup. Normally, using *a.b* to get, set or delete an attribute looks up the object named *b* in the class dictionary for *a*, but if *b* is a descriptor, the respective descriptor method gets called. Understanding descriptors is a key to a deep understanding of Python because they are the basis for many features including functions, methods, properties, class methods, static methods, and reference to super classes.

For more information about descriptors' methods, see descriptors.

- **dictionary** An associative array, where arbitrary keys are mapped to values. The keys can be any object with \_\_hash\_\_() and \_\_eq\_\_() methods. Called a hash in Perl.
- dictionary view The objects returned from dict.keys(), dict.values(), and dict.items() are called dictionary views. They provide a dynamic view on the dictionary's entries, which means that when the dictionary changes, the view reflects these changes. To force the dictionary view to become a full list use list(dictview). See dict-views.
- **docstring** A string literal which appears as the first expression in a class, function or module. While ignored when the suite is executed, it is recognized by the compiler and put into the \_\_\_doc\_\_ attribute of the enclosing class, function or module. Since it is available via introspection, it is the canonical place for documentation of the object.
- duck-typing A programming style which does not look at an object's type to determine if it has the right interface; instead, the method or attribute is simply called or used ("If it looks like a duck and quacks like a duck, it must be a duck.") By emphasizing interfaces rather than specific types, well-designed code improves its flexibility by allowing polymorphic substitution. Duck-typing avoids tests using type() or isinstance(). (Note, however, that duck-typing can be complemented with abstract base classes.) Instead, it typically employs hasattr() tests or EAFP programming.
- **EAFP** Easier to ask for forgiveness than permission. This common Python coding style assumes the existence of valid keys or attributes and catches exceptions if the assumption proves false. This clean and fast style is characterized by the presence of many try and except statements. The technique contrasts with the *LBYL* style common to many other languages such as C.
- **expression** A piece of syntax which can be evaluated to some value. In other words, an expression is an accumulation of expression elements like literals, names, attribute access, operators or function calls which all return a value. In contrast to many other languages, not all language constructs are expressions. There are also *statements* which cannot be used as expressions, such as while. Assignments are also statements, not expressions.
- extension module A module written in C or C++, using Python's C API to interact with the core and with user code.
- **f-string** String literals prefixed with 'f' or 'F' are commonly called "f-strings" which is short for formatted string literals. See also **PEP 498**.
- **file object** An object exposing a file-oriented API (with methods such as read() or write()) to an underlying resource. Depending on the way it was created, a file object can mediate access to a real on-disk file or to another type of storage or communication device (for example standard input/output, in-memory buffers, sockets, pipes, etc.). File objects are also called *file-like objects* or *streams*.

There are actually three categories of file objects: raw *binary files*, buffered *binary files* and *text files*. Their interfaces are defined in the io module. The canonical way to create a file object is by using the open () function.

file-like object A synonym for file object.

**finder** An object that tries to find the *loader* for a module that is being imported.

Since Python 3.3, there are two types of finder: *meta path finders* for use with sys.meta\_path, and *path entry finders* for use with sys.path\_hooks.

See PEP 302, PEP 420 and PEP 451 for much more detail.

**floor division** Mathematical division that rounds down to nearest integer. The floor division operator is //. For example, the expression 11 // 4 evaluates to 2 in contrast to the 2.75 returned by float true division. Note that (-11) // 4 is -3 because that is -2.75 rounded *downward*. See **PEP 238**.

**function** A series of statements which returns some value to a caller. It can also be passed zero or more *arguments* which may be used in the execution of the body. See also *parameter*, *method*, and the function section.

**function annotation** An *annotation* of a function parameter or return value.

Function annotations are usually used for *type hints*: for example, this function is expected to take two int arguments and is also expected to have an int return value:

```
def sum_two_numbers(a: int, b: int) -> int:
    return a + b
```

Function annotation syntax is explained in section function.

See variable annotation and PEP 484, which describe this functionality.

**\_\_future**\_\_ A pseudo-module which programmers can use to enable new language features which are not compatible with the current interpreter.

By importing the \_\_future\_\_ module and evaluating its variables, you can see when a new feature was first added to the language and when it becomes the default:

```
>>> import __future__
>>> __future__.division
_Feature((2, 2, 0, 'alpha', 2), (3, 0, 0, 'alpha', 0), 8192)
```

garbage collection The process of freeing memory when it is not used anymore. Python performs garbage collection via reference counting and a cyclic garbage collector that is able to detect and break reference cycles. The garbage collector can be controlled using the gc module.

**generator** A function which returns a *generator iterator*. It looks like a normal function except that it contains yield expressions for producing a series of values usable in a for-loop or that can be retrieved one at a time with the next() function.

Usually refers to a generator function, but may refer to a *generator iterator* in some contexts. In cases where the intended meaning isn't clear, using the full terms avoids ambiguity.

generator iterator An object created by a generator function.

Each yield temporarily suspends processing, remembering the location execution state (including local variables and pending try-statements). When the *generator iterator* resumes, it picks up where it left off (in contrast to functions which start fresh on every invocation).

**generator expression** An expression that returns an iterator. It looks like a normal expression followed by a for clause defining a loop variable, range, and an optional if clause. The combined expression generates values for an enclosing function:

```
>>> sum(i*i for i in range(10))  # sum of squares 0, 1, 4, ... 81
285
```

**generic function** A function composed of multiple functions implementing the same operation for different types. Which implementation should be used during a call is determined by the dispatch algorithm.

See also the single dispatch glossary entry, the functools.singledispatch() decorator, and PEP 443.

**GIL** See *global* interpreter lock.

**global interpreter lock** The mechanism used by the *CPython* interpreter to assure that only one thread executes Python *bytecode* at a time. This simplifies the CPython implementation by making the object model (including critical built-in types such as dict) implicitly safe against concurrent access. Locking the entire interpreter makes it easier for the interpreter to be multi-threaded, at the expense of much of the parallelism afforded by multi-processor machines.

However, some extension modules, either standard or third-party, are designed so as to release the GIL when doing computationally-intensive tasks such as compression or hashing. Also, the GIL is always released when doing I/O.

Past efforts to create a "free-threaded" interpreter (one which locks shared data at a much finer granularity) have not been successful because performance suffered in the common single-processor case. It is believed that overcoming this performance issue would make the implementation much more complicated and therefore costlier to maintain.

**hash-based pyc** A bytecode cache file that uses the hash rather than the last-modified time of the corresponding source file to determine its validity. See pyc-invalidation.

hashable An object is *hashable* if it has a hash value which never changes during its lifetime (it needs a \_\_hash\_\_() method), and can be compared to other objects (it needs an \_\_eq\_\_() method). Hashable objects which compare equal must have the same hash value.

Hashability makes an object usable as a dictionary key and a set member, because these data structures use the hash value internally.

Most of Python's immutable built-in objects are hashable; mutable containers (such as lists or dictionaries) are not; immutable containers (such as tuples and frozensets) are only hashable if their elements are hashable. Objects which are instances of user-defined classes are hashable by default. They all compare unequal (except with themselves), and their hash value is derived from their id().

- **IDLE** An Integrated Development Environment for Python. IDLE is a basic editor and interpreter environment which ships with the standard distribution of Python.
- **immutable** An object with a fixed value. Immutable objects include numbers, strings and tuples. Such an object cannot be altered. A new object has to be created if a different value has to be stored. They play an important role in places where a constant hash value is needed, for example as a key in a dictionary.
- import path A list of locations (or path entries) that are searched by the path based finder for modules to import. During import, this list of locations usually comes from sys.path, but for subpackages it may also come from the parent package's \_\_path\_\_ attribute.

**importing** The process by which Python code in one module is made available to Python code in another module.

**importer** An object that both finds and loads a module; both a *finder* and *loader* object.

- **interactive** Python has an interactive interpreter which means you can enter statements and expressions at the interpreter prompt, immediately execute them and see their results. Just launch python with no arguments (possibly by selecting it from your computer's main menu). It is a very powerful way to test out new ideas or inspect modules and packages (remember help(x)).
- **interpreted** Python is an interpreted language, as opposed to a compiled one, though the distinction can be blurry because of the presence of the bytecode compiler. This means that source files can be run directly without explicitly creating an executable which is then run. Interpreted languages typically have a shorter development/debug cycle than compiled ones, though their programs generally also run more slowly. See also *interactive*.
- **interpreter shutdown** When asked to shut down, the Python interpreter enters a special phase where it gradually releases all allocated resources, such as modules and various critical internal structures. It also makes several calls to the

*garbage collector*. This can trigger the execution of code in user-defined destructors or weakref callbacks. Code executed during the shutdown phase can encounter various exceptions as the resources it relies on may not function anymore (common examples are library modules or the warnings machinery).

The main reason for interpreter shutdown is that the \_\_main\_\_ module or the script being run has finished executing.

**iterable** An object capable of returning its members one at a time. Examples of iterables include all sequence types (such as list, str, and tuple) and some non-sequence types like dict, *file objects*, and objects of any classes you define with an \_\_iter\_\_() method or with a \_\_getitem\_\_() method that implements *Sequence* semantics.

Iterables can be used in a for loop and in many other places where a sequence is needed (zip(), map(), ...). When an iterable object is passed as an argument to the built-in function iter(), it returns an iterator for the object. This iterator is good for one pass over the set of values. When using iterables, it is usually not necessary to call iter() or deal with iterator objects yourself. The for statement does that automatically for you, creating a temporary unnamed variable to hold the iterator for the duration of the loop. See also *iterator*, *sequence*, and *generator*.

iterator An object representing a stream of data. Repeated calls to the iterator's \_\_next\_\_() method (or passing it to the built-in function next()) return successive items in the stream. When no more data are available a StopIteration exception is raised instead. At this point, the iterator object is exhausted and any further calls to its \_\_next\_\_() method just raise StopIteration again. Iterators are required to have an \_\_iter\_\_() method that returns the iterator object itself so every iterator is also iterable and may be used in most places where other iterables are accepted. One notable exception is code which attempts multiple iteration passes. A container object (such as a list) produces a fresh new iterator each time you pass it to the iter() function or use it in a for loop. Attempting this with an iterator will just return the same exhausted iterator object used in the previous iteration pass, making it appear like an empty container.

More information can be found in typeiter.

**key function** A key function or collation function is a callable that returns a value used for sorting or ordering. For example, locale.strxfrm() is used to produce a sort key that is aware of locale specific sort conventions.

A number of tools in Python accept key functions to control how elements are ordered or grouped. They include min(), max(), sorted(), list.sort(), heapq.merge(), heapq.nsmallest(), heapq.nlargest(), and itertools.groupby().

There are several ways to create a key function. For example, the str.lower() method can serve as a key function for case insensitive sorts. Alternatively, a key function can be built from a lambda expression such as lambda r: (r[0], r[2]). Also, the operator module provides three key function constructors: attrgetter(), itemgetter(), and methodcaller(). See the Sorting HOW TO for examples of how to create and use key functions.

#### keyword argument See argument.

**lambda** An anonymous inline function consisting of a single *expression* which is evaluated when the function is called. The syntax to create a lambda function is lambda [parameters]: expression

**LBYL** Look before you leap. This coding style explicitly tests for pre-conditions before making calls or lookups. This style contrasts with the *EAFP* approach and is characterized by the presence of many if statements.

In a multi-threaded environment, the LBYL approach can risk introducing a race condition between "the looking" and "the leaping". For example, the code, if key in mapping: return mapping [key] can fail if another thread removes *key* from *mapping* after the test, but before the lookup. This issue can be solved with locks or by using the EAFP approach.

**list** A built-in Python *sequence*. Despite its name it is more akin to an array in other languages than to a linked list since access to elements is O(1).

**list comprehension** A compact way to process all or part of the elements in a sequence and return a list with the results. result =  $['\{:\#04x\}']$ . format(x) for x in range(256) if x % 2 == 0] generates a list

of strings containing even hex numbers (0x..) in the range from 0 to 255. The if clause is optional. If omitted, all elements in range (256) are processed.

**loader** An object that loads a module. It must define a method named load\_module(). A loader is typically returned by a *finder*. See PEP 302 for details and importlib.abc.Loader for an *abstract base class*.

**magic method** An informal synonym for *special method*.

mapping A container object that supports arbitrary key lookups and implements the methods specified in the Mapping or MutableMapping abstract base classes. Examples include dict, collections.defaultdict, collections.OrderedDict and collections.Counter.

**meta path finder** A *finder* returned by a search of sys.meta\_path. Meta path finders are related to, but different from *path entry finders*.

See importlib.abc.MetaPathFinder for the methods that meta path finders implement.

metaclass The class of a class. Class definitions create a class name, a class dictionary, and a list of base classes. The metaclass is responsible for taking those three arguments and creating the class. Most object oriented programming languages provide a default implementation. What makes Python special is that it is possible to create custom metaclasses. Most users never need this tool, but when the need arises, metaclasses can provide powerful, elegant solutions. They have been used for logging attribute access, adding thread-safety, tracking object creation, implementing singletons, and many other tasks.

More information can be found in metaclasses.

**method** A function which is defined inside a class body. If called as an attribute of an instance of that class, the method will get the instance object as its first *argument* (which is usually called self). See *function* and *nested scope*.

**method resolution order** Method Resolution Order is the order in which base classes are searched for a member during lookup. See The Python 2.3 Method Resolution Order for details of the algorithm used by the Python interpreter since the 2.3 release.

**module** An object that serves as an organizational unit of Python code. Modules have a namespace containing arbitrary Python objects. Modules are loaded into Python by the process of *importing*.

See also package.

**module spec** A namespace containing the import-related information used to load a module. An instance of importlib.machinery.ModuleSpec.

MRO See method resolution order.

mutable Mutable objects can change their value but keep their id(). See also immutable.

**named tuple** The term "named tuple" applies to any type or class that inherits from tuple and whose indexable elements are also accessible using named attributes. The type or class may have other features as well.

Several built-in types are named tuples, including the values returned by time.localtime() and os. stat(). Another example is sys.float\_info:

```
>>> sys.float_info[1]  # indexed access
1024
>>> sys.float_info.max_exp  # named field access
1024
>>> isinstance(sys.float_info, tuple)  # kind of tuple
True
```

Some named tuples are built-in types (such as the above examples). Alternatively, a named tuple can be created from a regular class definition that inherits from tuple and that defines named fields. Such a class can be written by hand or it can be created with the factory function collections.namedtuple(). The latter technique also adds some extra methods that may not be found in hand-written or built-in named tuples.

- namespace The place where a variable is stored. Namespaces are implemented as dictionaries. There are the local, global and built-in namespaces as well as nested namespaces in objects (in methods). Namespaces support modularity by preventing naming conflicts. For instance, the functions builtins.open and os.open() are distinguished by their namespaces. Namespaces also aid readability and maintainability by making it clear which module implements a function. For instance, writing random.seed() or itertools.islice() makes it clear that those functions are implemented by the random and itertools modules, respectively.
- **namespace package** A **PEP 420** *package* which serves only as a container for subpackages. Namespace packages may have no physical representation, and specifically are not like a *regular package* because they have no \_\_init\_\_. py file.

See also module.

- **nested scope** The ability to refer to a variable in an enclosing definition. For instance, a function defined inside another function can refer to variables in the outer function. Note that nested scopes by default work only for reference and not for assignment. Local variables both read and write in the innermost scope. Likewise, global variables read and write to the global namespace. The nonlocal allows writing to outer scopes.
- **new-style class** Old name for the flavor of classes now used for all class objects. In earlier Python versions, only new-style classes could use Python's newer, versatile features like \_\_slots\_\_, descriptors, properties, \_\_getattribute\_\_(), class methods, and static methods.
- **object** Any data with state (attributes or value) and defined behavior (methods). Also the ultimate base class of any *new-style class*.
- **package** A Python *module* which can contain submodules or recursively, subpackages. Technically, a package is a Python module with an \_\_path\_\_ attribute.

See also regular package and namespace package.

- **parameter** A named entity in a *function* (or method) definition that specifies an *argument* (or in some cases, arguments) that the function can accept. There are five kinds of parameter:
  - *positional-or-keyword*: specifies an argument that can be passed either *positionally* or as a *keyword argument*. This is the default kind of parameter, for example *foo* and *bar* in the following:

```
def func(foo, bar=None): ...
```

- *positional-only*: specifies an argument that can be supplied only by position. Python has no syntax for defining positional-only parameters. However, some built-in functions have positional-only parameters (e.g. abs ()).
- *keyword-only*: specifies an argument that can be supplied only by keyword. Keyword-only parameters can be defined by including a single var-positional parameter or bare \* in the parameter list of the function definition before them, for example *kw only1* and *kw only2* in the following:

```
def func(arg, *, kw_only1, kw_only2): ...
```

• *var-positional*: specifies that an arbitrary sequence of positional arguments can be provided (in addition to any positional arguments already accepted by other parameters). Such a parameter can be defined by prepending the parameter name with \*, for example *args* in the following:

```
def func(*args, **kwargs): ...
```

var-keyword: specifies that arbitrarily many keyword arguments can be provided (in addition to any keyword arguments already accepted by other parameters). Such a parameter can be defined by prepending the parameter name with \*\*, for example kwargs in the example above.

Parameters can specify both optional and required arguments, as well as default values for some optional arguments.

See also the *argument* glossary entry, the FAQ question on the difference between arguments and parameters, the inspect.Parameter class, the function section, and PEP 362.

path entry A single location on the *import path* which the path based finder consults to find modules for importing.

**path entry finder** A *finder* returned by a callable on sys.path\_hooks (i.e. a *path entry hook*) which knows how to locate modules given a *path entry*.

See importlib.abc.PathEntryFinder for the methods that path entry finders implement.

path entry hook A callable on the sys.path\_hook list which returns a path entry finder if it knows how to find modules on a specific path entry.

**path based finder** One of the default *meta path finders* which searches an *import path* for modules.

- path-like object An object representing a file system path. A path-like object is either a str or bytes object representing a path, or an object implementing the os.PathLike protocol. An object that supports the os.PathLike
  protocol can be converted to a str or bytes file system path by calling the os.fspath() function; os.
  fsdecode() and os.fsencode() can be used to guarantee a str or bytes result instead, respectively.
  Introduced by PEP 519.
- **PEP** Python Enhancement Proposal. A PEP is a design document providing information to the Python community, or describing a new feature for Python or its processes or environment. PEPs should provide a concise technical specification and a rationale for proposed features.

PEPs are intended to be the primary mechanisms for proposing major new features, for collecting community input on an issue, and for documenting the design decisions that have gone into Python. The PEP author is responsible for building consensus within the community and documenting dissenting opinions.

See PEP 1.

**portion** A set of files in a single directory (possibly stored in a zip file) that contribute to a namespace package, as defined in **PEP 420**.

positional argument See argument.

provisional API A provisional API is one which has been deliberately excluded from the standard library's backwards compatibility guarantees. While major changes to such interfaces are not expected, as long as they are marked provisional, backwards incompatible changes (up to and including removal of the interface) may occur if deemed necessary by core developers. Such changes will not be made gratuitously – they will occur only if serious fundamental flaws are uncovered that were missed prior to the inclusion of the API.

Even for provisional APIs, backwards incompatible changes are seen as a "solution of last resort" - every attempt will still be made to find a backwards compatible resolution to any identified problems.

This process allows the standard library to continue to evolve over time, without locking in problematic design errors for extended periods of time. See PEP 411 for more details.

provisional package See provisional API.

**Python 3000** Nickname for the Python 3.x release line (coined long ago when the release of version 3 was something in the distant future.) This is also abbreviated "Py3k".

**Pythonic** An idea or piece of code which closely follows the most common idioms of the Python language, rather than implementing code using concepts common to other languages. For example, a common idiom in Python is to loop over all elements of an iterable using a for statement. Many other languages don't have this type of construct, so people unfamiliar with Python sometimes use a numerical counter instead:

```
for i in range(len(food)):
    print(food[i])
```

As opposed to the cleaner, Pythonic method:

```
for piece in food:
    print(piece)
```

**qualified name** A dotted name showing the "path" from a module's global scope to a class, function or method defined in that module, as defined in **PEP 3155**. For top-level functions and classes, the qualified name is the same as the object's name:

When used to refer to modules, the *fully qualified name* means the entire dotted path to the module, including any parent packages, e.g. email.mime.text:

```
>>> import email.mime.text
>>> email.mime.text.__name__
'email.mime.text'
```

**reference count** The number of references to an object. When the reference count of an object drops to zero, it is deallocated. Reference counting is generally not visible to Python code, but it is a key element of the *CPython* implementation. The sys module defines a getrefcount() function that programmers can call to return the reference count for a particular object.

**regular package** A traditional *package*, such as a directory containing an \_\_init\_\_.py file.

See also namespace package.

- **\_\_slots**\_\_ A declaration inside a class that saves memory by pre-declaring space for instance attributes and eliminating instance dictionaries. Though popular, the technique is somewhat tricky to get right and is best reserved for rare cases where there are large numbers of instances in a memory-critical application.
- **sequence** An *iterable* which supports efficient element access using integer indices via the \_\_getitem\_\_() special method and defines a \_\_len\_\_() method that returns the length of the sequence. Some built-in sequence types are list, str, tuple, and bytes. Note that dict also supports \_\_getitem\_\_() and \_\_len\_\_(), but is considered a mapping rather than a sequence because the lookups use arbitrary *immutable* keys rather than integers.

The collections.abc.Sequence abstract base class defines a much richer interface that goes be-yond just \_\_getitem\_\_() and \_\_len\_\_(), adding count(), index(), \_\_contains\_\_(), and \_\_reversed\_\_(). Types that implement this expanded interface can be registered explicitly using register().

- **single dispatch** A form of *generic function* dispatch where the implementation is chosen based on the type of a single argument.
- **slice** An object usually containing a portion of a *sequence*. A slice is created using the subscript notation, [] with colons between numbers when several are given, such as in variable\_name[1:3:5]. The bracket (subscript) notation uses slice objects internally.
- **special method** A method that is called implicitly by Python to execute a certain operation on a type, such as addition. Such methods have names starting and ending with double underscores. Special methods are documented in specialnames.
- **statement** A statement is part of a suite (a "block" of code). A statement is either an *expression* or one of several constructs with a keyword, such as if, while or for.

text encoding A codec which encodes Unicode strings to bytes.

**text file** A *file object* able to read and write str objects. Often, a text file actually accesses a byte-oriented datastream and handles the *text encoding* automatically. Examples of text files are files opened in text mode ('r' or 'w'), sys.stdin, sys.stdout, and instances of io.StringIO.

See also binary file for a file object able to read and write bytes-like objects.

**triple-quoted string** A string which is bound by three instances of either a quotation mark (") or an apostrophe ('). While they don't provide any functionality not available with single-quoted strings, they are useful for a number of reasons. They allow you to include unescaped single and double quotes within a string and they can span multiple lines without the use of the continuation character, making them especially useful when writing docstrings.

type The type of a Python object determines what kind of object it is; every object has a type. An object's type is accessible as its \_\_class\_\_ attribute or can be retrieved with type (obj).

type alias A synonym for a type, created by assigning the type to an identifier.

Type aliases are useful for simplifying *type hints*. For example:

could be made more readable like this:

```
from typing import List, Tuple

Color = Tuple[int, int, int]

def remove_gray_shades(colors: List[Color]) -> List[Color]:
    pass
```

See typing and PEP 484, which describe this functionality.

**type hint** An *annotation* that specifies the expected type for a variable, a class attribute, or a function parameter or return value.

Type hints are optional and are not enforced by Python but they are useful to static type analysis tools, and aid IDEs with code completion and refactoring.

Type hints of global variables, class attributes, and functions, but not local variables, can be accessed using typing.get\_type\_hints().

See typing and PEP 484, which describe this functionality.

universal newlines A manner of interpreting text streams in which all of the following are recognized as ending a line: the Unix end-of-line convention '\n', the Windows convention '\r\n', and the old Macintosh convention '\r'. See PEP 278 and PEP 3116, as well as bytes.splitlines() for an additional use.

variable annotation An annotation of a variable or a class attribute.

When annotating a variable or a class attribute, assignment is optional:

```
class C:
    field: 'annotation'
```

Variable annotations are usually used for *type hints*: for example this variable is expected to take int values:

```
count: int = 0
```

Variable annotation syntax is explained in section annassign.

See function annotation, PEP 484 and PEP 526, which describe this functionality.

**virtual environment** A cooperatively isolated runtime environment that allows Python users and applications to install and upgrade Python distribution packages without interfering with the behaviour of other Python applications running on the same system.

See also venv.

- **virtual machine** A computer defined entirely in software. Python's virtual machine executes the *bytecode* emitted by the bytecode compiler.
- **Zen of Python** Listing of Python design principles and philosophies that are helpful in understanding and using the language. The listing can be found by typing "import this" at the interactive prompt.

В

## **ABOUT THESE DOCUMENTS**

These documents are generated from reStructuredText sources by Sphinx, a document processor specifically written for the Python documentation.

Development of the documentation and its toolchain is an entirely volunteer effort, just like Python itself. If you want to contribute, please take a look at the reporting-bugs page for information on how to do so. New volunteers are always welcome!

Many thanks go to:

- Fred L. Drake, Jr., the creator of the original Python documentation toolset and writer of much of the content;
- the Docutils project for creating reStructuredText and the Docutils suite;
- · Fredrik Lundh for his Alternative Python Reference project from which Sphinx got many good ideas.

## **B.1 Contributors to the Python Documentation**

Many people have contributed to the Python language, the Python standard library, and the Python documentation. See Misc/ACKS in the Python source distribution for a partial list of contributors.

It is only with the input and contributions of the Python community that Python has such wonderful documentation – Thank You!

C

## **HISTORY AND LICENSE**

# C.1 History of the software

Python was created in the early 1990s by Guido van Rossum at Stichting Mathematisch Centrum (CWI, see https://www.cwi.nl/) in the Netherlands as a successor of a language called ABC. Guido remains Python's principal author, although it includes many contributions from others.

In 1995, Guido continued his work on Python at the Corporation for National Research Initiatives (CNRI, see https://www.cnri.reston.va.us/) in Reston, Virginia where he released several versions of the software.

In May 2000, Guido and the Python core development team moved to BeOpen.com to form the BeOpen PythonLabs team. In October of the same year, the PythonLabs team moved to Digital Creations (now Zope Corporation; see http://www.zope.com/). In 2001, the Python Software Foundation (PSF, see https://www.python.org/psf/) was formed, a non-profit organization created specifically to own Python-related Intellectual Property. Zope Corporation is a sponsoring member of the PSF.

All Python releases are Open Source (see https://opensource.org/ for the Open Source Definition). Historically, most, but not all, Python releases have also been GPL-compatible; the table below summarizes the various releases.

Release	Derived from	Year	Owner	GPL compatible?
0.9.0 thru 1.2	n/a	1991-1995	CWI	yes
1.3 thru 1.5.2	1.2	1995-1999	CNRI	yes
1.6	1.5.2	2000	CNRI	no
2.0	1.6	2000	BeOpen.com	no
1.6.1	1.6	2001	CNRI	no
2.1	2.0+1.6.1	2001	PSF	no
2.0.1	2.0+1.6.1	2001	PSF	yes
2.1.1	2.1+2.0.1	2001	PSF	yes
2.1.2	2.1.1	2002	PSF	yes
2.1.3	2.1.2	2002	PSF	yes
2.2 and above	2.1.1	2001-now	PSF	yes

**Note:** GPL-compatible doesn't mean that we're distributing Python under the GPL. All Python licenses, unlike the GPL, let you distribute a modified version without making your changes open source. The GPL-compatible licenses make it possible to combine Python with other software that is released under the GPL; the others don't.

Thanks to the many outside volunteers who have worked under Guido's direction to make these releases possible.

## C.2 Terms and conditions for accessing or otherwise using Python

## C.2.1 PSF LICENSE AGREEMENT FOR PYTHON 3.8.0

- 1. This LICENSE AGREEMENT is between the Python Software Foundation ("PSF"),  $\Box$  and
- the Individual or Organization ("Licensee") accessing and otherwise using  $\rightarrow$  Python
  - 3.8.0 software in source or binary form and its associated documentation.
- 2. Subject to the terms and conditions of this License Agreement, PSF hereby grants Licensee a nonexclusive, royalty-free, world-wide license to—reproduce,
  - analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use Python 3.8.0 alone or in any derivative version, provided, however, that PSF's License Agreement and PSF's notice.
  - copyright, i.e., "Copyright © 2001-2019 Python Software Foundation; All\_Rights
  - Reserved" are retained in Python 3.8.0 alone or in any derivative version prepared by Licensee.
- 3. In the event Licensee prepares a derivative work that is based on or incorporates Python 3.8.0 or any part thereof, and wants to make the derivative work available to others as provided herein, then Licensee hereby
- agrees to include in any such work a brief summary of the changes made to  $\rightarrow$  Python 3.8.0.
- 4. PSF is making Python 3.8.0 available to Licensee on an "AS IS" basis.
  PSF MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF
  EXAMPLE, BUT NOT LIMITATION, PSF MAKES NO AND DISCLAIMS ANY REPRESENTATION.
- WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT\_\_\_THE.
  - USE OF PYTHON 3.8.0 WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
- 5. PSF SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON 3.8.0 FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULTLOF
  - MODIFYING, DISTRIBUTING, OR OTHERWISE USING PYTHON 3.8.0, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
- - its terms and conditions.
- 7. Nothing in this License Agreement shall be deemed to create any →relationship
- of agency, partnership, or joint venture between PSF and Licensee. This→License
  - Agreement does not grant permission to use PSF trademarks or trade name in-

- →a
   trademark sense to endorse or promote products or services of Licensee, or
  →any
   third party.
- 8. By copying, installing or otherwise using Python 3.8.0, Licensee agrees to be bound by the terms and conditions of this License Agreement.

### C.2.2 BEOPEN.COM LICENSE AGREEMENT FOR PYTHON 2.0

#### BEOPEN PYTHON OPEN SOURCE LICENSE AGREEMENT VERSION 1

- 1. This LICENSE AGREEMENT is between BeOpen.com ("BeOpen"), having an office at 160 Saratoga Avenue, Santa Clara, CA 95051, and the Individual or Organization ("Licensee") accessing and otherwise using this software in source or binary form and its associated documentation ("the Software").
- 2. Subject to the terms and conditions of this BeOpen Python License Agreement, BeOpen hereby grants Licensee a non-exclusive, royalty-free, world-wide license to reproduce, analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use the Software alone or in any derivative version, provided, however, that the BeOpen Python License is retained in the Software, alone or in any derivative version prepared by Licensee.
- 3. Beopen is making the Software available to Licensee on an "AS IS" basis.
  BEOPEN MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF
  EXAMPLE, BUT NOT LIMITATION, BEOPEN MAKES NO AND DISCLAIMS ANY REPRESENTATION OR
  WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE
  USE OF THE SOFTWARE WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
- 4. BEOPEN SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF THE SOFTWARE FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THE SOFTWARE, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
- 5. This License Agreement will automatically terminate upon a material breach of its terms and conditions.
- 6. This License Agreement shall be governed by and interpreted in all respects by the law of the State of California, excluding conflict of law provisions. Nothing in this License Agreement shall be deemed to create any relationship of agency, partnership, or joint venture between BeOpen and Licensee. This License Agreement does not grant permission to use BeOpen trademarks or trade names in a trademark sense to endorse or promote products or services of Licensee, or any third party. As an exception, the "BeOpen Python" logos available at http://www.pythonlabs.com/logos.html may be used according to the permissions granted on that web page.
- 7. By copying, installing or otherwise using the software, Licensee agrees to be bound by the terms and conditions of this License Agreement.

## **C.2.3 CNRI LICENSE AGREEMENT FOR PYTHON 1.6.1**

- 1. This LICENSE AGREEMENT is between the Corporation for National Research Initiatives, having an office at 1895 Preston White Drive, Reston, VA 20191 ("CNRI"), and the Individual or Organization ("Licensee") accessing and otherwise using Python 1.6.1 software in source or binary form and its associated documentation.
- 2. Subject to the terms and conditions of this License Agreement, CNRI hereby grants Licensee a nonexclusive, royalty-free, world-wide license to reproduce, analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use Python 1.6.1 alone or in any derivative version, provided, however, that CNRI's License Agreement and CNRI's notice of copyright, i.e., "Copyright © 1995-2001 Corporation for National Research Initiatives; All Rights Reserved" are retained in Python 1.6.1 alone or in any derivative version prepared by Licensee. Alternately, in lieu of CNRI's License Agreement, Licensee may substitute the following text (omitting the quotes): "Python 1.6.1 is made available subject to the terms and conditions in CNRI's License Agreement. This Agreement together with Python 1.6.1 may be located on the Internet using the following unique, persistent identifier (known as a handle): 1895.22/1013. This Agreement may also be obtained from a proxy server on the Internet using the following URL: http://hdl.handle.net/1895.22/1013."
- 3. In the event Licensee prepares a derivative work that is based on or incorporates Python 1.6.1 or any part thereof, and wants to make the derivative work available to others as provided herein, then Licensee hereby agrees to include in any such work a brief summary of the changes made to Python 1.6.1.
- 4. CNRI is making Python 1.6.1 available to Licensee on an "AS IS" basis. CNRI MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF EXAMPLE, BUT NOT LIMITATION, CNRI MAKES NO AND DISCLAIMS ANY REPRESENTATION OR WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE USE OF PYTHON 1.6.1 WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
- 5. CNRI SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON 1.6.1 FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF MODIFYING, DISTRIBUTING, OR OTHERWISE USING PYTHON 1.6.1, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
- 6. This License Agreement will automatically terminate upon a material breach of its terms and conditions.
- 7. This License Agreement shall be governed by the federal intellectual property law of the United States, including without limitation the federal copyright law, and, to the extent such U.S. federal law does not apply, by the law of the Commonwealth of Virginia, excluding Virginia's conflict of law provisions. Notwithstanding the foregoing, with regard to derivative works based on Python 1.6.1 that incorporate non-separable material that was previously distributed under the GNU General Public License (GPL), the law of the Commonwealth of Virginia shall govern this License Agreement only as to issues arising under or with respect to Paragraphs 4, 5, and 7 of this License Agreement. Nothing in this License Agreement shall be deemed to create any relationship of agency, partnership, or joint venture between CNRI and Licensee. This License Agreement does not grant permission to use CNRI trademarks or trade name in a trademark sense to endorse or promote products or services of Licensee, or any third party.

8. By clicking on the "ACCEPT" button where indicated, or by copying, installing or otherwise using Python 1.6.1, Licensee agrees to be bound by the terms and conditions of this License Agreement.

### C.2.4 CWI LICENSE AGREEMENT FOR PYTHON 0.9.0 THROUGH 1.2

Copyright © 1991 - 1995, Stichting Mathematisch Centrum Amsterdam, The Netherlands. All rights reserved.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Stichting Mathematisch Centrum or CWI not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

STICHTING MATHEMATISCH CENTRUM DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL STICHTING MATHEMATISCH CENTRUM BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

# C.3 Licenses and Acknowledgements for Incorporated Software

This section is an incomplete, but growing list of licenses and acknowledgements for third-party software incorporated in the Python distribution.

### C.3.1 Mersenne Twister

The \_random module includes code based on a download from http://www.math.sci.hiroshima-u.ac.jp/~m-mat/MT/ MT2002/emt19937ar.html. The following are the verbatim comments from the original code:

A C-program for MT19937, with initialization improved 2002/1/26. Coded by Takuji Nishimura and Makoto Matsumoto.

Before using, initialize the state by using init\_genrand(seed) or init\_by\_array(init\_key, key\_length).

Copyright (C) 1997 - 2002, Makoto Matsumoto and Takuji Nishimura, All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- The names of its contributors may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR
A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR
CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,
EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR
PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF
LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING
NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS
SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Any feedback is very welcome. http://www.math.sci.hiroshima-u.ac.jp/~m-mat/MT/emt.html email: m-mat @ math.sci.hiroshima-u.ac.jp (remove space)

#### C.3.2 Sockets

The socket module uses the functions, getaddrinfo(), and getnameinfo(), which are coded in separate source files from the WIDE Project, http://www.wide.ad.jp/.

Copyright (C) 1995, 1996, 1997, and 1998 WIDE Project. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of the project nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE PROJECT AND CONTRIBUTORS ``AS IS'' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE PROJECT OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY

OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## C.3.3 Asynchronous socket services

The asynchat and asyncore modules contain the following notice:

Copyright 1996 by Sam Rushing

All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Sam Rushing not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

SAM RUSHING DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL SAM RUSHING BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

## C.3.4 Cookie management

The http.cookies module contains the following notice:

Copyright 2000 by Timothy O'Malley <timo@alum.mit.edu>

All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Timothy O'Malley not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

Timothy O'Malley DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL Timothy O'Malley BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

## C.3.5 Execution tracing

The trace module contains the following notice:

```
portions copyright 2001, Autonomous Zones Industries, Inc., all rights...
err... reserved and offered to the public under the terms of the
Python 2.2 license.
Author: Zooko O'Whielacronx
http://zooko.com/
mailto:zooko@zooko.com
Copyright 2000, Mojam Media, Inc., all rights reserved.
Author: Skip Montanaro
Copyright 1999, Bioreason, Inc., all rights reserved.
Author: Andrew Dalke
Copyright 1995-1997, Automatrix, Inc., all rights reserved.
Author: Skip Montanaro
Copyright 1991-1995, Stichting Mathematisch Centrum, all rights reserved.
Permission to use, copy, modify, and distribute this Python software and
its associated documentation for any purpose without fee is hereby
granted, provided that the above copyright notice appears in all copies,
and that both that copyright notice and this permission notice appear in
supporting documentation, and that the name of neither Automatrix,
Bioreason or Mojam Media be used in advertising or publicity pertaining to
distribution of the software without specific, written prior permission.
```

### C.3.6 UUencode and UUdecode functions

The uu module contains the following notice:

```
Copyright 1994 by Lance Ellinghouse
Cathedral City, California Republic, United States of America.
                      All Rights Reserved
Permission to use, copy, modify, and distribute this software and its
documentation for any purpose and without fee is hereby granted,
provided that the above copyright notice appear in all copies and that
both that copyright notice and this permission notice appear in
supporting documentation, and that the name of Lance Ellinghouse
not be used in advertising or publicity pertaining to distribution
of the software without specific, written prior permission.
LANCE ELLINGHOUSE DISCLAIMS ALL WARRANTIES WITH REGARD TO
THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND
FITNESS, IN NO EVENT SHALL LANCE ELLINGHOUSE CENTRUM BE LIABLE
FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES
WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN
ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT
OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.
Modified by Jack Jansen, CWI, July 1995:
- Use binascii module to do the actual line-by-line conversion
```

between ascii and binary. This results in a 1000-fold speedup. The C

version is still 5 times faster, though.
- Arguments more compliant with Python standard

#### C.3.7 XML Remote Procedure Calls

The xmlrpc.client module contains the following notice:

The XML-RPC client interface is

Copyright (c) 1999-2002 by Secret Labs AB Copyright (c) 1999-2002 by Fredrik Lundh

By obtaining, using, and/or copying this software and/or its associated documentation, you agree that you have read, understood, and will comply with the following terms and conditions:

Permission to use, copy, modify, and distribute this software and its associated documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appears in all copies, and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Secret Labs AB or the author not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

SECRET LABS AB AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANT-ABILITY AND FITNESS. IN NO EVENT SHALL SECRET LABS AB OR THE AUTHOR BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

## C.3.8 test\_epoll

The test\_epoll module contains the following notice:

Copyright (c) 2001-2006 Twisted Matrix Laboratories.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF

MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

#### C.3.9 Select kqueue

The select module contains the following notice for the kqueue interface:

Copyright (c) 2000 Doug White, 2006 James Knight, 2007 Christian Heimes All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS `AS IS' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## C.3.10 SipHash24

The file Python/pyhash.c contains Marek Majkowski' implementation of Dan Bernstein's SipHash24 algorithm. It contains the following note:

<MIT License>
Copyright (c) 2013 Marek Majkowski <marek@popcount.org>

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

```
Original location:
   https://github.com/majek/csiphash/

Solution inspired by code from:
   Samuel Neves (supercop/crypto_auth/siphash24/little)
   djb (supercop/crypto_auth/siphash24/little2)
   Jean-Philippe Aumasson (https://l31002.net/siphash/siphash24.c)
```

#### C.3.11 strtod and dtoa

The file Python/dtoa.c, which supplies C functions dtoa and strtod for conversion of C doubles to and from strings, is derived from the file of the same name by David M. Gay, currently available from http://www.netlib.org/fp/. The original file, as retrieved on March 16, 2009, contains the following copyright and licensing notice:

## C.3.12 OpenSSL

The modules hashlib, posix, ssl, crypt use the OpenSSL library for added performance if made available by the operating system. Additionally, the Windows and Mac OS X installers for Python may include a copy of the OpenSSL libraries, so we include a copy of the OpenSSL license here:

```
* Redistribution and use in source and binary forms, with or without
    * modification, are permitted provided that the following conditions
    * are met:
    * 1. Redistributions of source code must retain the above copyright
        notice, this list of conditions and the following disclaimer.
    * 2. Redistributions in binary form must reproduce the above copyright
        notice, this list of conditions and the following disclaimer in
        the documentation and/or other materials provided with the
        distribution.
    * 3. All advertising materials mentioning features or use of this
        software must display the following acknowledgment:
        "This product includes software developed by the OpenSSL Project
        for use in the OpenSSL Toolkit. (http://www.openssl.org/)"
    * 4. The names "OpenSSL Toolkit" and "OpenSSL Project" must not be used to
        endorse or promote products derived from this software without
        prior written permission. For written permission, please contact
        openssl-core@openssl.org.
    * 5. Products derived from this software may not be called "OpenSSL"
        nor may "OpenSSL" appear in their names without prior written
        permission of the OpenSSL Project.
    * 6. Redistributions of any form whatsoever must retain the following
        acknowledgment:
        "This product includes software developed by the OpenSSL Project
        for use in the OpenSSL Toolkit (http://www.openssl.org/)"
    * THIS SOFTWARE IS PROVIDED BY THE OpenSSL PROJECT ``AS IS'' AND ANY
   * EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
    * IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR
   * PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE OPENSSL PROJECT OR
   * ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL,
   * SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT
   * NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES;
   * LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
   * HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT,
    * STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE)
    * ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED
    * OF THE POSSIBILITY OF SUCH DAMAGE.
    * This product includes cryptographic software written by Eric Young
    * (eay@cryptsoft.com). This product includes software written by Tim
    * Hudson (tjh@cryptsoft.com).
Original SSLeay License
  /* Copyright (C) 1995-1998 Eric Young (eay@cryptsoft.com)
   * All rights reserved.
```

```
* This package is an SSL implementation written
* by Eric Young (eay@cryptsoft.com).
* The implementation was written so as to conform with Netscapes SSL.
* This library is free for commercial and non-commercial use as long as
* the following conditions are aheared to. The following conditions
* apply to all code found in this distribution, be it the RC4, RSA,
* lhash, DES, etc., code; not just the SSL code. The SSL documentation
* included with this distribution is covered by the same copyright terms
* except that the holder is Tim Hudson (tjh@cryptsoft.com).
* Copyright remains Eric Young's, and as such any Copyright notices in
* the code are not to be removed.
* If this package is used in a product, Eric Young should be given attribution
* as the author of the parts of the library used.
^{\star} This can be in the form of a textual message at program startup or
^{\star} in documentation (online or textual) provided with the package.
* Redistribution and use in source and binary forms, with or without
* modification, are permitted provided that the following conditions
* are met:
* 1. Redistributions of source code must retain the copyright
    notice, this list of conditions and the following disclaimer.
^{\star} 2. Redistributions in binary form must reproduce the above copyright
    notice, this list of conditions and the following disclaimer in the
    documentation and/or other materials provided with the distribution.
* 3. All advertising materials mentioning features or use of this software
    must display the following acknowledgement:
     "This product includes cryptographic software written by
     Eric Young (eay@cryptsoft.com) "
    The word 'cryptographic' can be left out if the rouines from the library
     being used are not cryptographic related :-).
* 4. If you include any Windows specific code (or a derivative thereof) from
     the apps directory (application code) you must include an acknowledgement:
     "This product includes software written by Tim Hudson (tjh@cryptsoft.com)"
* THIS SOFTWARE IS PROVIDED BY ERIC YOUNG ``AS IS'' AND
* ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
* IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE
* ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE
* FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
* DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS
* OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
* HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
* LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY
* OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF
* SUCH DAMAGE.
* The licence and distribution terms for any publically available version or
* derivative of this code cannot be changed. i.e. this code cannot simply be
* copied and put under another distribution licence
* [including the GNU Public Licence.]
*/
```

#### C.3.13 expat

The pyexpat extension is built using an included copy of the expat sources unless the build is configured --with-system-expat:

Copyright (c) 1998, 1999, 2000 Thai Open Source Software Center Ltd and Clark Cooper

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

#### C.3.14 libffi

The \_ctypes extension is built using an included copy of the libffi sources unless the build is configured --with-system-libffi:

Copyright (c) 1996-2008 Red Hat, Inc and others.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the ``Software''), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED ``AS IS'', WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

#### C.3.15 zlib

The zlib extension is built using an included copy of the zlib sources if the zlib version found on the system is too old to be used for the build:

Copyright (C) 1995-2011 Jean-loup Gailly and Mark Adler

This software is provided 'as-is', without any express or implied warranty. In no event will the authors be held liable for any damages arising from the use of this software.

Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it freely, subject to the following restrictions:

- The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required.
- 2. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software.
- 3. This notice may not be removed or altered from any source distribution.

Jean-loup Gailly Mark Adler

jloup@gzip.org madler@alumni.caltech.edu

#### C.3.16 cfuhash

The implementation of the hash table used by the tracemalloc is based on the cfuhash project:

Copyright (c) 2005 Don Owens All rights reserved.

This code is released under the BSD license:

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- \* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- \* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- \* Neither the name of the author nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS

FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

### C.3.17 libmpdec

The \_decimal module is built using an included copy of the libmpdec library unless the build is configured --with-system-libmpdec:

Copyright (c) 2008-2016 Stefan Krah. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

#### C.3.18 W3C C14N test suite

The C14N 2.0 test suite in the test package (Lib/test/xmltestdata/c14n-20/) was retrieved from the W3C website at https://www.w3.org/TR/xml-c14n2-testcases/ and is distributed under the 3-clause BSD license:

Copyright (c) 2013 W3C(R) (MIT, ERCIM, Keio, Beihang), All Rights Reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of works must retain the original copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the original copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

• Neither the name of the W3C nor the names of its contributors may be used to endorse or promote products derived from this work without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

### **APPENDIX**

D

# **COPYRIGHT**

Python and this documentation is:

Copyright © 2001-2019 Python Software Foundation. All rights reserved.

Copyright © 2000 BeOpen.com. All rights reserved.

Copyright © 1995-2000 Corporation for National Research Initiatives. All rights reserved.

Copyright © 1991-1995 Stichting Mathematisch Centrum. All rights reserved.

See *History and License* for complete license and permissions information.

# **INDEX**

Non-alphabetical	Α
, 223	abort(),39
2to3, <b>223</b>	abs
>>>, 223	built-in function, 63
all(package variable), 39	abstract base class, 223
dict (module attribute), 120	allocfunc (C type), 213
doc (module attribute), 120	annotation, 223
file (module attribute), 120, 121	argument, 223
future, 227	argv (in module sys), 143
import	ascii
built-in function, 40	built-in function, 59
loader (module attribute), 120	asynchronous context manager, 224
main	asynchronous generator, 224
module, 10, 140, 149	asynchronous generator iterator, 224
name ( <i>module attribute</i> ), 120, 121	asynchronous iterable, 224
package(module attribute), 120	asynchronous iterator, 224
slots, 233	attribute, 224
	awaitable, 224
$\_$ inittab ( $C$ type), 42	
_Py_c_diff (C function), 84	В
_Py_c_neg (C function), 85	BDFL, <b>224</b>
$_{\rm Py\_c\_pow}$ (C function), 85	binary file, 224
_Py_c_prod (C function), 85	binaryfunc ( <i>C type</i> ), 215
_Py_c_quot (C function), 85	buffer interface
_Py_c_sum (C function), 84	(see buffer protocol), 69
_Py_InitializeMain ( <i>C function</i> ), 169	buffer object
_Py_NoneStruct ( <i>C variable</i> ), 179	(see buffer protocol), 69
_Py_TPFLAGS_HAVE_VECTORCALL (built-in vari-	buffer protocol, 69
able), 198	built-in function
_PyBytes_Resize( <i>C function</i> ), 87	import,40
_PyCFunctionFast ( <i>C type</i> ), 181	abs, 63
_PyCFunctionFastWithKeywords (C type), 181	ascii,59
_PyImport_Fini (C function), 42	bytes, 59
_PyImport_Init (C function), 42	classmethod, 182
_PyObject_FastCallDict (C function), 61	compile, 40
_PyObject_New (C function), 179	divmod, 63
_PyObject_NewVar ( <i>C function</i> ), 179	float, 65
$_{ t PyObject\_Vectorcall}$ ( $C$ function), $60$	hash, 61, 195
_PyTuple_Resize ( <i>C function</i> ), 108	int, 65
_thread	len, 62, 65, 67, 110, 113, 115
module, 146	pow, 63, 64
	repr, 59, 194

staticmethod, 182	E
tuple, 66, 111	EAFP, <b>226</b>
type, 62	environment variable
builtins	exec_prefix,4
module, 10, 140, 149	PATH, 11
bytearray	prefix,4
object, 87	PYTHON*, 138
bytecode, 225	PYTHONCOERCECLOCALE, 166
bytes	PYTHONDEBUG, 138
built-in function, 59	PYTHONDONTWRITEBYTECODE, 138
object, 86	PYTHONDUMPREFS, 190
bytes-like object, 224	PYTHONHASHSEED, 138
	PYTHONHOME, 11, 138, 143, 144, 162
C	
calloc(), 171	PYTHONINSPECT, 139
Capsule	PYTHONIOENCODING, 141
object, 129	PYTHONLEGACYWINDOWSFSENCODING, 139
C-contiguous, 72, 225	PYTHONLEGACYWINDOWSSTDIO, 139
	PYTHONMALLOC, 172, 175, 177
class, 225 class variable, 225	PYTHONMALLOCSTATS, 172
classmethod	PYTHONNOUSERSITE, 139
built-in function, 182	PYTHONOPTIMIZE, 139
cleanup functions, 39	PYTHONPATH, 11, 138, 162
close() (in module os), 150	PYTHONUNBUFFERED, 139
	PYTHONUTF8, 166
CO_FUTURE_DIVISION ( <i>C variable</i> ), 19	PYTHONVERBOSE, 140
code object, 118	EOFError (built-in exception), 119
coercion, 225	exc_info() (in module sys), 9
compile 40	exec_module ( <i>C function</i> ), 124
built-in function, 40	exec_prefix,4
complex number, 225	executable (in module sys), 142
object, 84	exit(),39
context manager, 225	expression, 226
context variable, 225	extension module, 226
contiguous, 72, 225	F
copyright (in module sys), 142	
coroutine, 225	file
coroutine function, 225	object, 119
CPython, 225	file object, 226
create_module( <i>C function</i> ), 123	file-like object, 227
D	finder, <b>227</b>
	float
decorator, 225	built-in function, 65
descrgetfunc (C type), 214	floating point
descriptor, 226	object, 83
descrsetfunc(Ctype), 214	floor division, 227
destructor (C type), 214	Fortran contiguous, 72, 225
dictionary, 226	free(),171
object,111	freefunc ( $C$ type), 214
dictionary view, 226	freeze utility,42
divmod	frozenset
built-in function, 63	object, 114
docstring, 226	f-string, 226
duck-typing, 226	function, 227
	object, 115

function annotation, 227	len
	built-in function, 62, 65, 67, 110, 113, 115
G	lenfunc ( $C type$ ), 214
garbage collection, 227	list, <b>229</b>
generator, 227	object,110
generator expression, 227	list comprehension, 229
generator iterator, 227	loader, <b>230</b>
generic function, 228	lock, interpreter, 144
getattrfunc( <i>Ctype</i> ), 214	long integer
getattrofunc ( <i>Ctype</i> ), 214	object, 80
getbufferproc( <i>Ctype</i> ), 214	LONG_MAX, 81
getiterfunc( <i>Ctype</i> ), 214	M
GIL, <b>228</b>	IVI
global interpreter lock, 144, 228	magic
11	method, 230
Н	magic method, 230
hash	main(), 141, 143
built-in function, 61, 195	malloc(),171
hashable, 228	mapping, 230
hash-based pyc, 228	object, 111
hashfunc ( <i>Ctype</i> ), 214	memoryview
1	object, 128
	meta path finder, 230
IDLE, 228	metaclass, 230
immutable, 228	METH_CLASS (built-in variable), 182
import path, 228	METH_COEXIST (built-in variable), 182
importer, 228	METH_FASTCALL (built-in variable), 181
importing, 228	METH_NOARGS (built-in variable), 182
incr_item(), 9, 10	METH_O (built-in variable), 182
initproc ( <i>C type</i> ), 214	METH_STATIC (built-in variable), 182
inquiry ( <i>C type</i> ), 219	METH_VARARGS (built-in variable), 181
instancemethod	method, 230
object, 117	magic, 230
int	object, 117
built-in function, 65	special, 233
integer	method resolution order, 230
object, 80	MethodType (in module types), 116, 117
interactive, 228	module, 230
interpreted, 228	main, 10, 140, 149
interpreter lock, 144	_thread, 146
interpreter shutdown, 228	builtins, 10, 140, 149
iterable, 229	object, 120
iterator, 229	search path, 10, 140, 142
iternextfunc( <i>Ctype</i> ), 214	signal, 29
	sys, 10, 140, 149
K	module spec, 230
key function, 229	modules (in module sys), 39, 140
KeyboardInterrupt (built-in exception), 29	Module Type (in module types), 120
keyword argument, 229	MRO, <b>230</b>
-1	mutable, 230
L	N
lambda, 229	
LBYL, 229	named tuple, 230 namespace. 231
, =-	Hallesbace, 431

namespace package, 231	platform( <i>in module sys</i> ), 142
nested scope, 231	portion, 232
newfunc ( $Ctype$ ), 214	positional argument, 232
new-style class, 231	pow
None	built-in function, 63, 64
object, 80	prefix,4
numeric	provisional API, 232
object, 80	provisional package, 232
	$Py\_ABS(Cmacro), 4$
0	Py_AddPendingCall (C function), 150
object, 231	Py_AddPendingCall(),150
bytearray, 87	Py_AtExit ( $C$ function), 39
bytes, 86	Py_BEGIN_ALLOW_THREADS, 144
Capsule, 129	Py_BEGIN_ALLOW_THREADS (C macro), 147
code, 118	Py_BLOCK_THREADS (C macro), 147
complex number, 84	Py_buffer ( <i>C type</i> ), 70
dictionary, 111	Py_buffer.buf( <i>C member</i> ), 70
<del>-</del>	Py_buffer.format( <i>C member</i> ), 70
file, 119	Py_buffer.internal (C member), 71
floating point, 83	Py_buffer.itemsize( <i>C member</i> ), 70
frozenset, 114	Py_buffer.len( <i>C member</i> ), 70
function, 115	Py_buffer.ndim(C member), 70
instancemethod, 117	Py_buffer.obj(C member), 70
integer, 80	Py_buffer.readonly( <i>C member</i> ),70
list, 110	
long integer, 80	Py_buffer.shape( <i>C member</i> ),71
mapping, 111	Py_buffer.strides( <i>C member</i> ),71
memoryview, 128	Py_buffer.suboffsets( <i>C member</i> ),71
method, 117	Py_BuildValue (C function), 50
module, 120	Py_BytesMain(C function), 15
None, $80$	Py_BytesWarningFlag ( <i>C variable</i> ), 138
numeric, 80	Py_CHARMASK (C macro), 4
sequence, 86	Py_CLEAR (C function), 21
set, 114	Py_CompileString(C function), 18
tuple, 107	Py_CompileString(),19
type, 5, 77	Py_CompileStringExFlags(C function), 18
objobjargproc ( <i>C type</i> ), 215	Py_CompileStringFlags ( $C$ function), 18
objobjproc ( <i>C type</i> ), 215	Py_CompileStringObject( $C\ function$ ), 18
OverflowError (built-in exception), 81, 82	$Py\_complex(Ctype), 84$
_	Py_DebugFlag ( <i>C variable</i> ), 138
P	Py_DecodeLocale ( $C$ function), 36
package, 231	Py_DECREF ( $C$ function), 21
package variable	Py_DECREF(),5
all, 39	Py_DEPRECATED (C macro), 5
parameter, 231	Py_DontWriteBytecodeFlag( $C$ variable), 138
PATH, 11	Py_Ellipsis ( <i>C variable</i> ), 128
path	Py_EncodeLocale ( $C$ function), 36
module search, 10, 140, 142	Py_END_ALLOW_THREADS, 144
path (in module sys), 10, 140, 142	Py_END_ALLOW_THREADS (C macro), 147
path (in module 333), 10, 140, 142 path based finder, 232	Py_EndInterpreter (C function), 150
path entry, 232	Py_EnterRecursiveCall ( <i>C function</i> ), 31
path entry finder, 232	Py_eval_input ( <i>C variable</i> ), 19
	Py_Exit (C function), 39
path entry hook, 232	Py_ExitStatusException (C function), 157
path-like object, 232	Py_False ( <i>C variable</i> ), 83
PEP, 232	<del>-</del>

Py_FatalError ( <i>C function</i> ), 39	Py_PreInitializeFromArgs (C function), 159
Py_FatalError(), 143	Py_PreInitializeFromBytesArgs (C function),
Py_FdIsInteractive ( <i>C function</i> ), 35	159
Py_file_input (C variable), 19	Py_PRINT_RAW, 120
Py_Finalize (C function), 140	Py_QuietFlag ( <i>C variable</i> ), 139
Py_FinalizeEx (C function), 140	Py_REFCNT (C macro), 180
Py_FinalizeEx(), 39, 140, 150	Py_ReprEnter (C function), 31
Py_FrozenFlag (C variable), 138	Py_ReprLeave (C function), 32
Py_GetBuildInfo (C function), 143	Py_RETURN_FALSE ( <i>C macro</i> ), 83
Py_GetCompiler ( <i>C function</i> ), 142	Py_RETURN_NONE (C macro), 80
Py_GetCopyright (C function), 142	Py_RETURN_NOTIMPLEMENTED (C macro), 57
Py_GETENV (C macro), 5	Py_RETURN_RICHCOMPARE (C function), 201
Py_GetExecPrefix (C function), 141	Py_RETURN_TRUE ( <i>C macro</i> ), 83
Py_GetExecPrefix(),11	Py_RunMain ( <i>C function</i> ), 168
Py_GetPath ( <i>C function</i> ), 142	Py_SetPath ( <i>C function</i> ), 142
Py_GetPath(), 11, 141, 142	Py_SetPath(), 142
Py_GetPlatform ( <i>C function</i> ), 142	Py_SetProgramName (C function), 141
Py_GetPrefix ( <i>C function</i> ), 141	Py_SetProgramName(), 11, 140142
Py_GetPrefix(),11	Py_SetPythonHome ( <i>C function</i> ), 143
Py_GetProgramFullPath ( <i>C function</i> ), 142	Py_SetStandardStreamEncoding (C function),
Py_GetProgramFullPath(), 11	141
Py_GetProgramName ( <i>C function</i> ), 141	Py_single_input ( <i>C variable</i> ), 19
Py_GetPythonHome ( <i>C function</i> ), 143	Py_SIZE (C macro), 180
Py_GetVersion (C function), 142	PY_SSIZE_T_MAX, 82
Py_HashRandomizationFlag(Cvariable), 138	Py_STRINGIFY (C macro), 4
Py_IgnoreEnvironmentFlag ( <i>C variable</i> ), 138	Py_TPFLAGS_BASE_EXC_SUBCLASS (built-in vari- able), 198
Py_INCREF (C function), 21	
Py_INCREF(),5	Py_TPFLAGS_BASETYPE (built-in variable), 197
Py_Initialize ( <i>C function</i> ), 140	Py_TPFLAGS_BYTES_SUBCLASS (built-in variable),
Py_Initialize(), 10, 141, 150	198
Py_InitializeEx (C function), 140	Py_TPFLAGS_DEFAULT (built-in variable), 197
Py_InitializeFromConfig ( <i>C function</i> ), 164	Py_TPFLAGS_DICT_SUBCLASS (built-in variable),
Py_InspectFlag(C variable), 138	198
Py_InteractiveFlag (C variable), 139	Py_TPFLAGS_HAVE_FINALIZE (built-in variable),
Py_IsInitialized ( <i>C function</i> ), 140	198
Py_IsInitialized(),11	Py_TPFLAGS_HAVE_GC (built-in variable), 197
Py_IsolatedFlag(C variable), 139	Py_TPFLAGS_HEAPTYPE (built-in variable), 197
Py_LeaveRecursiveCall (C function), 31	Py_TPFLAGS_LIST_SUBCLASS (built-in variable),
Py_LegacyWindowsFSEncodingFlag (C vari-	198
able), 139	Py_TPFLAGS_LONG_SUBCLASS (built-in variable),
Py_LegacyWindowsStdioFlag( <i>C variable</i> ), 139	198
Py_Main ( <i>C function</i> ), 15	Py_TPFLAGS_METHOD_DESCRIPTOR (built-in vari-
Ру_МАХ ( <i>C macro</i> ), 4	able), 198
Py_MEMBER_SIZE (C macro), 4	Py_TPFLAGS_READY (built-in variable), 197
Ру_МІN ( <i>C macro</i> ), 4	Py_TPFLAGS_READYING (built-in variable), 197
Py_mod_create( <i>C variable</i> ), 123	Py_TPFLAGS_TUPLE_SUBCLASS (built-in variable),
Py_mod_exec( <i>C variable</i> ), 124	198
Py_NewInterpreter (C function), 149	Py_TPFLAGS_TYPE_SUBCLASS (built-in variable),
Py_None ( <i>C variable</i> ), 80	198
Py_NoSiteFlag ( <i>C variable</i> ), 139	Py_TPFLAGS_UNICODE_SUBCLASS (built-in vari-
Py_NotImplemented(C variable), 57	able), 198
Py_NoUserSiteDirectory( <i>C variable</i> ), 139	Py_tracefunc( <i>Ctype</i> ), 151
Py_OptimizeFlag( <i>C variable</i> ), 139	Py_True ( <i>C variable</i> ), 83
Py_PreInitialize ( <i>C function</i> ), 159	Py_tss_NEEDS_INIT (C macro), 153

Py_tss_t ( <i>Ctype</i> ), 153	PyAsyncMethods.am_await( <i>C member</i> ), 213
Py_TYPE ( <i>C macro</i> ), 180	PyBool_Check ( $C$ function), 83
Py_UCS1 ( <i>C type</i> ), 89	PyBool_FromLong ( $C$ function), 83
Py_UCS2 ( <i>C type</i> ), 89	PyBUF_ANY_CONTIGUOUS (C macro), 72
Py_UCS4 ( <i>C type</i> ), 89	PyBUF_C_CONTIGUOUS (C macro), 72
Py_UNBLOCK_THREADS (C macro), 147	PyBUF_CONTIG (C macro), 73
Py_UnbufferedStdioFlag( <i>C variable</i> ), 139	PyBUF_CONTIG_RO (C macro), 73
Py_UNICODE (C type), 89	PyBUF_F_CONTIGUOUS (C macro), 72
Py_UNICODE_IS_HIGH_SURROGATE (C macro), 92	PyBUF_FORMAT (C macro), 71
Py_UNICODE_IS_LOW_SURROGATE (C macro), 92	PyBUF_FULL (C macro), 73
Py_UNICODE_IS_SURROGATE (C macro), 92	PyBUF_FULL_RO (C macro), 73
Py_UNICODE_ISALNUM (C function), 91	PyBUF_INDIRECT (C macro), 72
Py_UNICODE_ISALPHA (C function), 91	PyBUF_ND (C macro), 72
Py_UNICODE_ISDECIMAL (C function), 91	PyBUF_RECORDS (C macro), 73
Py_UNICODE_ISDIGIT (C function), 91	PyBUF_RECORDS_RO (C macro), 73
Py_UNICODE_ISLINEBREAK (C function), 91	PyBUF_SIMPLE (C macro), 72
Py_UNICODE_ISLOWER (C function), 91	PyBUF_STRIDED (C macro), 73
Py_UNICODE_ISNUMERIC (C function), 91	PyBUF_STRIDED_RO (C macro), 73
Py_UNICODE_ISPRINTABLE (C function), 92	PyBUF_STRIDES (C macro), 72
Py_UNICODE_ISSPACE (C function), 91	PyBUF_WRITABLE (C macro), 71
Py_UNICODE_ISTITLE (C function), 91	PyBuffer_FillContiguousStrides ( $C$ func-
Py_UNICODE_ISUPPER (C function), 91	tion), 75
Py_UNICODE_JOIN_SURROGATES (C macro), 92	PyBuffer_FillInfo (C function), 75
Py_UNICODE_TODECIMAL (C function), 92	PyBuffer_FromContiguous ( <i>C function</i> ), 75
Py_UNICODE_TODIGIT (C function), 92	PyBuffer_GetPointer (C function), 75
Py_UNICODE_TOLOWER (C function), 92	PyBuffer_IsContiguous (C function), 75
Py_UNICODE_TONUMERIC (C function), 92	PyBuffer_Release ( <i>C function</i> ), 74
Py_UNICODE_TOTITLE (C function), 92	PyBuffer_SizeFromFormat (C function), 75
Py_UNICODE_TOUPPER (C function), 92	PyBuffer_ToContiguous (C function), 75
Py_UNREACHABLE (C macro), 4	PyBufferProcs, 69
Py_UNUSED (C macro), 5	PyBufferProcs (C type), 212
Py_VaBuildValue (C function), 51	PyBufferProcs.bf_getbuffer(C member), 212
PY_VECTORCALL_ARGUMENTS_OFFSET (C vari-	<pre>PyBufferProcs.bf_releasebuffer(Cmember),</pre>
able), 61	212
Py_VerboseFlag ( <i>C variable</i> ), 139	PyByteArray_AS_STRING(C function), 88
Py_VISIT (C function), 218	PyByteArray_AsString ( $C$ function), 88
Py_XDECREF (C function), 21	PyByteArray_Check (C function), 88
Py_XDECREF(), 10	PyByteArray_CheckExact (C function), 88
Py_XINCREF (C function), 21	PyByteArray_Concat (C function), 88
PyAnySet_Check (C function), 114	PyByteArray_FromObject(C function),88
PyAnySet_CheckExact (C function), 114	PyByteArray_FromStringAndSize (C function),
PyArg_Parse (C function), 49	88
PyArg_ParseTuple (C function), 48	PyByteArray_GET_SIZE (C function), 88
PyArg_ParseTupleAndKeywords ( $C$ function), 49	PyByteArray_Resize(C function), 88
PyArg_UnpackTuple (C function), 49	PyByteArray_Size (C function), 88
PyArg_ValidateKeywordArguments ( $C$ func-	PyByteArray_Type ( <i>C variable</i> ), 87
tion), 49	PyByteArrayObject (Ctype), 87
PyArg_VaParse (C function), 49	PyBytes_AS_STRING (C function), 87
PyArg_VaParseTupleAndKeywords (C function),	PyBytes_AsString (C function), 87
49	PyBytes_AsStringAndSize (C function), 87
PyASCIIObject ( <i>Ctype</i> ), 89	PyBytes_Check (C function), 86
PyAsyncMethods ( <i>C type</i> ), 213	PyBytes_CheckExact (C function), 86
PyAsyncMethods.am_aiter( <i>C member</i> ), 213	PyBytes_Concat (C function), 87
PyAsyncMethods.am_anext( <i>C member</i> ), 213	PyBytes_ConcatAndDel (C function), 87

PyBytes_FromFormat (C function), 86	PyCodec_NameReplaceErrors (C function), 55
PyBytes_FromFormatV(C function), 87	PyCodec_Register (C function), 53
PyBytes_FromObject (C function), 87	PyCodec_RegisterError(C function), 54
PyBytes_FromString (C function), 86	PyCodec_ReplaceErrors (C function), 55
PyBytes_FromStringAndSize(C function), 86	PyCodec_StreamReader(C function), 54
PyBytes_GET_SIZE (C function), 87	PyCodec_StreamWriter ( $C$ function), 54
PyBytes_Size (C function), 87	PyCodec_StrictErrors (C function), 54
PyBytes_Type (C variable), 86	${\tt PyCodec\_XMLCharRefReplaceErrors}~(C~func-$
PyBytesObject (Ctype), 86	tion), 55
PyCallable_Check ( $C$ function), 59	PyCodeObject ( <i>Ctype</i> ), 118
PyCallIter_Check ( $C$ function), 126	PyCompactUnicodeObject ( $Ctype$ ), $89$
PyCallIter_New ( <i>C function</i> ), 126	PyCompilerFlags ( $Ctype$ ), 19
PyCallIter_Type ( <i>C variable</i> ), 126	PyCompilerFlags.cf_feature_version $(C$
PyCapsule ( $Ctype$ ), 129	member), 19
PyCapsule_CheckExact (C function), 130	PyCompilerFlags.cf_flags(C member), 19
PyCapsule_Destructor (C type), 130	PyComplex_AsCComplex ( $C$ function), $85$
PyCapsule_GetContext (C function), 130	PyComplex_Check (C function), 85
PyCapsule_GetDestructor (C function), 130	PyComplex_CheckExact (C function), 85
PyCapsule_GetName (C function), 130	PyComplex_FromCComplex ( $C$ function), $85$
PyCapsule_GetPointer(C function), 130	PyComplex_FromDoubles ( $C$ function), $85$
PyCapsule_Import (C function), 130	PyComplex_ImagAsDouble ( $C$ function), $85$
PyCapsule_IsValid ( <i>C function</i> ), 130	PyComplex_RealAsDouble ( $C$ function), $85$
PyCapsule_New (C function), 130	PyComplex_Type ( <i>C variable</i> ), 85
PyCapsule_SetContext (C function), 131	PyComplexObject ( $Ctype$ ), $85$
PyCapsule_SetDestructor (C function), 131	PyConfig ( $C type$ ), $160$
PyCapsule_SetName (C function), 131	PyConfig_Clear ( $C$ function), 160
PyCapsule_SetPointer(C function), 131	${\tt PyConfig\_InitIsolatedConfig} \ ({\it Cfunction}), 160$
PyCell_Check (C function), 118	PyConfig_InitPythonConfig( $C function$ ), $160$
PyCell_GET (C function), 118	PyConfig_Read ( $C$ function), 160
PyCell_Get (C function), 118	PyConfig_SetArgv ( $C$ function), 160
PyCell_New (C function), 118	PyConfig_SetBytesArgv (C function), 160
PyCell_SET (C function), 118	PyConfig_SetBytesString ( $C$ function), $160$
PyCell_Set (C function), 118	PyConfig_SetString(Cfunction), 160
PyCell_Type ( <i>C variable</i> ), 118	PyConfig_SetWideStringList (C function), 160
PyCellObject (Ctype), 118	PyConfig.argv(C member), 161
PyCFunction ( $C type$ ), 181	PyConfig.base_exec_prefix( <i>C member</i> ), 161
PyCFunctionWithKeywords (C type), 181	PyConfig.base_executable( <i>C member</i> ), 161
PyCode_Check (C function), 118	PyConfig.base_prefix(C member), 161
PyCode_GetNumFree (C function), 118	PyConfig.buffered_stdio( <i>C member</i> ), 161
PyCode_New (C function), 118	PyConfig.bytes_warning(C member), 161
PyCode_NewEmpty (C function), 119	PyConfig.check_hash_pycs_mode ( $C\ member$ ),
PyCode_NewWithPosOnlyArgs (C function), 119	161
PyCode_Type ( <i>C variable</i> ), 118	PyConfig.configure_c_stdio(C member), 161
${\tt PyCodec\_BackslashReplaceErrors} \ \ (C \ \textit{func-}$	PyConfig.dev_mode( <i>C member</i> ), 161
tion), 55	PyConfig.dump_refs( <i>C member</i> ), 161
PyCodec_Decode (C function), 54	PyConfig.exec_prefix(C member), 161
PyCodec_Decoder (C function), 54	PyConfig.executable ( <i>C member</i> ), 161
PyCodec_Encode (C function), 53	PyConfig.faulthandler( <i>C member</i> ), 161
PyCodec_Encoder (C function), 54	PyConfig.filesystem_encoding ( $C$ member),
PyCodec_IgnoreErrors (C function), 54	162
${\tt PyCodec\_IncrementalDecoder}~(C~\textit{function}), 54$	PyConfig.filesystem_errors( <i>C member</i> ), 162
PyCodec_IncrementalEncoder (C function), 54	PyConfig.hash_seed( <i>C member</i> ), 162
PyCodec_KnownEncoding (C function), 53	PyConfig.home ( $C$ member), $162$
PyCodec_LookupError (C function), 54	PyConfig.import_time ( <i>C member</i> ), 162

PyConfig.inspect( <i>C member</i> ), 162	PyContextVar_CheckExact (C function), 132
PyConfig.install_signal_handlers (C mem-	PyContextVar_Get (C function), 133
ber), 162	PyContextVar_New (C function), 133
PyConfig.interactive( <i>C member</i> ), 162	PyContextVar_Reset (C function), 133
PyConfig.isolated( <i>C member</i> ), 162	PyContextVar_Set (C function), 133
PyConfig.legacy_windows_stdio ( $C$ member),	PyContextVar_Type ( <i>C variable</i> ), 132
162	PyCoro_CheckExact (C function), 132
PyConfig.malloc_stats( <i>C member</i> ), 162	PyCoro_New (C function), 132
PyConfig.module_search_paths ( $C$ member),	PyCoro_Type ( <i>C variable</i> ), 132
162	PyCoroObject ( <i>Ctype</i> ), 132
PyConfig.module_search_paths_set ( $\emph{C}$ mem-	PyDate_Check (C function), 134
ber), 162	PyDate_CheckExact (C function), 134
PyConfig.optimization_level( <i>C member</i> ), 162	PyDate_FromDate (C function), 134
PyConfig.parse_argv( <i>C member</i> ),163	PyDate_FromTimestamp(C function), 136
PyConfig.parser_debug( <i>C member</i> ),163	PyDateTime_Check ( $C$ function), 134
PyConfig.pathconfig_warnings ( $C$ member),	PyDateTime_CheckExact (C function), 134
163	PyDateTime_DATE_GET_HOUR(C function), 135
PyConfig.prefix ( <i>C member</i> ), 163 PyConfig.program_name ( <i>C member</i> ), 163	PyDateTime_DATE_GET_MICROSECOND (C function), 135
PyConfig.pycache_prefix(C member), 163	PyDateTime_DATE_GET_MINUTE (C function), 135
PyConfig.pythonpath_env( <i>C member</i> ), 162	PyDateTime_DATE_GET_SECOND (C function), 135
PyConfig.quiet (C member), 163	PyDateTime_DELTA_GET_DAYS (C function), 136
PyConfig.run_command( <i>C member</i> ), 163	PyDateTime_DELTA_GET_MICROSECONDS (C
PyConfig.run_filename( <i>C member</i> ), 163	function), 136
PyConfig.run_module( <i>C member</i> ), 163	PyDateTime_DELTA_GET_SECONDS ( $C$ function).
PyConfig.show_alloc_count( <i>C member</i> ), 163	136
PyConfig.show_ref_count( <i>C member</i> ), 163	PyDateTime_FromDateAndTime ( $C$ function), 134
PyConfig.site_import( <i>C member</i> ), 163	PyDateTime_FromDateAndTimeAndFold (C
PyConfig.skip_source_first_line ( $\emph{C}$ mem-	function), 134
ber), 163	PyDateTime_FromTimestamp ( $C$ function), 136
PyConfig.stdio_encoding( $C$ member), $163$	PyDateTime_GET_DAY ( <i>C function</i> ), 135
PyConfig.stdio_errors( <i>C member</i> ), 163	PyDateTime_GET_MONTH(C function), 135
PyConfig.tracemalloc( <i>C member</i> ), 164	PyDateTime_GET_YEAR ( <i>C function</i> ), 135
PyConfig.use_environment( <i>C member</i> ), 164	PyDateTime_TIME_GET_HOUR ( <i>C function</i> ), 135
PyConfig.use_hash_seed( <i>C member</i> ), 162	PyDateTime_TIME_GET_MICROSECOND ( $C\ func-$
<pre>PyConfig.user_site_directory (C member),</pre>	tion), 136
164	PyDateTime_TIME_GET_MINUTE (C function), 136
PyConfig.verbose ( <i>C member</i> ), 164	PyDateTime_TIME_GET_SECOND (C function), 136
PyConfig.warnoptions ( <i>C member</i> ), 164	PyDateTime_TimeZone_UTC (C variable), 134
PyConfig.write_bytecode( <i>C member</i> ), 164	PyDelta_Check (C function), 134
PyConfig.xoptions ( <i>C member</i> ), 164	PyDelta_CheckExact (C function), 134
PyContext ( <i>C type</i> ), 132 PyContext_CheckExact ( <i>C function</i> ), 132	PyDelta_FromDSU ( <i>C function</i> ), 135 PyDescr_IsData ( <i>C function</i> ), 126
PyContext_ClearFreeList (C function), 132	PyDescr_NewClassMethod ( <i>C function</i> ), 126
PyContext_Copy ( <i>C function</i> ), 133	PyDescr_NewGetSet ( <i>C function</i> ), 126
PyContext_CopyCurrent (C function), 133	PyDescr_NewMember ( <i>C function</i> ), 126
PyContext_Enter (C function), 133	PyDescr_NewMethod ( <i>C function</i> ), 126
PyContext_Exit (C function), 133	PyDescr_NewWrapper ( <i>C function</i> ), 126
PyContext_New (C function), 133	PyDict_Check ( <i>C function</i> ), 111
PyContext_Type ( <i>C variable</i> ), 132	PyDict_CheckExact ( <i>C function</i> ), 111
PyContextToken (C type), 132	PyDict_Clear (C function), 112
PyContextToken_CheckExact (C function), 133	PyDict_ClearFreeList (C function), 114
PyContextToken_Type ( <i>C variable</i> ), 132	PyDict_Contains ( <i>C function</i> ), 112
PyContextVar (C type), 132	PyDict_Copy ( <i>C function</i> ), 112
i y concexe var (e type), 132	1 / D 1 0 0 _ 0 0 p f (0 / timettett), 112

PyDict_DelItem (C function), 112	PyErr_SetFromErrnoWithFilenameObject ( $C$
PyDict_DelItemString (C function), 112	function), 24
PyDict_GetItem (C function), 112	PyErr_SetFromErrnoWithFilenameObjects
PyDict_GetItemString (C function), 112	(C function), 25
PyDict_GetItemWithError (C function), 112	PyErr_SetFromWindowsErr (C function), 25
PyDict_Items (C function), 112	PyErr_SetFromWindowsErrWithFilename ( $C$
PyDict_Keys (C function), 112	function), 25
PyDict_Merge (C function), 113	PyErr_SetImportError(C function), 25
PyDict_MergeFromSeq2 (C function), 113	PyErr_SetImportErrorSubclass (C function),
PyDict_New (C function), 111	26
PyDict_Next (C function), 113	PyErr_SetInterrupt ( $C$ function), 29
PyDict_SetDefault (C function), 112	PyErr_SetNone (C function), 24
PyDict_SetItem ( $C$ function), 112	PyErr_SetObject ( $C$ function), 24
PyDict_SetItemString ( $C$ function), 112	PyErr_SetString ( $C$ function), 24
PyDict_Size (C function), 113	PyErr_SetString(), $9$
PyDict_Type ( <i>C variable</i> ), 111	PyErr_SyntaxLocation ( $C$ function), 26
PyDict_Update (C function), 113	PyErr_SyntaxLocationEx(C function), 26
PyDict_Values (C function), 112	PyErr_SyntaxLocationObject ( $C$ function), 26
PyDictObject ( $Ctype$ ), 111	PyErr_WarnEx (C function), 26
PyDictProxy_New ( $C$ function), 111	PyErr_WarnExplicit ( $C$ function), 27
PyErr_BadArgument ( $C$ function), 24	PyErr_WarnExplicitObject ( $C$ function), 26
PyErr_BadInternalCall ( <i>C function</i> ), 26	PyErr_WarnFormat ( <i>C function</i> ), 27
PyErr_CheckSignals (C function), 29	PyErr_WriteUnraisable ( $C$ function), 23
PyErr_Clear (C function), 23	PyEval_AcquireLock (C function), 149
PyErr_Clear(), 9, 10	PyEval_AcquireThread (C function), 148
PyErr_ExceptionMatches (C function), 27	PyEval_AcquireThread(), 146
PyErr_ExceptionMatches(), 10	PyEval_EvalCode ( $C$ function), 18
PyErr_Fetch (C function), 27	PyEval_EvalCodeEx (C function), 18
PyErr_Format (C function), 24	PyEval_EvalFrame (C function), 18
PyErr_FormatV (C function), 24	PyEval_EvalFrameEx ( $C$ function), 18
PyErr_GetExcInfo (C function), 28	PyEval_GetBuiltins (C function), 53
PyErr_GivenExceptionMatches (C function), 27	PyEval_GetFrame (C function), 53
PyErr_NewException (C function), 29	PyEval_GetFuncDesc (C function), 53
PyErr_NewExceptionWithDoc(C function), 29	PyEval_GetFuncName (C function), 53
PyErr_NoMemory (C function), 24	PyEval_GetGlobals (C function), 53
PyErr_NormalizeException (C function), 28	PyEval_GetLocals ( <i>C function</i> ), 53
PyErr_Occurred (C function), 27	PyEval_InitThreads ( <i>C function</i> ), 146
PyErr_Occurred(),9	PyEval_InitThreads(),140
PyErr_Print ( <i>C function</i> ), 23	PyEval_MergeCompilerFlags ( <i>C function</i> ), 18
PyErr_PrintEx (C function), 23	PyEval_ReleaseLock (C function), 149
PyErr_ResourceWarning ( <i>C function</i> ), 27	PyEval_ReleaseThread (C function), 149
PyErr_Restore (C function), 28	PyEval_ReleaseThread(), 146
PyErr_SetExcFromWindowsErr (C function), 25	PyEval_RestoreThread (C function), 146
PyErr_SetExcFromWindowsErrWithFilename	PyEval_RestoreThread(), 144, 146
(C function), 25	PyEval_SaveThread ( <i>C function</i> ), 146
PyErr_SetExcFromWindowsErrWithFilenameO	
(C function), 25	PyEval_SetProfile ( <i>C function</i> ), 152
PyErr_SetExcFromWindowsErrWithFilenameO	=
(C function), 25	PyEval_ThreadsInitialized ( <i>C function</i> ), 146
PyErr_SetExcInfo ( <i>C function</i> ), 28	PyExc_ArithmeticError, 32
PyErr_SetFromErrno (C function), 24	PyExc_AssertionError, 32
<del>-</del>	PyExc_AttributeError, 32
tion), 25	PyExc_BaseException, 32
,, ==	PyExc_BlockingIOError, 32
	1 1 DIOCKING TODITOI, 32

PyExc_BrokenPipeError, 32	PyExc_UnicodeError,32
PyExc_BufferError, 32	PyExc_UnicodeTranslateError,32
PyExc_BytesWarning, 34	PyExc_UnicodeWarning, 34
PyExc_ChildProcessError, 32	PyExc_UserWarning,34
PyExc_ConnectionAbortedError, 32	PyExc_ValueError,32
PyExc_ConnectionError, 32	PyExc_Warning,34
PyExc_ConnectionRefusedError, 32	PyExc_WindowsError, 33
PyExc_ConnectionResetError, 32	PyExc_ZeroDivisionError, 32
PyExc_DeprecationWarning, 34	PyException_GetCause (C function), 30
PyExc_EnvironmentError, 33	PyException_GetContext(C function), 30
PyExc_EOFError, 32	PyException_GetTraceback(C function), 30
PyExc_Exception, 32	PyException_SetCause (C function), 30
PyExc_FileExistsError, 32	PyException_SetContext (C function), 30
PyExc_FileNotFoundError, 32	PyException_SetTraceback (C function), 30
PyExc_FloatingPointError, 32	PyFile_FromFd (C function), 119
PyExc_FutureWarning, 34	PyFile_GetLine ( <i>C function</i> ), 119
PyExc_GeneratorExit, 32	PyFile_SetOpenCodeHook ( <i>C function</i> ), 119
PyExc_ImportError, 32	PyFile_WriteObject ( <i>C function</i> ), 120
PyExc_ImportWarning, 34	PyFile_WriteString ( <i>C function</i> ), 120
PyExc_IndentationError, 32	PyFloat_AS_DOUBLE ( <i>C function</i> ), 84
PyExc_IndexError, 32	PyFloat_As_booble ( <i>C function</i> ), 84
PyExc_InterruptedError, 32	PyFloat_AsDouble (C function), 83
PyExc_IOError, 33	- · · · · · · · · · · · · · · · · · · ·
<del>-</del> -	<pre>PyFloat_CheckExact (C function), 83 PyFloat_ClearFreeList (C function), 84</pre>
PyExc_IsADirectoryError, 32	
PyExc_KeyboardInterrupt, 32	PyFloat_FromDouble (C function), 84
PyExc_KeyError, 32	PyFloat_FromString (C function), 84
PyExc_LookupError, 32	PyFloat_GetInfo( <i>C function</i> ), 84
PyExc_MemoryError, 32	PyFloat_GetMax (C function), 84
PyExc_ModuleNotFoundError, 32	PyFloat_GetMin (C function), 84
PyExc_NameError, 32	PyFloat_Type (C variable), 83
PyExc_NotADirectoryError, 32	PyFloatObject (C type), 83
PyExc_NotImplementedError, 32	PyFrame_GetLineNumber (C function), 53
PyExc_OSError, 32	PyFrameObject ( <i>Ctype</i> ), 18
PyExc_OverflowError, 32	PyFrozenSet_Check (C function), 114
PyExc_PendingDeprecationWarning, 34	PyFrozenSet_CheckExact (C function), 114
PyExc_PermissionError, 32	PyFrozenSet_New (C function), 114
PyExc_ProcessLookupError, 32	PyFrozenSet_Type ( <i>C variable</i> ), 114
PyExc_RecursionError, 32	PyFunction_Check ( $C$ function), 116
PyExc_ReferenceError, 32	PyFunction_GetAnnotations ( <i>C function</i> ), 116
PyExc_ResourceWarning, 34	PyFunction_GetClosure ( $C$ function), 116
PyExc_RuntimeError, 32	PyFunction_GetCode ( $C$ function), 116
PyExc_RuntimeWarning, 34	PyFunction_GetDefaults ( $C$ function), 116
PyExc_StopAsyncIteration, 32	PyFunction_GetGlobals ( $C$ function), 116
PyExc_StopIteration, 32	PyFunction_GetModule ( $C$ function), 116
PyExc_SyntaxError, 32	PyFunction_New (C function), 116
PyExc_SyntaxWarning, 34	PyFunction_NewWithQualName (C function), 116
PyExc_SystemError, 32	PyFunction_SetAnnotations (C function), 116
PyExc_SystemExit, 32	PyFunction_SetClosure (C function), 116
PyExc_TabError, 32	PyFunction_SetDefaults (C function), 116
PyExc_TimeoutError, 32	PyFunction_Type (C variable), 115
PyExc_TypeError, 32	PyFunctionObject (C type), 115
PyExc_UnboundLocalError, 32	PyGen_Check (C function), 131
PyExc_UnicodeDecodeError, 32	PyGen_CheckExact (C function), 131
PyExc_UnicodeEncodeError, 32	PyGen_New (C function), 131
= '	- · · · ·

PyGen_NewWithQualName (C function), 131	PyInterpreterState_ThreadHead ( $C$ function),
PyGen_Type (C variable), 131	152
PyGenObject (C type), 131	PyIter_Check (C function), 68
PyGetSetDef(Ctype), 183	PyIter_Next (C function), 68
PyGILState_Check ( <i>C function</i> ), 147	PyList_Append (C function), 111
PyGILState_Ensure ( <i>C function</i> ), 146	PyList_AsTuple (C function), 111
<pre>PyGILState_GetThisThreadState (C function),</pre>	PyList_Check (C function), 110
147	PyList_CheckExact (C function), 110
PyGILState_Release ( <i>C function</i> ), 147	PyList_ClearFreeList (C function), 111
PyImport_AddModule (C function), 40	PyList_GET_ITEM (C function), 110
PyImport_AddModuleObject (C function), 40	PyList_GET_SIZE (C function), 110
PyImport_AppendInittab (C function), 42	PyList_GetItem (C function), 110
PyImport_Cleanup (C function), 42	PyList_GetItem(),7
PyImport_ExecCodeModule (C function), 40	PyList_GetSlice ( <i>C function</i> ), 111
PyImport_ExecCodeModuleEx (C function), 41	PyList_Insert (C function), 111
PyImport_ExecCodeModuleObject (C function),	PyList_New (C function), 110
41	PyList_Reverse ( <i>C function</i> ), 111
PyImport_ExecCodeModuleWithPathnames (C	PyList_SET_ITEM (C function), 110
function), 41	PyList_SetItem (C function), 110
PyImport_ExtendInittab ( <i>C function</i> ), 43	PyList_SetItem(),6
PyImport_FrozenModules ( <i>C variable</i> ), 42	PyList_SetSlice ( <i>C function</i> ), 111
PyImport_GetImporter(C function), 41	PyList_Size (C function), 110
PyImport_GetMagicNumber ( <i>C function</i> ), 41	PyList_Sort (C function), 111
PyImport_GetMagicTag(C function), 41	PyList_Type (C variable), 110
PyImport_GetModule ( <i>C function</i> ), 41	PyListObject (Ctype), 110
PyImport_GetModuleDict ( <i>C function</i> ), 41	PyLong_AsDouble ( <i>C function</i> ), 83
PyImport_Import (C function), 40	PyLong_AsLong ( <i>C function</i> ), 81
PyImport_ImportFrozenModule ( <i>C function</i> ), 42	PyLong_AsLongAndOverflow ( <i>C function</i> ), 81
PyImport_ImportFrozenModuleObject (C	PyLong_AsLongLong ( <i>C function</i> ), 81
function), 42	PyLong_AsLongLongAndOverflow (C function),
PyImport_ImportModule (C function), 39	82
PyImport_ImportModuleEx (C function), 39	PyLong_AsSize_t (C function), 82
PyImport_ImportModuleLevel (C function), 40	PyLong_AsSsize_t ( <i>C function</i> ), 82
PyImport_ImportModuleLevelObject (C func-	PyLong_AsUnsignedLong ( <i>C function</i> ), 82
tion), 40	PyLong_AsUnsignedLongLong ( <i>C function</i> ), 82
PyImport_ImportModuleNoBlock (C function),	PyLong_AsUnsignedLongLongMask ( <i>C function</i> ),
39	82
$PyImport_ReloadModule$ ( $C$ function), 40	PyLong_AsUnsignedLongMask ( $C$ function), $82$
PyIndex_Check (C function), 65	PyLong_AsVoidPtr( <i>C function</i> ), 83
PyInstanceMethod_Check (C function), 117	PyLong_Check (C function), 80
PyInstanceMethod_Function ( $C$ function), 117	PyLong_CheckExact ( $C$ function), $80$
${\tt PyInstanceMethod\_GET\_FUNCTION}~(\textit{C function}),$	PyLong_FromDouble ( $C$ function), $80$
117	PyLong_FromLong (C function), 80
PyInstanceMethod_New(C function), 117	PyLong_FromLongLong ( $C$ function), $80$
PyInstanceMethod_Type (C variable), 117	PyLong_FromSize_t (C function), 80
PyInterpreterState (C type), 145	PyLong_FromSsize_t (C function), 80
PyInterpreterState_Clear (C function), 148	PyLong_FromString (C function), 81
PyInterpreterState_Delete (C function), 148	PyLong_FromUnicode ( $C$ function), 81
PyInterpreterState_GetDict(C function), 148	PyLong_FromUnicodeObject (C function), 81
PyInterpreterState_GetID (C function), 148	PyLong_FromUnsignedLong (C function), 80
PyInterpreterState_Head ( <i>C function</i> ), 152	PyLong_FromUnsignedLongLong(C function), 80
PyInterpreterState_Main (C function), 152	PyLong_FromVoidPtr(C function), 81
PyInterpreterState_New (C function), 147	PyLong_Type ( <i>C variable</i> ), 80
PyInterpreterState_Next ( <i>C function</i> ), 152	PyLongObject (C type), 80

PyMapping_Check (C function), 67	PyMemoryView_GET_BASE (C function), 129
PyMapping_DelItem( <i>C function</i> ),67	PyMemoryView_GET_BUFFER (C function), 128
PyMapping_DelItemString( <i>C function</i> ),68	PyMemoryView_GetContiguous (C function), 128
PyMapping_GetItemString( <i>C function</i> ),67	PyMethod_Check (C function), 117
PyMapping_HasKey ( <i>C function</i> ), 68	PyMethod_ClearFreeList ( $C$ function), 117
PyMapping_HasKeyString( $C\mathit{function}$ ), $68$	PyMethod_Function ( $C$ function), 117
PyMapping_Items ( $C$ function), $68$	PyMethod_GET_FUNCTION (C function), 117
PyMapping_Keys ( $C$ function), $68$	PyMethod_GET_SELF (C function), 117
PyMapping_Length ( $C$ function), 67	PyMethod_New (C function), 117
PyMapping_SetItemString( $C\ function$ ), $67$	PyMethod_Self ( <i>C function</i> ), 117
PyMapping_Size ( $C$ function), 67	PyMethod_Type ( <i>C variable</i> ), 117
PyMapping_Values ( <i>C function</i> ), 68	PyMethodDef( <i>Ctype</i> ), 181
PyMappingMethods ( $C$ type), $210$	PyModule_AddFunctions (C function), 124
PyMappingMethods.mp_ass_subscript $(C$	PyModule_AddIntConstant ( $C$ function), 125
member), 211	PyModule_AddIntMacro( <i>C function</i> ), 125
PyMappingMethods.mp_length( <i>C member</i> ), 210	PyModule_AddObject (C function), 125
PyMappingMethods.mp_subscript ( $C\ member$ ),	PyModule_AddStringConstant ( $C$ function), 125
211	PyModule_AddStringMacro (C function), 125
PyMarshal_ReadLastObjectFromFile (C func-	PyModule_Check ( <i>C function</i> ), 120
tion), 43	PyModule_CheckExact (C function), 120
PyMarshal_ReadLongFromFile(Cfunction), 43	PyModule_Create ( <i>C function</i> ), 122
PyMarshal_ReadObjectFromFile ( $C$ function),	PyModule_Create2 ( <i>C function</i> ), 122
43	PyModule_ExecDef (C function), 124
PyMarshal_ReadObjectFromString ( $C$ func-	PyModule_FromDefAndSpec (C function), 124
tion), 44	PyModule_FromDefAndSpec2 (C function), 124
PyMarshal_ReadShortFromFile ( <i>C function</i> ), 43	PyModule_GetDef ( <i>C function</i> ), 121
PyMarshal_WriteLongToFile ( <i>C function</i> ), 43	PyModule_GetDict (C function), 120
PyMarshal_WriteObjectToFile ( <i>C function</i> ), 43	PyModule_GetFilename ( <i>C function</i> ), 121
PyMarshal_WriteObjectToString ( $C$ function),	PyModule_GetFilenameObject ( <i>C function</i> ), 121
43	PyModule_GetName ( <i>C function</i> ), 121
PyMem_Calloc ( <i>C function</i> ), 173	PyModule_GetNameObject (Cfunction), 120
PyMem_Del (C function), 173	PyModule_GetState ( <i>C function</i> ), 121
PYMEM_DOMAIN_MEM (C variable), 176	PyModule_New (C function), 120
PYMEM_DOMAIN_OBJ (C variable), 176	PyModule_NewObject ( <i>C function</i> ), 120
PYMEM_DOMAIN_RAW ( <i>C variable</i> ), 175 PyMem_Free ( <i>C function</i> ), 173	PyModule_SetDocString ( <i>C function</i> ), 124
PyMem_GetAllocator ( <i>C function</i> ), 176	PyModule_Type ( <i>C variable</i> ), 120 PyModuleDef ( <i>C type</i> ), 121
PyMem_Malloc ( <i>C function</i> ), 173	PyModuleDef_Init ( <i>C function</i> ), 123
PyMem_New (C function), 173	PyModuleDef_Slot ( <i>Ctype</i> ), 123
PyMem_RawCalloc (C function), 173 PyMem_RawCalloc (C function), 172	PyModuleDef_Slot.slot ( <i>C nype</i> ), 123 PyModuleDef_Slot.slot ( <i>C member</i> ), 123
PyMem_RawFree ( <i>C function</i> ), 172	PyModuleDef_Slot.value( <i>C member</i> ), 123
PyMem_RawMalloc (C function), 172	PyModuleDef.m_base ( <i>C member</i> ), 121
PyMem_RawRealloc ( <i>C function</i> ), 172	PyModuleDef.m_clear ( <i>C member</i> ), 122
PyMem_Realloc (C function), 173	PyModuleDef.m_doc(C member), 121
PyMem_Resize (C function), 173	PyModuleDef.m_free (C member), 122
PyMem_SetAllocator ( <i>C function</i> ), 176	PyModuleDef.m_methods ( <i>C member</i> ), 122
PyMem_SetupDebugHooks ( <i>C function</i> ), 176	PyModuleDef.m_name ( <i>C member</i> ), 121
PyMemAllocatorDomain ( <i>C type</i> ), 175	PyModuleDef.m_reload( <i>C member</i> ), 122
PyMemAllocatorEx (C type), 175	PyModuleDef.m_size ( <i>C member</i> ), 121
PyMemberDef ( $C$ type), 182	PyModuleDef.m_slots( <i>C member</i> ), 121
PyMemoryView_Check ( <i>C function</i> ), 128	PyModuleDef.m_traverse( <i>C member</i> ), 122
PyMemoryView_FromBuffer ( <i>C function</i> ), 128	PyNumber_Absolute ( <i>C function</i> ), 63
PyMemoryView_FromMemory ( <i>C function</i> ), 128	PyNumber_Add (C function), 63
PyMemoryView_FromObject ( <i>C function</i> ), 128	PyNumber_And (C function), 64
- 1110mor 1 v 10 m _ 1 10 m 0 0 1 0 0 0 (0 1 m 0 m), 120	- 1 and o = (

PyNumber_AsSsize_t ( $C$ function), $65$	PyNumberMethods.nb_inplace_matrix_multiply
PyNumber_Check ( $C$ function), $62$	(C member), 210
PyNumber_Divmod ( $C$ function), 63	PyNumberMethods.nb_inplace_multiply ( $C$
PyNumber_Float ( $C$ function), $65$	member), 210
PyNumber_FloorDivide ( $C$ function), 63	PyNumberMethods.nb_inplace_or ( <i>C member</i> ),
PyNumber_Index ( $C$ function), $65$	210
PyNumber_InPlaceAdd ( $C$ function), 64	PyNumberMethods.nb_inplace_power (C mem-
PyNumber_InPlaceAnd ( $C$ function), $65$	ber), 210
PyNumber_InPlaceFloorDivide (C function), 64	PyNumberMethods.nb_inplace_remainder ( $C$
PyNumber_InPlaceLshift (C function), 64	member), 210
PyNumber_InPlaceMatrixMultiply (C func-	PyNumberMethods.nb_inplace_rshift $(C$
tion), 64	member), 210
PyNumber_InPlaceMultiply(C function), 64	PyNumberMethods.nb_inplace_subtract ( $C$
PyNumber_InPlaceOr(C function), 65	member), 210
PyNumber_InPlacePower (C function), 64	PyNumberMethods.nb_inplace_true_divide
PyNumber_InPlaceRemainder ( <i>C function</i> ), 64	(C member), 210
PyNumber_InPlaceRshift (C function), 64	PyNumberMethods.nb_inplace_xor(Cmember),
PyNumber_InPlaceSubtract (C function), 64	210
PyNumber_InPlaceTrueDivide ( <i>C function</i> ), 64	PyNumberMethods.nb_int(C member), 210
PyNumber_InPlaceXor(Cfunction), 65	PyNumberMethods.nb_invert ( <i>C member</i> ), 210
PyNumber_Invert (C function), 63	PyNumberMethods.nb_lshift(C member), 210
PyNumber_Long ( <i>C function</i> ), 65	PyNumberMethods.nb_matrix_multiply (C
PyNumber_Lshift ( <i>C function</i> ), 63	member), 210
PyNumber_MatrixMultiply(Cfunction), 63	PyNumberMethods.nb_multiply( <i>C member</i> ), 209
PyNumber_Multiply ( <i>C function</i> ), 63	PyNumberMethods.nb_negative( <i>C member</i> ), 209
PyNumber_Negative (C function), 63	PyNumberMethods.nb_or(C member), 210
PyNumber_Or ( <i>C function</i> ), 64	PyNumberMethods.nb_positive( <i>C member</i> ), 210
PyNumber_Positive ( <i>C function</i> ), 63	PyNumberMethods.nb_power( <i>C member</i> ), 209
PyNumber_Power (C function), 63	PyNumberMethods.nb_remainder ( <i>C member</i> ),
PyNumber_Remainder ( <i>C function</i> ), 63	209
PyNumber_Rshift ( <i>C function</i> ), 64	PyNumberMethods.nb_reserved( <i>C member</i> ), 210
PyNumber_Subtract ( <i>C function</i> ), 63	PyNumberMethods.nb_rshift ( <i>C member</i> ), 210
PyNumber_ToBase ( <i>C function</i> ), 65	PyNumberMethods.nb_subtract(Cmember), 209
PyNumber_TrueDivide (C function), 63	PyNumberMethods.nb_true_divide( <i>Cmember</i> ), 210
PyNumber_Xor (C function), 64	
PyNumberMethods ( <i>Ctype</i> ), 208	PyNumberMethods.nb_xor(C member), 210
PyNumberMethods.nb_absolute( <i>Cmember</i> ), 210	PyObject ( <i>C type</i> ), 180 PyObject_AsCharBuffer ( <i>C function</i> ), 75
PyNumberMethods.nb_add(Cmember), 209	
PyNumberMethods.nb_and( <i>C member</i> ), 210 PyNumberMethods.nb_bool( <i>C member</i> ), 210	PyObject_ASCII ( <i>C function</i> ), 59 PyObject_AsFileDescriptor ( <i>C function</i> ), 119
PyNumberMethods.nb_divmod( <i>C member</i> ), 210	PyObject_AsReadBuffer ( <i>C function</i> ), 76
PyNumberMethods.nb_float (C member), 209	PyObject_AskeadBuffer (C function), 76  PyObject_AsWriteBuffer (C function), 76
PyNumberMethods.nb_floor_divide (C mem-	PyObject_Bytes ( <i>C function</i> ), 79
ber), 210	PyObject_Call ( <i>C function</i> ), 59
PyNumberMethods.nb_index(C member), 210	PyObject_CallFunction ( <i>C function</i> ), 60
PyNumberMethods.nb_inplace_add( <i>Cmember</i> ),	PyObject_CallFunctionObjArgs ( <i>C function</i> ),
210	60
PyNumberMethods.nb_inplace_and( $Cmember$ ),	PyObject_CallMethod ( $C$ function), $60$
210	PyObject_CallMethodObjArgs ( $C$ function), $60$
PyNumberMethods.nb_inplace_floor_divide	
( <i>C member</i> ), 210	PyObject_Calloc ( $C$ function), 174
	PyObject_CheckBuffer(C function),74
member), 210	PyObject_CheckReadBuffer (C function), 76
	PyObject Del (C function) 179

PyObject_DelAttr(C function), 58	PyObjectArenaAllocator ( $Ctype$ ), 177
PyObject_DelAttrString(C function), 58	PyObject.ob_refcnt(C member), 190
PyObject_DelItem(C function), 62	PyObject.ob_type(C member), 190
PyObject_Dir(C function), 62	PyOS_AfterFork (C function), 35
PyObject_Free (C function), 174	PyOS_AfterFork_Child (C function), 35
PyObject_GC_Del(C function), 218	PyOS_AfterFork_Parent (C function), 35
PyObject_GC_New (C function), 218	PyOS_BeforeFork (C function), 35
PyObject_GC_NewVar (C function), 218	PyOS_CheckStack (C function), 36
PyObject_GC_Resize (C function), 218	PyOS_double_to_string(C function), 52
PyObject_GC_Track (C function), 218	PyOS_FSPath ( <i>C function</i> ), 35
PyObject_GC_UnTrack (C function), 218	PyOS_getsig (C function), 36
PyObject_GenericGetAttr (C function), 57	PyOS_InputHook ( <i>C variable</i> ), 16
PyObject_GenericGetDict (C function), 58	PyOS_ReadlineFunctionPointer ( <i>C variable</i> ),
PyObject_GenericSetAttr(C function), 58	16
PyObject_GenericSetDict (C function), 58	PyOS_setsig (C function), 36
PyObject_GetArenaAllocator( <i>C function</i> ), 177	PyOS_snprintf ( <i>C function</i> ), 51
PyObject_GetAttr ( <i>C function</i> ), 57	PyOS_stricmp ( <i>C function</i> ), 53
PyObject_GetAttrString ( <i>C function</i> ), 57	PyOS_string_to_double (C function), 52
PyObject_GetBuffer ( <i>C function</i> ), 74	PyOS_strnicmp ( <i>C function</i> ), 53
PyObject_GetItem ( <i>C function</i> ), 62	PyOS_vsnprintf ( <i>C function</i> ), 51
PyObject_GetIter ( <i>C function</i> ), 62	PyParser_SimpleParseFile ( <i>C function</i> ), 17
PyObject_HasAttr ( <i>C function</i> ), 57	PyParser_SimpleParseFileFlags ( <i>C function</i> ),
PyObject_HasAttrString ( <i>C function</i> ), 57	17
PyObject_Hash ( <i>C function</i> ), 61	PyParser_SimpleParseString ( <i>C function</i> ), 17
PyObject_HashNotImplemented ( <i>C function</i> ), 61	PyParser_SimpleParseStringFlags (C func-
PyObject_HEAD ( <i>C macro</i> ), 180	tion), 17
PyObject_HEAD_INIT (C macro), 180	PyParser_SimpleParseStringFlagsFilename
PyObject_Init (C function), 179	( <i>C function</i> ), 17
PyObject_Init(C function), 179 PyObject_InitVar(C function), 179	PyPreConfig (C type), 158
PyObject_IsInstance (C function), 59	PyPreConfig_InitIsolatedConfig (C func-
PyObject_IsSubclass ( <i>C function</i> ), 59	tion), 158
PyObject_IsTrue ( <i>C function</i> ), 61	PyPreConfig_InitPythonConfig (C function),
	158
PyObject_Length (C function), 62	
PyObject_LengthHint ( <i>C function</i> ), 62 PyObject_Malloc ( <i>C function</i> ), 174	PyPreConfig.allocator( <i>C member</i> ), 158 PyPreConfig.coerce_c_locale( <i>C member</i> ), 158
PyObject_New (C function), 179	
	PyPreConfig.coerce_c_locale_warn ( <i>C mem-</i>
PyObject_NewVar ( <i>C function</i> ), 179	ber), 158
PyObject_Not (C function), 62	PyPreConfig.configure_locale ( <i>C member</i> ),
PyObjectob_next (C member), 190	158
PyObjectob_prev(C member), 190	PyPreConfig.dev_mode( <i>C member</i> ), 158
PyObject_Print ( <i>C function</i> ), 57	PyPreConfig.isolated ( <i>C member</i> ), 158
PyObject_Realloc ( <i>C function</i> ), 174	PyPreConfig.legacy_windows_fs_encoding
PyObject_Repr (C function), 59	(C member), 158
PyObject_RichCompare ( <i>C function</i> ), 58	PyPreConfig.parse_argv (C member), 159
PyObject_RichCompareBool (Cfunction), 58	PyPreConfig.use_environment( <i>Cmember</i> ), 159
PyObject_SetArenaAllocator (C function), 177	PyPreConfig.utf8_mode( <i>C member</i> ), 159
PyObject_SetAttr (C function), 58	PyProperty_Type (C variable), 126
PyObject_SetAttrString (C function), 58	PyRun_AnyFile (C function), 15
PyObject_SetItem (C function), 62	PyRun_AnyFileEx (C function), 15
PyObject_Size (C function), 62	PyRun_AnyFileExFlags (C function), 15
PyObject_Str (C function), 59	PyRun_AnyFileFlags (C function), 15
PyObject_Type (C function), 62	PyRun_File (C function), 17
PyObject_TypeCheck ( <i>C function</i> ), 62	PyRun_FileEx (C function), 17
PyObject_VAR_HEAD ( <i>C macro</i> ), 180	PyRun_FileExFlags ( $C$ function), 17

PyRun_FileFlags ( <i>C function</i> ), 17	PySet_Clear ( <i>C function</i> ), 115
PyRun_InteractiveLoop (C function), 16	PySet_ClearFreeList(C function), 115
PyRun_InteractiveLoopFlags (C function), 16	PySet_Contains ( <i>C function</i> ), 115
PyRun_InteractiveOne (C function), 16	PySet_Discard (C function), 115
PyRun_InteractiveOneFlags (C function), 16	PySet_GET_SIZE (C function), 115
PyRun_SimpleFile (C function), 16	PySet_New (C function), 114
PyRun_SimpleFileEx (C function), 16	PySet_Pop (C function), 115
PyRun_SimpleFileExFlags (C function), 16	PySet_Size (C function), 115
PyRun_SimpleString (C function), 15	PySet_Type ( <i>C variable</i> ), 114
PyRun_SimpleStringFlags (C function), 16	PySetObject (Ctype), 114
PyRun_String ( <i>C function</i> ), 17	PySignal_SetWakeupFd ( $C$ function), 29
PyRun_StringFlags ( <i>C function</i> ), 17	PySlice_AdjustIndices ( $C$ function), 128
PySeqIter_Check (C function), 126	PySlice_Check (C function), 127
PySeqIter_New (C function), 126	PySlice_GetIndices ( $C$ function), 127
PySeqIter_Type ( <i>C variable</i> ), 126	PySlice_GetIndicesEx ( $C$ function), 127
PySequence_Check (C function), 65	PySlice_New ( $C$ function), 127
PySequence_Concat (C function), 65	PySlice_Type ( <i>C variable</i> ), 127
PySequence_Contains (C function), 66	PySlice_Unpack ( <i>C function</i> ), 128
PySequence_Count (C function), 66	PyState_AddModule ( $C$ function), 125
PySequence_DelItem (C function), 66	PyState_FindModule ( $C$ function), 125
PySequence_DelSlice (C function), 66	PyState_RemoveModule ( $C$ function), 126
PySequence_Fast (C function), 67	PyStatus ( <i>Ctype</i> ), 156
PySequence_Fast_GET_ITEM ( $C$ function), 67	PyStatus_Error ( <i>C function</i> ), 157
PySequence_Fast_GET_SIZE (C function), 67	PyStatus_Exception ( $C$ function), 157
PySequence_Fast_ITEMS (C function), 67	PyStatus_Exit ( <i>C function</i> ), 157
PySequence_GetItem (C function), 66	PyStatus_IsError( <i>C function</i> ), 157
PySequence_GetItem(),7	PyStatus_IsExit ( $C$ function), 157
PySequence_GetSlice (C function), 66	PyStatus_NoMemory ( $C$ function), 157
PySequence_Index (C function), 66	PyStatus_Ok ( <i>C function</i> ), 157
PySequence_InPlaceConcat (C function), 66	PyStatus.err_msg( <i>C member</i> ), 157
PySequence_InPlaceRepeat (C function), 66	PyStatus.exitcode ( $C$ member), 156
PySequence_ITEM (C function), 67	PyStatus.func( <i>C member</i> ), 157
PySequence_Length (C function), 65	PyStructSequence_Desc( $Ctype$ ), $109$
PySequence_List (C function), 66	PyStructSequence_Field( $Ctype$ ), $109$
PySequence_Repeat (C function), 66	PyStructSequence_GET_ITEM(C function), 109
PySequence_SetItem (C function), 66	PyStructSequence_GetItem ( $C$ function), 109
PySequence_SetSlice(C function), 66	PyStructSequence_InitType (C function), 109
PySequence_Size (C function), 65	PyStructSequence_InitType2 (C function), 109
PySequence_Tuple (C function), 66	PyStructSequence_New ( $C$ function), $109$
PySequenceMethods (C type), 211	PyStructSequence_NewType ( $C$ function), 109
PySequenceMethods.sq_ass_item ( $C$ member),	PyStructSequence_SET_ITEM(C function), 110
211	PyStructSequence_SetItem ( $C$ function), $109$
PySequenceMethods.sq_concat(Cmember),211	PyStructSequence_UnnamedField ( $C\ variable$ )
PySequenceMethods.sq_contains (C member),	109
211	PySys_AddAuditHook ( $C$ function), 38
${\tt PySequenceMethods.sq\_inplace\_concat}  (C$	PySys_AddWarnOption( <i>C function</i> ), 37
member), 211	PySys_AddWarnOptionUnicode ( $C$ function), 37
${\tt PySequenceMethods.sq\_inplace\_repeat}  (C$	PySys_AddXOption ( $C$ function), 38
member), 211	PySys_Audit ( <i>C function</i> ), 38
PySequenceMethods.sq_item( <i>C member</i> ), 211	PySys_FormatStderr ( $C$ function), 38
PySequenceMethods.sq_length(Cmember),211	PySys_FormatStdout ( $C$ function), 38
PySequenceMethods.sq_repeat(C member),211	PySys_GetObject ( $C$ function), 37
PySet_Add (C function), 115	PySys_GetXOptions ( $C$ function), 38
PySet_Check (C function), 114	PySys_ResetWarnOptions ( <i>C function</i> ), 37

PySys_SetArgv ( <i>C function</i> ), 143	Pythonic, 232
PySys_SetArgv(),140	PYTHONINSPECT, 139
PySys_SetArgvEx ( <i>C function</i> ), 143	PYTHONIOENCODING, 141
PySys_SetArgvEx(), 10, 140	PYTHONLEGACYWINDOWSFSENCODING, 139
PySys_SetObject (C function), 37	PYTHONLEGACYWINDOWSSTDIO, 139
PySys_SetPath (C function), 37	PYTHONMALLOC, 172, 175, 177
PySys_WriteStderr( <i>C function</i> ), 38	PYTHONMALLOCSTATS, 172
PySys_WriteStdout (C function), 38	PYTHONNOUSERSITE, 139
Python 3000, 232	PYTHONOPTIMIZE, 139
Python Enhancement Proposals	PYTHONPATH, 11, 138, 162
PEP 1,232	PYTHONUNBUFFERED, 139
PEP 7,3	PYTHONUTF8, 166
PEP 238, 19, 227	PYTHONVERBOSE, 140
PEP 278, 234	PyThread_create_key ( <i>C function</i> ), 154
PEP 302, 227, 230	PyThread_delete_key ( <i>C function</i> ), 154
PEP 343, 225	PyThread_delete_key_value ( <i>C function</i> ), 154
PEP 362, 224, 231	PyThread_get_key_value ( <i>C function</i> ), 154
PEP 383, 97	PyThread_ReInitTLS ( <i>C function</i> ), 154
PEP 384, 13	PyThread_set_key_value ( <i>C function</i> ), 154
PEP 393, 88, 96	
	PyThread_tss_alloc( <i>C function</i> ), 153
PEP 411, 232	PyThread_tss_create ( <i>C function</i> ), 154
PEP 420, 227, 231, 232	PyThread_tss_delete ( <i>C function</i> ), 154
PEP 432, 168, 169	PyThread_tss_free ( <i>C function</i> ), 153
PEP 442, 207	PyThread_tss_get (C function), 154
PEP 443, 228	PyThread_tss_is_created(Cfunction), 154
PEP 451, 123, 227	PyThread_tss_set (C function), 154
PEP 484, 223, 227, 234, 235	PyThreadState, 144
PEP 489, 124	PyThreadState ( $Ctype$ ), 146
PEP 492, 224, 225	PyThreadState_Clear ( $C$ function), 148
PEP 498, 226	PyThreadState_Delete (C function), 148
PEP 519,232	PyThreadState_Get (C function), 146
PEP 525, 224	PyThreadState_GetDict(C function), 148
PEP 526, 223, 235	PyThreadState_New ( <i>C function</i> ), 148
PEP 528, 139	PyThreadState_Next (C function), 152
PEP 529, 97, 139	PyThreadState_SetAsyncExc(C function), 148
PEP 538, 166	PyThreadState_Swap (C function), 146
PEP 539, 153	PyTime_Check (C function), 134
PEP 540,166	PyTime_CheckExact (C function), 134
PEP 552, 161	PyTime_FromTime (C function), 135
PEP 578,39	PyTime_FromTimeAndFold(C function), 135
PEP 587, 156	PyTimeZone_FromOffset (C function), 135
PEP 3116,234	PyTimeZone_FromOffsetAndName ( $C$ function),
PEP 3119,59	135
PEP 3121, 122	PyTrace_C_CALL ( <i>C variable</i> ), 152
PEP 3147,41	PyTrace_C_EXCEPTION ( <i>C variable</i> ), 152
PEP 3151,33	PyTrace_C_RETURN ( <i>C variable</i> ), 152
PEP 3155, 233	PyTrace_CALL ( <i>C variable</i> ), 151
PYTHON*, 138	PyTrace_EXCEPTION ( <i>C variable</i> ), 151
PYTHONCOERCECLOCALE, 166	PyTrace_LINE ( <i>C variable</i> ), 152
PYTHONDEBUG, 138	PyTrace_OPCODE (C variable), 152
PYTHONDONTWRITEBYTECODE, 138	PyTrace_RETURN ( <i>C variable</i> ), 152
PYTHONDUMPREFS, 190	PyTuple_Check ( <i>C function</i> ), 108
PYTHONHASHSEED, 138	PyTuple_CheckExact (C function), 108
PYTHONHOME, 11, 138, 143, 144, 162	PyTuple_ClearFreeList ( <i>C function</i> ), 108

PyTuple_GET_ITEM (C function), 108	PyTypeObject.tp_clear( $C$ member), 199
PyTuple_GET_SIZE (C function), 108	PyTypeObject.tp_dealloc( $C$ member), 192
PyTuple_GetItem (C function), 108	PyTypeObject.tp_del( $C$ member), 207
PyTuple_GetSlice (C function), 108	PyTypeObject.tp_descr_get(C member), 203
PyTuple_New (C function), 108	PyTypeObject.tp_descr_set( <i>C member</i> ), 203
PyTuple_Pack ( <i>C function</i> ), 108	PyTypeObject.tp_dict( $C$ member), 203
PyTuple_SET_ITEM ( $C$ function), $108$	PyTypeObject.tp_dictoffset( <i>C member</i> ), 204
PyTuple_SetItem (C function), 108	PyTypeObject.tp_doc( <i>C member</i> ), 199
PyTuple_SetItem(),6	PyTypeObject.tp_finalize( $C$ member), 207
PyTuple_Size (C function), 108	PyTypeObject.tp_flags( <i>C member</i> ), 196
PyTuple_Type ( <i>C variable</i> ), 107	PyTypeObject.tp_free( <i>C member</i> ), 205
PyTupleObject ( $Ctype$ ), 107	PyTypeObject.tp_frees( <i>C member</i> ), 208
PyType_Check (C function), 77	PyTypeObject.tp_getattr(C member), 193
PyType_CheckExact ( <i>C function</i> ), 77	PyTypeObject.tp_getattro( <i>C member</i> ), 195
PyType_ClearCache ( <i>C function</i> ), 77	PyTypeObject.tp_getset( <i>C member</i> ), 202
PyType_FromSpec ( $C$ function), 78	PyTypeObject.tp_hash( <i>C member</i> ), 195
${\tt PyType\_FromSpecWithBases}~(\textit{C function}), 78$	PyTypeObject.tp_init( <i>C member</i> ), 204
PyType_GenericAlloc (C function), 78	PyTypeObject.tp_is_gc(C member), 206
PyType_GenericNew (C function), 78	PyTypeObject.tp_itemsize(C member), 192
PyType_GetFlags ( <i>C function</i> ), 77	PyTypeObject.tp_iter( <i>C member</i> ), 201
PyType_GetSlot (C function), 78	PyTypeObject.tp_iternext(C member), 202
PyType_HasFeature (C function), 78	PyTypeObject.tp_maxalloc(C member), 208
PyType_IS_GC (C function), 78	PyTypeObject.tp_members( <i>C member</i> ), 202
PyType_IsSubtype ( <i>C function</i> ), 78	PyTypeObject.tp_methods( <i>C member</i> ), 202
PyType_Modified ( <i>C function</i> ), 77	PyTypeObject.tp_mro( <i>C member</i> ), 206
PyType_Ready ( <i>C function</i> ), 78	PyTypeObject.tp_name(C member), 191
PyType_Slot ( <i>C type</i> ), 79	PyTypeObject.tp_new(C member), 205
PyType_Slot.PyType_Slot.pfunc ( <i>C member</i> ),	PyTypeObject.tp_next(C member), 208
79	PyTypeObject.tp_prev(C member), 208
PyType_Slot.PyType_Slot.slot( <i>Cmember</i> ),79	PyTypeObject.tp_repr(C member), 194
PyType_Spec (C type), 78	PyTypeObject.tp_richcompare(Cmember), 200
member), 79	PyTypeObject.tp_setattro( <i>C member</i> ), 196
<pre>PyType_Spec.PyType_Spec.flags (C member),</pre>	PyTypeObject.tp_str(C member), 195
79	PyTypeObject.tp_subclasses(C member), 206
PyType_Spec.PyType_Spec.itemsize ( <i>C mem-</i>	PyTypeObject.tp_traverse(C member), 199
ber), 79	PyTypeObject.tp_vectorcall_offset (C
PyType_Spec.PyType_Spec.name( <i>Cmember</i> ),78	member), 193
PyType_Spec.PyType_Spec.slots ( <i>C member</i> ),	PyTypeObject.tp_version_tag( <i>C member</i> ), 207
79	PyTypeObject.tp_weaklist(C member), 207
PyType_Type (C variable), 77	<pre>PyTypeObject.tp_weaklistoffset(Cmember), 201</pre>
PyTypeObject (Ctype), 77  PyTypeObject (Ctype), 77	
PyTypeObject.tp_alloc(C member), 205	PyTZInfo_Check (C function), 134
PyTypeObject.tp_allocs(C member), 207	PyTZInfo_CheckExact ( <i>C function</i> ), 134 PyUnicode_1BYTE_DATA ( <i>C function</i> ), 90
PyTypeObject.tp_as_async( <i>Cmember</i> ), 194	
PyTypeObject.tp_as_buffer(C member), 196	PyUnicode_1BYTE_KIND ( <i>C macro</i> ), 90 PyUnicode_2BYTE_DATA ( <i>C function</i> ), 90
PyTypeObject.tp_as_mapping( <i>C member</i> ), 194 PyTypeObject.tp_as_number( <i>C member</i> ), 194	PyUnicode_2BYTE_KIND (C macro), 90 PyUnicode_2BYTE_KIND (C macro), 90
PyTypeObject.tp_as_number(C member), 194 PyTypeObject.tp_as_sequence(C member), 194	PyUnicode_4BYTE_DATA (C function), 90
PyTypeObject.tp_as_sequence(C member), 194 PyTypeObject.tp_base(C member), 202	PyUnicode_4BYTE_KIND (C macro), 90 PyUnicode_4BYTE_KIND (C macro), 90
PyTypeObject.tp_bases ( <i>C member</i> ), 206 PyTypeObject.tp_basicsize ( <i>C member</i> ), 192	PyUnicode_AS_DATA ( <i>C function</i> ), 91 PyUnicode_AS_UNICODE ( <i>C function</i> ), 91
PyTypeObject.tp_basicsize(C member), 192 PyTypeObject.tp_cache(C member), 206	PyUnicode_AsAsCIIstring ( <i>C function</i> ), 104
PyTypeObject.tp_cache(C member), 200 PyTypeObject.tp call(C member), 195	PyUnicode AsCharmapString (C function), 104
T Y T Y NOUND   COU T COU T TO THORIDON IS 172	i y oni i oddo i no ona i mapo ci i na (o i micholi. 10t

PyUnicode_AsEncodedString(C function), 99	PyUnicode_DecodeUTF16Stateful (C function),
PyUnicode_AsLatin1String ( <i>C function</i> ), 104	102
PyUnicode_AsMBCSString (C function), 105	PyUnicode_DecodeUTF32 (C function), 101
PyUnicode_AsRawUnicodeEscapeString (C	PyUnicode_DecodeUTF32Stateful (C function),
function), 103	101
PyUnicode_AsUCS4 (C function), 95	PyUnicode_Encode (C function), 100
PyUnicode_AsUCS4Copy (C function), 95	PyUnicode_EncodeASCII (C function), 104
PyUnicode_AsUnicode ( <i>C function</i> ), 96	PyUnicode_EncodeCharmap (C function), 105
PyUnicode_AsUnicodeAndSize (C function), 96	PyUnicode_EncodeCodePage (C function), 105
PyUnicode_AsUnicodeCopy (C function), 96	PyUnicode_EncodeFSDefault (C function), 98
PyUnicode_AsUnicodeEscapeString (C func-	PyUnicode_EncodeLatin1 (C function), 104
tion), 103	PyUnicode_EncodeLocale (C function), 97
PyUnicode_AsUTF8 (C function), 100	PyUnicode_EncodeMBCS (C function), 105
PyUnicode_AsUTF8AndSize (C function), 100	PyUnicode_EncodeRawUnicodeEscape (C func-
PyUnicode_AsUTF8String (C function), 100	tion), 103
PyUnicode_AsUTF16String(C function), 102	PyUnicode_EncodeUnicodeEscape (C function),
PyUnicode_AsUTF32String (C function), 101	103
PyUnicode_AsWideChar (C function), 99	PyUnicode_EncodeUTF7 (C function), 103
PyUnicode_AsWideCharString ( $C$ function), 99	PyUnicode_EncodeUTF8 (C function), 100
PyUnicode_Check (C function), 89	PyUnicode_EncodeUTF16 (C function), 102
PyUnicode_CheckExact (C function), 89	PyUnicode_EncodeUTF32 (C function), 101
PyUnicode_ClearFreeList (C function), 90	PyUnicode_Fill (C function), 95
PyUnicode_Compare ( <i>C function</i> ), 107	PyUnicode_Find (C function), 106
PyUnicode_CompareWithASCIIString (C func-	PyUnicode_FindChar (C function), 106
tion), 107	PyUnicode_Format (C function), 107
PyUnicode_Concat (C function), 106	PyUnicode_FromEncodedObject (C function), 94
PyUnicode_Contains (C function), 107	PyUnicode_FromFormat (C function), 93
PyUnicode_CopyCharacters (C function), 95	PyUnicode_FromFormatV(C function), 94
PyUnicode_Count (C function), 107	PyUnicode_FromKindAndData(C function), 93
PyUnicode_DATA (C function), 90	PyUnicode_FromObject (C function), 96
PyUnicode_Decode (C function), 99	PyUnicode_FromString (C function), 93
PyUnicode_DecodeASCII (C function), 104	PyUnicode_FromString(),112
PyUnicode_DecodeCharmap ( <i>C function</i> ), 104	PyUnicode_FromStringAndSize (C function), 93
PyUnicode_DecodeFSDefault ( <i>C function</i> ), 98	PyUnicode_FromUnicode (C function), 96
PyUnicode_DecodeFSDefaultAndSize (C func-	PyUnicode_FromWideChar(C function), 99
tion), 98	PyUnicode_FSConverter ( $C$ function), 97
PyUnicode_DecodeLatin1 ( $C$ function), $104$	PyUnicode_FSDecoder ( $C$ function), 98
PyUnicode_DecodeLocale ( $\it Cfunction$ ), 97	PyUnicode_GET_DATA_SIZE (C function), 91
PyUnicode_DecodeLocaleAndSize ( $C\ function$ ),	PyUnicode_GET_LENGTH ( $C$ function), 89
97	PyUnicode_GET_SIZE (C function), 91
PyUnicode_DecodeMBCS (C function), 105	PyUnicode_GetLength ( $C$ function), 95
PyUnicode_DecodeMBCSStateful ( $C$ function),	PyUnicode_GetSize(C function), 96
105	PyUnicode_InternFromString(C function), 107
PyUnicode_DecodeRawUnicodeEscape ( $C\ func$ -	PyUnicode_InternInPlace (C function), 107
tion), 103	PyUnicode_Join ( $C$ function), $106$
PyUnicode_DecodeUnicodeEscape ( $C\ function$ ),	PyUnicode_KIND ( $C$ function), 90
103	PyUnicode_MAX_CHAR_VALUE ( $C$ function), $90$
PyUnicode_DecodeUTF7 (C function), 102	PyUnicode_New ( $C$ function), 92
PyUnicode_DecodeUTF7Stateful ( $C$ function),	PyUnicode_READ ( $C$ function), 90
102	PyUnicode_READ_CHAR ( $C$ function), 90
PyUnicode_DecodeUTF8 ( $\emph{C function}$ ), $100$	PyUnicode_ReadChar (C function), 95
PyUnicode_DecodeUTF8Stateful ( $C$ function),	PyUnicode_READY ( $C$ function), 89
100	PyUnicode_Replace ( $C$ function), 107
PyUnicode_DecodeUTF16 (C function), 101	PyUnicode_RichCompare (C function), 107

PyUnicode_Split ( <i>C function</i> ), 106	<i>tion</i> ), 31
PyUnicode_Splitlines ( $C$ function), $106$	PyUnicodeTranslateError_SetReason (C
PyUnicode_Substring ( $C$ function), $95$	function), 31
PyUnicode_Tailmatch ( $C$ function), $106$	PyUnicodeTranslateError_SetStart ( $C\ func$ -
PyUnicode_TransformDecimalToASCII ( $C$	tion), 31
function), 96	PyVarObject ( <i>Ctype</i> ), 180
PyUnicode_Translate ( $C$ function), $105$ , $106$	PyVarObject_HEAD_INIT( <i>C macro</i> ), 180
PyUnicode_TranslateCharmap ( $C\mathit{function}$ ), $105$	PyVarObject.ob_size( <i>C member</i> ), 191
PyUnicode_Type ( <i>C variable</i> ), 89	PyVectorcall_Call ( $C$ function), 193
PyUnicode_WCHAR_KIND ( <i>C macro</i> ), 90	PyVectorcall_NARGS ( $C$ function), 61
PyUnicode_WRITE ( $C$ function), $90$	PyWeakref_Check ( <i>C function</i> ), 129
PyUnicode_WriteChar ( $C$ function), $95$	PyWeakref_CheckProxy ( $C$ function), 129
PyUnicodeDecodeError_Create ( $C$ function), 30	PyWeakref_CheckRef ( $C$ function), 129
PyUnicodeDecodeError_GetEncoding ( $C\ func$ -	PyWeakref_GET_OBJECT ( <i>C function</i> ), 129
tion), 30	PyWeakref_GetObject ( $C$ function), 129
PyUnicodeDecodeError_GetEnd( $C$ function), 31	PyWeakref_NewProxy ( <i>C function</i> ), 129
PyUnicodeDecodeError_GetObject ( $C\ func$ -	PyWeakref_NewRef ( $C$ function), 129
tion), 30	PyWideStringList ( $Ctype$ ), 156
PyUnicodeDecodeError_GetReason ( $C\ func$ -	PyWideStringList_Append ( $C$ function), 156
tion), 31	PyWideStringList_Insert ( $C$ function), 156
PyUnicodeDecodeError_GetStart ( $C$ function),	PyWideStringList.items (C member), 156
30	PyWideStringList.length(C member), 156
PyUnicodeDecodeError_SetEnd(C function), 31	PyWrapper_New (C function), 127
<pre>PyUnicodeDecodeError_SetReason (C func- tion), 31</pre>	Q
<pre>PyUnicodeDecodeError_SetStart (C function), 31</pre>	qualified name, 233
PyUnicodeEncodeError_Create (C function), 30	R
PyUnicodeEncodeError_GetEncoding (C func-	realloc(),171
tion), 30	reference count, 233
PyUnicodeEncodeError_GetEnd(C function), 31	regular package, 233
PyUnicodeEncodeError_GetObject (C func-	releasebufferproc ( <i>C type</i> ), 214
tion), 30	repr
PyUnicodeEncodeError_GetReason ( $C$ func-	built-in function, 59, 194
<i>tion</i> ), 31	reprfunc ( <i>C type</i> ), 214
PyUnicodeEncodeError_GetStart ( $C\ function$ ),	richempfunc ( <i>Ctype</i> ), 214
30	
PyUnicodeEncodeError_SetEnd( $C$ function), 31	S
PyUnicodeEncodeError_SetReason ( $C\ func$ -	sdterr
<i>tion</i> ), 31	stdin stdout, 141
PyUnicodeEncodeError_SetStart ( $C\ function$ ),	search
31	path, module, 10, 140, 142
PyUnicodeObject ( $ extit{C type}$ ), $ extit{89}$	sequence, 233
PyUnicodeTranslateError_Create ( $C$ function), 30	object, 86
PyUnicodeTranslateError_GetEnd (C func-	set
tion), 31	object, 114
PyUnicodeTranslateError_GetObject (C	set_all(),7
function), 30	setattrfunc ( <i>C type</i> ), 214 setattrofunc ( <i>C type</i> ), 214
PyUnicodeTranslateError_GetReason (C	setattrolunc (C type), 214 setswitchinterval () (in module sys), 144
function), 31	SIGINT, 29
PyUnicodeTranslateError_GetStart (C func-	signal
tion), 30	module, 29
PyUnicodeTranslateError_SetEnd ( $\emph{C}$ func-	single dispatch 233

```
Ζ
SIZE MAX, 82
slice, 233
                                                Zen of Python, 235
special
    method, 233
special method, 233
ssizeargfunc (Ctype), 215
ssizeobjargproc (Ctype), 215
statement, 233
staticmethod
    built-in function, 182
stderr (in module sys), 149
stdin
    stdout sdterr, 141
stdin (in module sys), 149
stdout
    sdterr, stdin, 141
stdout (in module sys), 149
strerror(), 24
string
    PyObject_Str (C function), 59
sum_list(), 8
sum\_sequence(), 8, 9
sys
    module, 10, 140, 149
SystemError (built-in exception), 121
Т
ternaryfunc (C type), 215
text encoding, 233
text file, 234
traverseproc(Ctype), 218
triple-quoted string, 234
tuple
    built-in function, 66, 111
    object, 107
type, 234
    built-in function, 62
    object, 5, 77
type alias, 234
type hint, 234
U
ULONG MAX, 82
unaryfunc (C type), 215
universal newlines, 234
variable annotation, 234
vectorcallfunc (Ctype), 214
version (in module sys), 142, 143
virtual environment, 235
virtual machine, 235
visitproc(Ctype), 218
```