## Alias

The alias remote provides a new name for another remote.

Paths may be as deep as required or a local path, e.g. remote:directory/subdirectory Or /directory/subdirectory.

During the initial setup with rclone config you will specify the target remote. The target remote can either be a local path or another remote.

Subfolders can be used in target remote. Assume an alias remote named backup with the target mydrive:private/backup. Invoking rclone mkdir backup:desktop is exactly the same as invoking rclone mkdir mydrive:private/backup/desktop.

There will be no special handling of paths containing .. segments. Invoking rclone mkdir backup:../desktop is exactly the same as invoking rclone mkdir mydrive:private/backup/../desktop. The empty path is not allowed as a remote. To alias the current directory use . instead.

Here is an example of how to make an alias called remote for local folder. First run:

rclone config

This will guide you through an interactive setup process:

```
No remotes found - make a new one
n) New remote
s) Set configuration password
q) Quit config
n/s/q > n
name> remote
Type of storage to configure.
Choose a number from below, or type in your own value
[snip]
XX / Alias for an existing remote
   \ "alias"
[snip]
Storage> alias
Remote or path to alias.
Can be "myremote:path/to/dir", "myremote:bucket", "myremote:" or "/local/path".
remote> /mnt/storage/backup
Remote config
[remote]
remote = /mnt/storage/backup
______
y) Yes this is OK
e) Edit this remote
d) Delete this remote
y/e/d>y
Current remotes:
Name
                     Type
====
                     ====
                     alias
remote
e) Edit existing remote
n) New remote
d) Delete remote
r) Rename remote
c) Copy remote
s) Set configuration password
q) Quit config
e/n/d/r/c/s/q>q
```

Once configured you can then use rclone like this,

List directories in top level in /mnt/storage/backup

```
rclone 1sd remote:
```

List all the files in /mnt/storage/backup

```
rclone ls remote:
```

Copy another local directory to the alias directory called source

rclone copy /home/source remote:source

## **Standard Options**

Here are the standard options specific to alias (Alias for an existing remote).

## --alias-remote

Remote or path to alias. Can be "myremote:path/to/dir", "myremote:bucket", "myremote:" or "/local/path".

• Config: remote

• Env Var: RCLONE\_ALIAS\_REMOTE

Type: stringDefault: ""