- 1. Download the following files from the browser using the links Maven Repository: com.google.guava » guava » 27.0.1-jre https://apachemirror.wuchna.com/hive/hive-3.1.2/
- 2. Make sure that hadoop has been installed, and all the nodes are running properly
- 3. sudo my /home/luser/Downloads/apache-hive-3.1.2-bin /usr/local/hadoop/hive
- 4. sudo chown -R hadoop:hadoop /usr/local/hadoop/hive
- 5. sudo vim /etc/profile.d/hadoop\_java.sh (Add the following lines) export HIVE HOME=/usr/local/hadoop/hive

export HIVE\_CONF\_DIR=\$HIVE\_HOME/conf

export PATH=\$PATH:\$HIVE HOME/bin

export CLASSPATH=\$CLASSPATH:\$HADOOP HOME/lib/\*

export CLASSPATH=\$CLASSPATH:\$HIVE HOME/lib/\*

- 6. source /etc/profile.d/hadoop java.sh
- 7. cd \$HADOOP\_HOME/sbin && ./start-all.sh
- 8. hdfs dfs -mkdir -p /tmp hdfs dfs -mkdir -p /user/hive/warehouse
- 9. hdfs dfs -chmod g+w /tmp hdfs dfs -chmod g+w /user/hive/warehouse
- cd \$HIVE\_HOME/lib and look for gauva.jar (19)
   mv guava-19.0.jar guava-19.0.jar\_buf
   sudo mv /home/luser/Downloads/quava-27.0.1-jre.jar . (. current directory)
- 11. cd .. && cd conf
- 12. cp hive-env.sh.template hive-env.sh
- 13. vim hive-env.sh

Go to line number 49 , Add the line after this line HADOOP\_HOME=/usr/local/hadoop

 cp hive-default.xml.template hive-site.xml vim hive-site.xml

Go to line number 39, in that change the value as <value>/tmp/hive-\${user.name}

// remove the additional symbol such as &lt, &gt in the description field (IMPORTANT)

- 15. Go to line number 143, change the value field as <value>/tmp/\${user.name}
- 16. Go to line number 147, change the value field as <value>/tmp/\${user.name}\_resources</value>
- 17. Go to line number 153, change the value field as change the value from 700 to 733
- 18. Go to line number 3215 and remove the special character in the description
- 19. schematool -dbType derby -initSchema

(Observe no error)
20. hive ( to start the hive shell )