

Ajoke POS

Step-by-step guide for Android phones and tablets

For shop owners, managers and cashiers

Covers app version 1.0 · October 2026

Developed by **Ajoke Code Sphere**

Help & activation (call or WhatsApp): **+234 803 415 0437**

What's in this guide

1 Before you start

2 Install the app

3 Activate your licence

4 Set up your shop

5 Signing in and finding your way

6 Add your products

7 Add your staff

8 Open the register

9 Make a sale

10 Receipts: print or send by WhatsApp

11 Selling on credit

12 Customers, payments and statements

13 Sales history and voiding a sale

14 New stock, expiry dates and expenses

15 Stock report

16 Setting up a receipt printer

17 Business details and logo

18 Close the register

19 Backup and moving to a new device

20 Problems and answers

How to read this guide

Buttons and boxes you tap in the app look like this: Complete sale. The tabs along the bottom of the screen look like this: Sell.

Most of this guide is about the **"This device only"** setup, where one phone or tablet runs the whole shop. If your phone is linked to an office or online server, see the note in section 4.

A typical day

When	What to do	Section
Morning	Sign in with your PIN, then open the register with the cash in the drawer	5, 8
All day	Sell, print or send receipts, receive customer payments	9 – 12
When goods arrive	Record them under Inflow so quantities stay correct	14
Evening	Count the cash and close the register; check the stock report	18, 15
At least weekly	Make a backup and keep it off the phone	19

1. Before you start

You need:

- **An Android phone or tablet.** A tablet is more comfortable at the counter, but a phone works well too.
- **The Ajoke POS app file** (an *.apk* file) from Ajoke Code Sphere, usually sent by WhatsApp or a download link.
- **An activation code** for this device. You get it after you send your device code (section 3).
- **Optional:** a Bluetooth thermal receipt printer (58 mm or 80 mm paper).

The app works **without internet**. You only need data or Wi-Fi to download the app, send receipts by WhatsApp and save backups online.

> **One licence = one device**
>
> Each licence only works on the phone or tablet it was activated on. If you change device, contact Ajoke Code Sphere for a new activation code. Back up your records first (section 19).

2. Install the app

1. Open the *.apk* file you received (in WhatsApp, tap the file; or open it from **Files** → **Downloads**).
2. Android may say the app is from an unknown source. Tap `Settings`, turn on **Allow from this source**, then go back.
3. Tap `Install`. If Google Play Protect asks, choose `Install anyway`. The app is safe; it is just not from the Play Store.
4. Tap `Open`. The Ajoke POS logo appears for a few seconds while the app starts.

> **Updating later**
>
> When you get a newer version, install it the same way, over the old one. Do **not** uninstall first, because uninstalling deletes the shop's records on the device.

3. Activate your licence

The first time the app opens, it shows the **Activate Ajoke POS** screen with a **device code** such as `K7QF-29XM-C4TB`.

1. Tap `Share device code` and send it to Ajoke Code Sphere on WhatsApp (+234 803 415 0437) (or write it down carefully).
2. You receive a long **activation code** back. Copy *all* of it; it is about 230 characters long.
3. Paste it into the box **Paste the activation code here** and tap `Activate`.
4. The app moves on to setting up your shop.

> **"This code is for device ..., not this device"**
> The code was made for a different device code. Check that you sent the code shown on *this* device, then ask for a new one.

If your licence has an end date, the app warns you before it runs out. If it does expire, the app shows **Renew your licence**. Contact Ajoke Code Sphere to renew; you will get a new code to paste the same way, and your records stay as they are.

4. Set up your shop

Choose how this device will work:

Option	Choose it when
This device only (no server)	Small shop, one phone or tablet. Everything is kept on the device. *Most shops choose this.*
Office server only	The shop has the Ajoke POS server on an office computer. Syncs over the shop Wi-Fi.
Cloud only	The business uses the online server. Syncs whenever there is internet.
Office server + cloud	Uses the office server on shop Wi-Fi and the cloud elsewhere.

"This device only" setup

1. Enter the **Business name** (as you want it on receipts) and choose your **Currency**.
2. Enter **VAT %** (use 0 if you do not charge VAT). Turn on **Add a service charge** only if you charge one.
3. Enter the **Owner's name**, then a **6-digit PIN** and **Repeat PIN**. Remember this PIN: it is the owner's key to everything.
4. Tap `Create business on this device`.

Moving from another device? Tap `Restore from a backup file instead` and choose your backup file (section 19).

> **Linked to a server?**
> For the server options, a manager gets a **Server address** and **Pairing code** from the web app (*Sync monitor → Pair a tablet*). Enter them, tap `Test connection`, then continue. On a linked device, products, staff and reports are managed in the web app, and the bottom bar shows `Sync` instead of `Backup`.

5. Signing in and finding your way

Every time the app opens, or after someone taps `Lock`, it shows the sign-in screen. Tap your name and enter your PIN. Each staff member has their own PIN, so every sale shows who made it.

> **Lock when you step away**
> Tap the padlock `Lock` at the top so nobody can sell or see figures under your name.

Forgot your PIN?

- **Staff:** ask an owner to set a new PIN in `Manage` → **Staff**.
- **Owner:** tap your name, then `Forgot PIN?`. The app shows a **request code**. Tap `Share request code` and send it to Ajoke Code Sphere (+234 803 415 0437). After they confirm you are the owner, they send back a **reset code**. Paste it, tap `Continue` and choose a new PIN. Your records are not affected. The reset code works once, on this phone only.

The bottom bar

Sell	Sales	Register	Reports	Manage	Backup
ring up sales	today's sales, reprint	open / close cash	stock report	products, customers…	backup & printer

`Reports` and `Manage` only appear for staff whose role allows them (section 7).

The status badge

At the top of the screen a small badge shows whether your records are safe:

- **Backed up** (green): a backup was made in the last 7 days.
- **Not backed up** or **Backup 9d old** (orange): make a backup soon. Tap the badge to go straight to Backup.

6. Add your products

Go to `Manage` → **Products** and tap `+ Product` (the round button at the bottom right).

Field	What to enter
Name	As customers know it, e.g. “Golden Penny Semovita 1kg”.
Category	Groups products on the Sell screen, e.g. Drinks, Groceries.
Selling price	Price per unit.
Cost price	What you pay the supplier per unit (optional, used for stock value).
Barcode	Optional. Lets you search or scan instead of scrolling.
Quantity in stock	How many you have now.
Low-stock warning at	The app warns when stock falls to this number.
Service	Turn on for services (e.g. delivery). Services have no stock count.

Tap `Save`. To change a product, tap it in the list.

Correcting stock

Open the product and use the stock section: choose `Received (+)` or `Remove (−)`, enter the **Quantity** and a reason (e.g. “Damaged”, “Counted”), then tap `Save stock change`. Every change is kept in the product's history. For new deliveries, use **Inflow** instead (section 14).

Products you no longer sell can be **archived**: they disappear from the Sell screen but stay in old sales and reports.

7. Add your staff

Go to Manage → **Staff**, tap + Staff, enter the name, phone, role and a 6-digit PIN (and repeat it), then tap Save. Give each person their own PIN and ask them not to share it.

What they can do	Owner	Manager	Cashier
Sell, open/close register, add customers	✓	✓	✓
Receive customer payments	✓	✓	✓
Void a sale	✓	✓	–
Give discounts (change an item's price at the till)	✓	✓	If allowed
Set customers' credit limits	✓	✓	–
Products, stock, inflow, reports	✓	✓	–
Staff and business settings	✓	–	–

When someone leaves, open their record and switch them off (deactivate). Their past sales stay on record but they can no longer sign in.

> **Add a second owner**
> Make a trusted person (a partner or family member) an Owner too, with their own PIN. If one owner forgets their PIN, the other can set a new one straight away.

8. Open the register

You must open the register before you can sell. This records how much cash was in the drawer at the start.

1. Tap Register.
2. Count the cash in the drawer and enter it as the **Opening float** (enter 0 if it is empty).
3. Tap Open register. The app takes you to Sell.

The register stays open until you close it (section 18), even if you lock the app or switch the phone off.

9. Make a sale

1. On **Sell**, tap products to add them. Use **Search name, SKU or scan barcode** to find items quickly, or tap a category.
2. Each tap adds one. On a phone, tap the bar **View sale** at the bottom to see the cart. Change quantities with **+** and **−**, or tap the number and type it (e.g. 50).
3. Discount: tap the price under an item (it shows ✎) and type the price you are selling at, then **Save price**. It starts at the set price; the difference is shown as a discount on the receipt. **Set price** puts it back. Owners and managers can always do this; cashiers only if the owner allows it (section 17).
4. Optional: tap **Add customer** to attach a customer (needed for credit, and it earns them points). You can search by name or phone, or add a new one with name and phone.
5. Tap **Charge**.
6. Choose how the customer pays: **Cash**, **Card**, **Transfer**, **Mobile money** or **On account** (credit).
   - **Cash:** enter the **Cash received**; the app shows the **Change** to give.
   - **Card, Transfer, Mobile money:** enter the **Payment reference** (terminal slip or transfer reference). It is required, so you can match it later.
   - A customer can pay with more than one method, e.g. part cash, part transfer.
7. Tap **Complete sale**. The receipt appears.
8. Tap **New sale** for the next customer.

> **Stock is updated automatically**
>
> Every sale takes the items out of stock. If an item shows **Out of stock**, record a delivery (section 14) or correct the count (section 6).

10. Receipts: print or send by WhatsApp

After each sale, the receipt screen gives you:

- **Print**: prints on your Bluetooth printer (set it up first, section 16).
- **Send (WhatsApp)**: makes a **picture of the receipt** and opens the share menu. Choose WhatsApp and the customer's chat. If the picture cannot be made, use **Send as text**.

Receipts show your logo, address and phone (section 17), the items, payments and, when a customer is attached, the customer's current **account balance**. You can print or send any receipt again later from **Sales**; it is marked **REPRINT**.

11. Selling on credit

Any registered customer can buy on credit ("on account") and pay later, unless the owner has set them to cash only.

1. Add the items and attach the customer with `Add customer`. You can also add the customer at the payment step with `Choose customer`.
2. Tap `Charge` and choose `On account`. The app shows what the customer already owes and their limit.
3. If they pay part now, enter it under **Paid now (optional)**; the rest goes on their account.
4. Tap `Complete credit sale`. The receipt shows the amount on account and the **Account balance** they now owe.

Credit limits

Owners and managers set this under `Manage` → **Customers** → customer → **Details** → **Credit limit**.

Credit limit	Meaning
Blank (empty)	No limit: the customer can owe any amount.
A number, e.g. 50,000	The most they may owe. A sale that would go over it is refused, and nothing is saved.
0	Cash only: no credit for this customer.

> **Credit is real money**
>
> Set limits for customers you do not know well, and check the **Owing** list regularly (section 12).

12. Customers, payments and statements

Go to `Manage` → **Customers**. The top shows the total owed to the shop and how many customers owe. Use the **Owing** filter to see only debtors. Tap a customer to open them; the **Account** tab shows **Owes**, **Credit limit**, **Available** and a dated **Statement**.

Receiving a payment

1. On the customer's **Account** tab, tap `Receive payment`. The full amount owed is filled in; change it for a part payment.
2. Choose `Cash`, `Transfer`, `Card` or `Mobile money`. For anything but cash, enter the **Payment reference**. Add a **Note** if useful.
3. Tap `Receive ...`. Cash payments need an open register; they are added to the cash expected in the drawer.
4. The **Payment recorded** panel shows the receipt number (e.g. PAY-00001), previous balance, amount paid and balance owed. Tap `Print` or `Send (WhatsApp)`, then `Done`.

To print or send an old payment receipt again, tap the payment in the **Statement**.

Tap `Share statement` to send the customer a full statement of credit sales, payments and balance by WhatsApp or SMS.

What the receipts look like

MAMA NKECHI PROVISIONS
12 Market Road, Ibadan
Tel: 0803 123 4567

Receipt	TAB1-00042
Date	12/10/2026 14:05
Served by	Bisi
Customer	Mama Tunde
Rice 5kg	
2 x N9,500	N19,000
Groundnut oil 1L	
1 x N3,000	N3,000
TOTAL	**N22,000**
Cash	N12,000
On account	N10,000
Account balance	**N35,000**

Thank you for shopping with us

Sale receipt with a customer

MAMA NKECHI PROVISIONS
12 Market Road, Ibadan
Tel: 0803 123 4567

PAYMENT RECEIPT

Receipt	PAY-00007
Date	12/10/2026 16:40
Received by	Bisi
Customer	Mama Tunde
Previous balance	N35,000
PAID	**N20,000**
Method	Transfer
Ref	TRF-5521
Balance owed	**N15,000**

Thank you for shopping with us

Payment receipt

13. Sales history and voiding a sale

Tap **Sales** to see today's sales, newest first. Tap a sale to see its items and payments, and to **Print receipt** or **Send (WhatsApp)** again.

Voiding a sale (owner or manager)

If a sale was rung up wrongly, open it, tap **Void sale**, enter the **Reason for voiding** (e.g. “Wrong item rung up”) and confirm. The app:

- puts the items back into stock,
- takes any credit part off the customer's account,
- keeps the sale on record marked **Voided**, with who voided it, when and why.

Voided sales are never deleted, so the history always adds up.

14. New stock, expiry dates and expenses

When goods arrive from a supplier, record them so your quantities stay correct.

1. Go to **Manage** → **Inflow** and tap **Record inflow**.
2. Optional: enter the **Supplier** and the **Invoice / waybill no.**
3. Use **Find a product to add** for each product received. Enter the **Quantity received** and, if you know it, the **Cost per unit**.
4. Leave **Update products' cost price** on if the new cost should replace the old one.
5. Tap **Record inflow**. Each delivery gets a number such as INF-00012 and the quantities go up at once.

Entered something twice? Open the inflow, tap **Cancel inflow** and give a reason. The quantities are taken back out and the inflow stays on record as **Cancelled**.

Expiry dates and clearance (near-expiry discount)

When recording an inflow, set the **Expiry date** printed on each product's delivery (you can also set it for a new product's opening stock, or when receiving stock on a product). Each delivery is kept as a **batch**; the app works out how many units of each batch are left, assuming the oldest are sold first.

1. Go to **Manage** → **Expiring**. It lists batches expiring within **7**, **30**, **60** or **90** days (or already expired), with the units left.
2. An owner or manager taps a batch to **Put on clearance**. Type the **Percent off** (e.g. 30) and the **Clearance price** updates, or type the price and see the percent.
3. **Units on clearance** is filled in with what is left of that batch; **Clearance ends on** with its expiry date. Tap **Start clearance**.

At the till, the product shows a **Clearance** badge. Those units are sold first at the clearance price (receipts mark them "clearance"); once they are gone, or after the end date, the normal price comes back by itself. Cashiers can sell clearance units even if they are not allowed to give discounts. To change or end it, use **Change** on the Expiring screen, or the product's **Expiry** tab.

Recording expenses

Record money the shop spends (fuel, transport, repairs, nylon bags, rent…) under **Manage** → **Expenses** (owners and managers).

1. Tap **+ Expense**. Enter the **Amount**, choose a **Category** and say **What was it for?** Add **Paid to** if useful.
2. Under **How was it paid?** choose **Cash**, **Transfer**, **Card** or **Mobile money**. For anything but cash you can add the **Payment reference**.
3. For cash, leave **Paid from the till drawer** on if the money came out of the register: it is taken off the expected cash, so the drawer still balances at closing. Turn it off if the cash came from elsewhere (e.g. the owner's pocket).
4. Tap **Save**. Each expense gets a number such as EXP-00007.

The Expenses screen shows what was spent **Today**, **This week** or **This month**, split by payment method and category; **Share** sends the list. Tap an expense to see it, or **Void** it with a reason if it was entered by mistake.

15. Stock report

Tap **Reports**. Choose a period (**Today**, **Yesterday**, **This week**, **This month**) or pick your own **From** and **To** dates.

Column	Meaning
Opening	Quantity at the start of the period.
Out	Quantity that left: sales and removals.
In	Quantity that came in: inflows, returns and additions.
Closing	Quantity at the end of the period (Opening − Out + In).

- Turn on **Moved only** to hide products that did not move in the period.
- Use **Filter products** to find a product or category.
- Tap `Share` to send the report as a spreadsheet file (CSV) that opens in Excel or Google Sheets.

> **Check your stock regularly**
>
> Compare the **Closing** figure with what is really on the shelf. If they differ, correct the count on the product (section 6) with a reason such as “Counted”.

16. Setting up a receipt printer

Ajoke POS prints on most Bluetooth thermal receipt printers (58 mm or 80 mm).

1. Switch the printer on and load paper.
2. On the phone, open Android **Settings** → **Bluetooth**, find the printer and pair it. The PIN is often **0000** or **1234**; see the printer's manual.
3. In Ajoke POS, open `Backup` → **Receipt printer**, or tap the printer icon on any receipt screen.
4. Under **Connection** choose `Bluetooth (paired)` and pick your printer. If it does not appear, try `Bluetooth LE (scan)`.
5. Choose the **Paper width**: `58 mm (small)` or `80 mm (wide)`.
6. Tap `Print test page`. If it looks right, you are ready.

Setting	What it does
Print automatically after each sale	Prints the receipt as soon as a sale is completed.
Open cash drawer on cash sales	For drawers connected to the printer: opens the drawer on cash sales and cash payments.
Forget printer	Removes the printer so you can choose another.

Nothing prints?

- Check the printer is on, has paper, and is not connected to another phone.
- Allow the app's **Nearby devices** / Bluetooth permission when Android asks. If you refused it, go to Android **Settings** → **Apps** → **Ajoke POS** → **Permissions**.
- Switch the printer off and on, then try `Print test page` again.
- You can always `Send (WhatsApp)` the receipt instead.

17. Business details and logo

The owner can change these under `Manage` → **Business**:

- **Business name**, **Phone number** and **Address**: shown at the top of every receipt.
- **Logo**: tap `Choose logo` and pick a picture from the gallery. A simple logo on a white background prints best. Turn **Print logo on receipts** off if your printer is slow or the logo prints badly.
- **VAT %**, **Service charge %** and the payment methods you accept.
- **Receipt footer**: a line at the bottom of receipts, e.g. “No refund after payment. Thank you!”
- **Allow cashiers to give discounts**: switch on to let cashiers change prices at the till too. Owners and managers always can.

Tap `Save settings`. A preview shows how the top of your receipt will look.

18. Close the register

At the end of the day (or end of each shift), count the cash and close the register.

1. Tap **Register**. The screen shows the **Opening float**, **Cash sales on this device**, **Customer payments (cash)**, **Expenses paid from drawer** and the **Expected cash in drawer**.
2. Count the cash in the drawer and enter it under **Counted cash**.
3. The app shows **Balanced**, **Over** or **Short** and by how much. Add a **Note (optional)** to explain any difference.
4. Tap **Close register**.

Past shifts lists earlier shifts with who opened and closed them and any difference. Card, transfer and mobile money payments are not in the drawer, so they are not part of the expected cash.

19. Backup and moving to a new device

> **Your records live only on this device**
>
> If the phone is lost, stolen or broken and you have no backup, the records are gone. Make a backup **at least once a week**; the app reminds you after 7 days.

Make a backup

1. Tap **Backup** → **Back up now**.
2. The first time, set a **backup password** (at least 6 characters) and type it twice. It locks your backup files so customer details stay private. **Write it down**: you need it to restore on a new phone. The phone remembers it, so later backups do not ask again.
3. The share menu opens with the backup file. Save it somewhere **off the phone**: Google Drive, email it to yourself, or send it to your own WhatsApp.

Restore on a new or repaired device

1. Install Ajoke POS on the new device and activate it with a new activation code (section 3).
2. On the setup screen choose **This device only**, then tap **Restore from a backup file instead**, pick your latest backup file and enter your backup password.
3. Sign in with your usual PIN. Products, staff, customers, balances and sales are all back.

> **Forgot the backup password?**
>
> Send the backup file to Ajoke Code Sphere (+234 803 415 0437). After checking you are the owner, they can unlock it and send it back with a new password. To change your password, tap **Change backup password** on the Backup screen, then make a new backup.

On a device already in use, **Backup** → **Restore from backup file** replaces everything on it with the backup. **Erase this device** deletes everything; make a backup first.

20. Problems and answers

Problem	What to do
“Open the register before selling”	Go to **Register** and open it with the opening float (section 8).
Forgot a staff PIN	The owner opens **Manage** → **Staff**, taps the person and sets a new PIN.
Owner forgot their PIN	If there is a second owner, they set a new PIN in **Manage** → **Staff**. Otherwise see “Forgot your PIN?” in section 5.
“Credit limit exceeded”	The customer would owe more than their limit. Take more payment now, or ask an owner/manager to raise or clear the limit.
“… is set to cash only”	The customer's credit limit is 0. An owner/manager can clear it (blank = no limit).
Cash payment refused: “Open the register…”	Cash payments go into the drawer, so the register must be open. Open it, or record the payment as Transfer/Card with a reference.
Expected cash looks wrong	Check **Customer payments (cash)** on the Register screen and any voided sales in **Sales**.
Receipt picture will not send	Make sure WhatsApp is installed and try again, or use **Send as text**.
Printer not found / not printing	See “Nothing prints?” in section 16.
Product shows wrong quantity	Check the product's stock history, then correct with Received (+) / Remove (−) and a reason.
Licence expired or new phone	Send your device code to Ajoke Code Sphere for a new activation code. Your records are kept.

Good habits

- Every staff member signs in with their own PIN, and taps **Lock** when leaving the counter.
- Always enter the payment reference for transfers and POS card payments.
- Record every delivery under Inflow on the day it arrives.
- Close the register every day and look into any difference straight away.
- Back up every week, and keep the backup off the phone.
- Do not uninstall the app to update it; install the new version over the old one.