在Windows上安裝Unified Manager

Active IQ Unified Manager

NetApp
May 05, 2022

This PDF was generated from https://docs.netapp.com/zh-tw/active-iq-unified-manager/install-windows/task_install_unified_manager_on_windows.html on May 05, 2022. Always check docs.netapp.com for the latest.

目錄

在Windows上安裝Unified Manager 1
安裝Unified Manager 1
執行Unified Manager的無人值守安裝 2

在Windows上安裝Unified Manager

請務必瞭解在Windows上下載及安裝Unified Manager的步驟順序。

安裝Unified Manager

您可以安裝Unified Manager來監控和疑難排解資料儲存容量、可用度、效能和保護問題。

您需要的是什麼

- 您打算安裝Unified Manager的系統應符合系統和軟體需求。

  "硬體系統需求"

  "Windows軟體與安裝需求"

  > 從Unified Manager 9.5開始、OpenJDK會隨附於安裝套件中、並會自動安裝。不支援從Unified Manager 9.5開始使用Oracle Java。

- 您應該擁有Windows系統管理員權限。請確定您的使用者名稱開頭沒有驚嘆號「！」。如果執行安裝的使用者名稱開頭為「！」、Unified Manager安裝可能會失敗。
- 您應該擁有支援的網頁瀏覽器。
- Unified Manager維護使用者密碼應介於8到20個字元之間、且應包含大寫字母或大小寫字母、數字和特殊字元。
- 對於維護使用者或MySQL root使用者、密碼字串中不允許使用下列特殊字元：「"%、=&<>|^\/（）[]；：

  允許使用下列特殊字元：~！@#$*-？。+ {}

步驟

1. 使用預設的本機系統管理員帳戶登入Windows。
2. 登入NetApp支援網站、然後瀏覽至Unified Manager的下載頁面：

   "NetApp 支援網站"

3. 選取所需的Unified Manager版本、並接受終端使用者授權合約（EULA）。
4. 將Unified Manager Windows安裝檔案下載至Windows系統上的目標目錄。
5. 瀏覽至安裝檔案所在的目錄。
6. 以系統管理員身分按一下滑鼠右鍵並執行Unified Manager安裝程式執行檔（.exe）。

   Unified Manager會偵測遺失或預先安裝的協力廠商套件、並列出這些套件。如果系統中未安裝所需的協力廠商套件、Unified Manager會在安裝過程中安裝這些套件。

7. 單擊 * 下一步 * 。
8. 輸入使用者名稱和密碼以建立維護使用者。

9. 在Database Connection（資料庫連線）精靈中、輸入MySQL根密碼。
10. 按一下「變更」以指定Unified Manager安裝目錄和MySQL資料目錄的新位置。

    如果您未變更安裝目錄、Unified Manager會安裝在預設安裝目錄中。

11. 單擊 * 下一步 * 。
12. 在Ready to Install Shield精靈中、按一下* Install*。
13. 安裝完成後、按一下*「Finish」（完成）*。
14. 如果您的Windows系統上安裝了作用中的防毒軟體、請在安裝完成後、手動將下列路徑排除在防毒掃描之外：
    - Unified Manager資料目錄
    - Unified Manager安裝目錄
    - MySQL資料目錄

安裝會建立多個目錄：

- 安裝目錄

  這是您在安裝期間指定的Unified Manager根目錄。範例：「C:\Program Files\NetApp\」

- MySQL資料目錄

  這是您在安裝期間指定的MySQL資料庫儲存目錄。範例：「C：\ProgramData\MySQL\MySQLServerData\」

- Java目錄

  這是安裝OpenJDK的目錄。範例：「C:\Program Files\NetApp\JDK\」

- Unified Manager應用程式資料目錄（appDataDir)

  這是儲存所有應用程式產生資料的目錄。這包括記錄、支援套裝組合、備份及所有其他額外資料。範例：「C：\ProgramData\NetApp\OnCommandAppData\」

您可以存取Web UI來執行Unified Manager的初始設定、如所述 "《系統組態指南》Active IQ Unified Manager"。

執行Unified Manager的無人值守安裝

您可以使用命令列介面來安裝Unified Manager、而無需使用者介入。您可以在金鑰值配對中傳遞參數、以完成無人值守安裝。

步驟

1. 使用預設的本機系統管理員帳戶登入Windows命令列介面。
2. 瀏覽至您要安裝Unified Manager的位置、然後選擇下列其中一個選項：

選項	說明
如果已預先安裝協力廠商套件	「ActiveIQUnifiedManager-x.y.exe /V"MySQL_password=mySQL_password INSTALLDIR=\"安裝目錄\" MySQL_data_DIR=\"MySQL資料目錄\" maintening_password=maintenance maintening_username=maintening_username/qn /l*v完整路徑記錄檔"」 範例： 「ActiveIQUnifiedManager.exe /s /v"MySQL_password=netapp21 ！INSTALLDIR=\"C:\Program Files\NetApp\" MySQL_data_DIR=\"C ：\ProgramData\MySQL\MySQLServer\" maintening_password=# **maintenation_username=admin /qn /l** v C ：\install.log"
如果未安裝協力廠商套件	「ActiveIQUnifiedManager-x.y.exe /V"MySQL_password=mySQL_password INSTALLDIR=\"安裝目錄\" MySQL_data_DIR=\"MySQL資料目錄\" maintening_password=maintenance maintening_username=maintening_username/QR /l*v完整路徑檔案"」 範例： 「ActiveIQUnifiedManager.exe /s /v"MySQL_password=netapp21 ！INSTALLDIR=\"C:\Program Files\NetApp\" MySQL_data_DIR=\"C ：\ProgramData\MySQL\MySQLServer\" maintening_password=# **maintenance**使用者名稱**= admin /QR /l** v C：\install.log

「/QR」選項可透過精簡的使用者介面來啟用無模式。隨即顯示基本使用者介面、顯示安裝進度。系統不會提示您輸入資料。如果未預先安裝任何第三方套件、例如：JREE、MySQL和7Zip、您應該使用「/QR」選項。如果在未安裝協力廠商套件的伺服器上使用「/qn」選項、安裝將會失敗。

「/qn」選項可在無使用者介面的情況下啟用「Quiet」模式。安裝期間不會顯示使用者介面或詳細資料。若未安裝協力廠商套件、則不應使用「/qn」選項。

3. 使用下列URL登入Unified Manager Web使用者介面：

   https://IP位址

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.