啟用多因素驗證

Element Software

NetApp
May 18, 2022

This PDF was generated from https://docs.netapp.com/zh-tw/element-software-123/storage/task_system_manage_mfa_set_up_multi_factor_authentication.html on May 18, 2022.
Always check docs.netapp.com for the latest.

目錄

啟用多因素驗證 1
設定多因素驗證 1
多因素驗證的其他資訊 1

啟用多因素驗證

多因素驗證（MFA）透過安全聲明標記語言（SAML）使用第三方身分識別供應商（IDP）來管理使用者工作階段。MFA可讓系統管理員視需要設定其他驗證因素、例如密碼和文字訊息、密碼和電子郵件訊息。

設定多因素驗證

您可以透過Element API使用這些基本步驟、將叢集設定為使用多因素驗證。

如需每種API方法的詳細資料、請參閱 "Element API參考"。

1. 透過呼叫下列API方法並以Json格式傳遞IDP中繼資料、為叢集建立新的協力廠商身分識別供應商（IDP）組態：「Create IdpConfiguration」（建立IdpConfiguration）

   IDP中繼資料以純文字格式從第三方IDP擷取。此中繼資料必須經過驗證、以確保其在Json中正確格式化。您可以使用許多Json格式化板應用程式、例如：https://freeformatter.com/json-escape.html。

2. 透過spmetadata Url擷取叢集中繼資料、以呼叫下列API方法複製到第三方IDP：「ListIdpConfigurations」

   SpMetadataUrl是一個URL、用於從叢集擷取IDP的服務供應商中繼資料、以建立信任關係。

3. 在協力廠商IDP上設定SAML斷言、以納入「NameID」屬性、以唯一識別使用者進行稽核記錄、並讓「單一登出」正常運作。
4. 建立一或多個由協力廠商IDP驗證的叢集管理員使用者帳戶、以取得授權、方法是呼叫下列API方法：「AddIdpClusterAdmin」

   > IDP叢集管理員的使用者名稱應與SAML屬性名稱/值對應相符、以取得所需的效果、如下列範例所示：

   - email=bob@company.com -其中IDP已設定為在SAML屬性中釋出電子郵件地址。
   - Group=cluster系統管理員：其中IDP設定為釋放所有使用者應有存取權的群組內容。請注意、為了安全起見、SAML屬性名稱/值配對區分大小寫。
5. 若要為叢集啟用MFA、請呼叫下列API方法：「EnabIIdpAuthentication」

如需詳細資訊、請參閱

- "「元件與元素資源」頁面SolidFire"
- "vCenter Server的VMware vCenter外掛程式NetApp Element"

多因素驗證的其他資訊

您應該瞭解下列有關多因素驗證的注意事項。

- 若要重新整理不再有效的IDP憑證、您必須使用非IDP管理使用者來呼叫下列API方法：「更新IdpConfiguration」

- MFA與長度小於2048位元的憑證不相容。根據預設、會在叢集上建立一個2048位元SSL憑證。在呼叫API方法「etSSLCertificate」時、您應該避免設定較小的憑證

> 如果叢集使用的憑證在升級前低於2048位元、則叢集憑證必須在升級至Element 12或更新版本之後、以2048位元或更高的憑證進行更新。

- IDP管理使用者無法直接（例如透過SDK或Postman）撥打API呼叫、也無法用於其他整合（例如OpenStack Cinder或vCenter外掛程式）。如果您需要建立具有這些功能的使用者、請新增LDAP叢集管理使用者或本機叢集管理使用者。

如需詳細資訊、請參閱

- "使用Element API管理儲存設備"
- "「元件與元素資源」頁面SolidFire"
- "vCenter Server的VMware vCenter外掛程式NetApp Element"

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.