ユーザクラスタで Trident のサポートを有効にします

HCI

Michael Wallis, Aksel Davis
June 21, 2021

This PDF was generated from https://docs.netapp.com/ja-jp/hci/docs/task_trident_configure_networking.html on July 01, 2021. Always check docs.netapp.com for the latest.

目次

ユーザクラスタで Trident のサポートを有効にします 1

ユーザクラスタで Trident のサポートを有効にします

NetApp HCI 環境の管理ネットワークとストレージネットワークの間にルートがなく、Trident のサポートが必要なユーザクラスタを導入する場合は、 Trident のインストール後にユーザクラスタネットワークをさらに設定する必要があります。各ユーザクラスタについて、管理ネットワークとストレージネットワークの間の通信を有効にする必要があります。これを行うには、ユーザクラスタ内の各ノードのネットワーク設定を変更します。

ユーザクラスタ内の各ノードのネットワーク設定を変更するには、次の一般的な手順を実行します。次の手順では、 NetApp HCI に Rancher をインストールしたデフォルトノードテンプレートを使用してユーザクラスタを作成したものとします。

これらの変更をカスタムノードテンプレートの一部として追加すると、以降のユーザクラスタで使用できるようになります。

手順

1. 既存のデフォルトテンプレートを使用してユーザクラスタを導入する。
2. ストレージネットワークをユーザクラスタに接続
   a. 接続されている vCenter インスタンスの VMware vSphere Web Client を開きます。
   b. ホストおよびクラスタインベントリツリーで、新しく導入したユーザクラスタ内のノードを選択します。
   c. ノードの設定を編集します。
   d. 設定ダイアログで、新しいネットワークアダプタを追加します。
   e. [新しいネットワーク *] ドロップダウン・リストで、ネットワークを参照し、 [* HCI _ 内部 _ ストレージ _ データ _ ネットワーク *] を選択します。
   f. [ネットワークアダプタ] セクションを展開し、新しいネットワークアダプタの MAC アドレスを記録します。
   g. [OK] をクリックします。
3. rancher で、ユーザクラスタ内の各ノードの SSH 秘密鍵ファイルをダウンロードします。
4. ダウンロードした秘密鍵ファイルを使用して、ユーザクラスタ内のノードに SSH を使用して接続します。

   ```
   ssh -i <private key filename> <ip address>
   ```

5. スーパーユーザーとして '/etc/netplan/50-cloud-init.yaml ファイルを編集して保存し ' 次の例のように ens224' セクションが含まれるようにします「 <MAC アドレス >` 」を、前に記録した MAC アドレスに置き換えます。

```
network:
    ethernets:
        ens192:
            dhcp4: true
            match:
                macaddress: 00:50:56:91:1d:41
            set-name: ens192
        ens224:
            dhcp4: true
            match:
                macaddress: <MAC address>
            set-name: ens224
    version: 2
```

6. 次のコマンドを使用して、ネットワークを再設定します。

```
`netplan try`
```

7. ユーザクラスタの残りのノードについて、手順 4~6 を繰り返します。
8. ユーザクラスタ内の各ノードのネットワークを再設定したら、 Trident を利用するユーザクラスタにアプリケーションを導入できます。

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.