Create a file share

NetApp Keystone

Manini Mandal, Ciaran McNamara, David Peterson, Reenu Jojo
April 29, 2021

This PDF was generated from https://docs.netapp.com/us-en/keystone/sewebiug_create_a_new_file_share.html on June 11, 2021. Always check docs.netapp.com for the latest.

Table of Contents

Create a file share 1

Create a file share

This section describes how to create a new share by directly specifying the share details. To create a new share based on a Snapshot of an existing share, see Create Share from Snapshot.

Before you begin

- A share is created on a file server. The file server must exist and be in an operational state before you can create a new file share.
- For creating a CIFS or NFS file share, the server must be enabled for the respective service. For a multi-protocol file shares, the server should support both CIFS and NFS services.
- To enable asynchronous disaster recovery options for the share, you must create the share on a server that has asynchronous disaster recovery enabled. For more information, see Disaster recovery.
- To enable synchronous disaster recovery for a share, create the share in a zone that is MetroCluster-enabled.
- You can define a backup policy to capture backups of the file share on a scheduled basis. For more information, see Backups.
- You can define a Snapshot policy to capture Snapshots of the file share on a scheduled basis. For more information, see Snapshots.

Steps

1. Go to **FILE SERVICES > Shares**.
2. Click **Create Share**.
3. In the Create Share dialog box, select Create New Share.



The Create Share page is displayed.

4. Select the share type: NFS, CIFS, or Multi-protocol. The options are enabled based on the services that your server supports.
5. Complete the following fields:

Field	Description
Name	Enter the share name.
Share Path	Enter the path for the file share. For CIFS shares, adding a $ character to the end of the share path will make it a hidden share (for example, pathtomyhiddenshare$).
Region	Select the region in which the share resides.
Zone	Select the zone of the share.
File Server	Select the file server to host the share. The list of the file server depends on the region, zone, and share type selected.
Security Style	Select the security style applicable to the file share. This list is automatically populated based on the share type selected.

6. Select a Performance Service Level. The IOPS and throughput limits are displayed based on the service level selected.

> Select an option to view the performance details for that level (as peak/expected IOPS/throughput). Select the service level that best matches your needs.

7. Specify the capacity of the file share.

> NetApp Service Engine displays a warning and the capacity bar changes color if the specified capacity puts the consumed capacity into burst (or even more into burst if it is already in burst). The capacity check is performed against the total capacity for all subscriptions in the tenancy.

8. If asynchronous disaster recovery is enabled on the underlying file server, asynchronous disaster recovery replication is automatically enabled for the new share. If you wish to exclude the share from asynchronous disaster recovery replication, toggle the Asynchronous Disaster Recovery button so that it is disabled.
9. If the share is being created in a zone that is MetroCluster-enabled, the Synchronous Disaster Recovery button is automatically enabled and cannot be disabled. The share will be replicated to the zone displayed in the panel below the Synchronous Disaster Recovery toggle.
10. If Snapshots are required for this file share:
    a. Toggle to enable the Snapshot Policy and view the Snapshot Policy fields.
    b. Specify when to create the Snapshots:
        - **Hourly.** Specify which minute (of the hour) to take Snapshot and the number of hourly Snapshots to retain.
        - **Daily.** Specify when (hour and minute) to take the Snapshot the number of daily Snapshots to retain. If you want to specify multiple hours when the Snapshot has to be taken daily, you can add the values of the hours in a comma-separated list, for example, 5, 10, 15, and so forth.
        - **Weekly.** Specify when (day of the week, hour, and minute) to take Snapshot and the number of weekly Snapshots to retain.
        - **Monthly.** Specify when (day of the month, hour, and minute) to take Snapshot and the number of monthly Snapshots to retain.

11. To enable backups for this file share:
    a. Toggle to enable the Backup Policy and the Backup Policy fields.
    b. Specify the backup zone.
    c. Specify how many of each type of backup to keep: daily, weekly, and/or monthly.
12. For NFS or multi-protocol shares, specify the Export Policy. You can apply multiple export policies on a share. This section is available for only NFS and multi-protocol shares.
    a. Add the IPv4 address (with a subnet mask expressed as a number of bits) of the client to which the rule applies.
    b. Specify the read and write access, and whether the client has root access (superuser).
13. For a CIFS (SMB) or multi-protocol shares, specify the Access Control List (ACL) for restricting user access. This section is available for only CIFS and multi-protocol shares.
    a. Specify the Windows user or group based on the Active Directory (AD) settings to add to the ACL. If you specify the user name, include the user's domain in the `<domain>\<username>` format. The default value is `Everyone`.
    b. Specify the Windows permission. The default value is `Full control`. If a user is a part of two groups, the permissions of the group that has higher privileges get applied on the user's access.

> The user or group name should follow the standard AD format. If the entered user or group does not match the user or user group configured on ONTAP, the ACL validation fails during a CIFS operation, even when the file share is operational.

14. If you want to add tags (key-value pairs) to the file share, specify them in the Tags section.
15. Click **Create**. This creates a job to create the share.

After you finish

- For CIFs type shares only: to make the shares available by host name, your domain administrator must update the DNS records with the CIFS server name and IP address. Otherwise, the share is only accessible through the IP address. For example:
    - With DNS records updated, use either the host name or IP to access the share: such as \\hostname\share or \\IP\share
    - With no DNS records updated, you must use the IP address to access the share i.e. \\IP\share
- Create share is run as an asynchronous job. You can:
    - Check the status of the job in the jobs list.
    - After the job is finished, check the status of the share in the Shares list.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.