Setting up and adding Azure accounts to Cloud Manager

Cloud Manager 3.7

Aksel Davis, Ben Cammett
April 22, 2020

This PDF was generated from https://docs.netapp.com/us-en/occm37/task_adding_azure_accounts.html on April 22, 2020. Always check docs.netapp.com for the latest.

Table of Contents

Setting up and adding Azure accounts to Cloud Manager 1
Granting Azure permissions using a service principal 1
Adding Azure accounts to Cloud Manager 7
Associating additional Azure subscriptions with a managed identity 8

Setting up and adding Azure accounts to Cloud Manager

If you want to deploy Cloud Volumes ONTAP in different Azure accounts, then you need to provide the required permissions to those accounts and then add details about the accounts to Cloud Manager.

> When you deploy Cloud Manager from Cloud Central, Cloud Manager automatically adds the Azure account in which you deployed Cloud Manager. An initial account is not added if you manually installed the Cloud Manager software on an existing system. Learn about Azure accounts and permissions.

Granting Azure permissions using a service principal

Cloud Manager needs permissions to perform actions in Azure. You can grant the required permissions to an Azure account by creating and setting up a service principal in Azure Active Directory and by obtaining the Azure credentials that Cloud Manager needs.

About this task

The following image depicts how Cloud Manager obtains permissions to perform operations in Azure. A service principal object, which is tied to one or more Azure subscriptions, represents Cloud Manager in Azure Active Directory and is assigned to a custom role that allows the required permissions.



Steps

1. Create an Azure Active Directory application.
2. Assign the application to a role.
3. Add Windows Azure Service Management API permissions.
4. Get the application ID and directory ID.
5. Create a client secret.

Creating an Azure Active Directory application

Create an Azure Active Directory (AD) application and service principal that Cloud Manager can use for role-based access control.

Before you begin

You must have the right permissions in Azure to create an Active Directory application and to assign the application to a role. For details, refer to Microsoft Azure Documentation: Required permissions.

Steps

1. From the Azure portal, open the **Azure Active Directory** service.



2. In the menu, click **App registrations**.
3. Click **New registration**.
4. Specify details about the application:
   - **Name**: Enter a name for the application.
   - **Account type**: Select an account type (any will work with Cloud Manager).
   - **Redirect URI**: Select **Web** and then enter any URL—for example, https://url
5. Click **Register**.

Result

You’ve created the AD application and service principal.

Assigning the application to a role

You must bind the service principal to one or more Azure subscriptions and assign it the custom "OnCommand Cloud Manager Operator" role so Cloud Manager has permissions in Azure.

Steps

1. Create a custom role:
   a. Download the Cloud Manager Azure policy.
   b. Modify the JSON file by adding Azure subscription IDs to the assignable scope.

      You should add the ID for each Azure subscription from which users will create Cloud Volumes ONTAP systems.

      Example

```
"AssignableScopes": [
"/subscriptions/d333af45-0d07-4154-943d-c25fbzzzzzzz",
"/subscriptions/54b91999-b3e6-4599-908e-416e0zzzzzzz",
"/subscriptions/398e471c-3b42-4ae7-9b59-ce5bbzzzzzzz"
```

c. Use the JSON file to create a custom role in Azure.

   The following example shows how to create a custom role using the Azure CLI 2.0:

   az role definition create --role-definition C:\Policy_for_cloud_Manager_Azure_3.7.4.json

   You should now have a custom role called *OnCommand Cloud Manager Operator*.

2. Assign the application to the role:

   a. From the Azure portal, open the **Subscriptions** service.

   b. Select the subscription.

   c. Click **Access control (IAM)** > **Add** > **Add role assignment**.

   d. Select the **OnCommand Cloud Manager Operator** role.

   e. Keep **Azure AD user, group, or service principal** selected.

   f. Search for the name of the application (you can't find it in the list by scrolling).



   g. Select the application and click **Save**.

   The service principal for Cloud Manager now has the required Azure permissions for that subscription.

   If you want to deploy Cloud Volumes ONTAP from multiple Azure subscriptions, then you must bind the service principal to each of those subscriptions. Cloud Manager enables you to select the subscription that you want to use when deploying Cloud Volumes ONTAP.

Adding Windows Azure Service Management API permissions

The service principal must have "Windows Azure Service Management API" permissions.

Steps

1. In the **Azure Active Directory** service, click **App registrations** and select the application.
2. Click **API permissions** > **Add a permission**.
3. Under **Microsoft APIs**, select **Azure Service Management**.



4. Click **Access Azure Service Management as organization users** and then click **Add permissions**.



Getting the application ID and directory ID

When you add the Azure account to Cloud Manager, you need to provide the application (client) ID and the directory (tenant) ID for the application. Cloud Manager uses the IDs to programmatically sign in.

Steps

1. In the **Azure Active Directory** service, click **App registrations** and select the application.
2. Copy the **Application (client) ID** and the **Directory (tenant) ID**.



Creating a client secret

You need to create a client secret and then provide Cloud Manager with the value of the secret so Cloud Manager can use it to authenticate with Azure AD.

When you add the account to Cloud Manager, Cloud Manager refers to the client secret as the Application Key.

Steps

1. Open the **Azure Active Directory** service.
2. Click **App registrations** and select your application.
3. Click **Certificates & secrets** > **New client secret**.
4. Provide a description of the secret and a duration.
5. Click **Add**.
6. Copy the value of the client secret.

Result

Your service principal is now setup and you should have copied the application (client) ID, the directory (tenant) ID, and the value of the client secret. You need to enter this information in Cloud Manager when you add an Azure account.

Adding Azure accounts to Cloud Manager

After you provide an Azure account with the required permissions, you can add the account to Cloud Manager. This enables you to launch Cloud Volumes ONTAP systems in that account.

Steps

1. In the upper right of the Cloud Manager console, click the Settings icon, and select **Cloud Provider & Support Accounts**.



2. Click **Add New Account** and select **Microsoft Azure**.
3. Enter information about the Azure Active Directory service principal that grants the required permissions:
   - Application ID: See Getting the application ID and directory ID.
   - Tenant ID (or Directory ID): See Getting the application ID and directory ID.
   - Application Key (the client secret): See Creating a client secret.

4. Confirm that the policy requirements have been met and then click **Create Account**.

Result

You can now switch to another account from the Details and Credentials page when creating a new working environment:



Associating additional Azure subscriptions with a managed identity

Cloud Manager enables you to choose the Azure account and subscription in which you want to deploy Cloud Volumes ONTAP. You can't select a different Azure subscription for the managed identity profile unless you associate the managed identity with those subscriptions.

About this task

A managed identity is the initial Azure account when you deploy Cloud Manager from NetApp Cloud Central. When you deployed Cloud Manager, Cloud Central created the OnCommand Cloud Manager Operator role and assigned it to the Cloud Manager virtual machine.

Steps

1. Log in to the Azure portal.
2. Open the **Subscriptions** service and then select the subscription in which you want to deploy Cloud

Volumes ONTAP systems.

3. Click **Access control (IAM)**.
   a. Click **Add** > **Add role assignment** and then add the permissions:
      - Select the **OnCommand Cloud Manager Operator** role.

        OnCommand Cloud Manager Operator is the default name provided in the Cloud Manager policy. If you chose a different name for the role, then select that name instead.

      - Assign access to a **Virtual Machine**.
      - Select the subscription in which the Cloud Manager virtual machine was created.
      - Select the Cloud Manager virtual machine.
      - Click **Save**.
4. Repeat these steps for additional subscriptions.

Result

When you create a new working environment, you should now have the ability to select from multiple Azure subscriptions for the managed identity profile.



Copyright Information

Copyright © 2019–2020 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.