# Manage an event destination instance

ONTAP 9.6 REST API reference

NetApp
February 13, 2024

This PDF was generated from https://docs.netapp.com/us-en/ontap-restapi-96/ontap/support_ems_destinations_name_endpoint_overview.html on February 13, 2024. Always check docs.netapp.com for the latest.

# Table of Contents

Manage an event destination instance . . . 1
Support EMS destinations name endpoint overview . . . 1
Delete an event destination . . . 2
Retrieve an event destination . . . 4
Update an event destination . . . 8

# Manage an event destination instance

## Support EMS destinations name endpoint overview

### Overview

Manages a specific instance of a destination. There are limits to the information that can be modified once a destination is created. For example, a destination's type cannot be changed but the underlying details of the type can be modified. See the documentation for /support/ems/destinations for details on the various fields in a destination.

### Examples

#### Retrieving a specific destination instance

```
# API
GET /api/support/ems/destinations/snmp-traphost

# Response
200 OK

# JSON Body
{
"name": "snmp-traphost",
"type": "snmp",
"destination": "",
"filters": [
  {
    "name": "default-trap-events",
    "_links": {
      "self": {
        "href": "/api/support/ems/filters/default-trap-events"
      }
    }
  }
],
"_links": {
  "self": {
    "href": "/api/support/ems/destinations/snmp-traphost"
  }
}
}
```

#### Updating an existing destination (change of e-mail address)

```
# API
PATCH /api/support/ems/destinations/test-destination

# JSON Body
{
"destination": "support@mycompany.com"
}

# Response
200 OK
```

#### Deleting an existing destination

```
# API
DELETE /api/support/ems/destinations/test-destination

# Response
200 OK
```

# Delete an event destination

DELETE `/support/ems/destinations/{name}`

Deletes an event destination.

## Related ONTAP commands

- `event notification destination delete`
- `event notification delete`

## Learn more

- DOC /support/ems/destinations/{name}

## Parameters

| Name | Type | In | Required | Description |
|---|---|---|---|---|
| name | string | path | True | |

## Response

```
Status: 200, Ok
```

## Error

```
Status: Default
```

ONTAP Error Response Codes

| Error Code | Description |
|---|---|
| 983152 | Default destinations cannot be modified or removed |

| Name | Type | Description |
|---|---|---|
| error | error | |

**Example error**

```
{
  "error": {
    "arguments": {
      "code": "string",
      "message": "string"
    },
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

## Definitions

**See Definitions**

error_arguments

| Name | Type | Description |
|---|---|---|
| code | string | Argument code |
| message | string | Message argument |

error

| Name | Type | Description |
|---|---|---|
| arguments | array[error_arguments] | Message arguments |
| code | string | Error code |
| message | string | Error message |
| target | string | The target parameter that caused the error. |

# Retrieve an event destination

GET `/support/ems/destinations/{name}`

Retrieves event destinations.

## Related ONTAP commands

- `event notification destination show`
- `event notification show`

## Learn more

- DOC /support/ems/destinations/{name}

## Parameters

| Name | Type | In | Required | Description |
|---|---|---|---|---|
| name | string | path | True | Destination name |
| fields | array[string] | query | False | Specify the fields to return. |

## Response

```
Status: 200, Ok
```

| Name | Type | Description |
|---|---|---|
| _links | _links | |
| certificate | certificate | Certificate information is valid for the "rest_api" type. |
| destination | string | Event destination |
| filters | array[filters] | |
| name | string | Destination name. Valid in POST. |
| type | string | Type of destination. Valid in POST. |

### Example response


```
{
  "_links": {
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "certificate": {
    "ca": "VeriSign",
    "serial_number": 1234567890
  },
  "destination": "<a href="
mailto:administrator@mycompany.com">administrator@mycompany.com</a>",
  "filters": {
    "_links": {
      "self": {
        "href": "/api/resourcelink"
      }
    },
    "name": "important-events"
  },
  "name": "Admin_Email",
  "type": "email"
}
```

## Error

```
Status: Default, Error
```

| Name | Type | Description |
|---|---|---|
| error | error | |

### Example error

```
{
  "error": {
    "arguments": {
      "code": "string",
      "message": "string"
    },
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

## Definitions

**See Definitions**

href

| Name | Type | Description |
|---|---|---|
| href | string | |

_links

| Name | Type | Description |
|---|---|---|
| self | href | |

certificate

Certificate information is valid for the "rest_api" type.

| Name | Type | Description |
|---|---|---|
| ca | string | Client certificate issuing CA |
| serial_number | string | Client certificate serial number |

filters

| Name | Type | Description |
|---|---|---|
| _links | _links | |
| name | string | |

error_arguments

| Name | Type | Description |
|---|---|---|
| code | string | Argument code |
| message | string | Message argument |

error

| Name | Type | Description |
|---|---|---|
| arguments | array[error_arguments] | Message arguments |
| code | string | Error code |
| message | string | Error message |

| Name | Type | Description |
| --- | --- | --- |
| target | string | The target parameter that caused the error. |

# Update an event destination

PATCH `/support/ems/destinations/{name}`

Updates an event destination.

## Recommended optional properties

- `filters.name` - New list of filters that should direct to this destination. The existing list is discarded.
- `certificate` - New certificate parameters when the destination type is `rest api`.

## Related ONTAP commands

- `event notification destination modify`
- `event notification modify`

## Learn more

- DOC /support/ems/destinations/{name}

## Parameters

| Name | Type | In | Required | Description |
| --- | --- | --- | --- | --- |
| name | string | path | True | Destination name |

## Request Body

| Name | Type | Description |
| --- | --- | --- |
| _links | _links | |
| certificate | certificate | Certificate information is valid for the "rest_api" type. |
| destination | string | Event destination |
| filters | array[filters] | |
| name | string | Destination name. Valid in POST. |
| type | string | Type of destination. Valid in POST. |

**Example request**

```
{
  "_links": {
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "certificate": {
    "ca": "VeriSign",
    "serial_number": 1234567890
  },
  "destination": "<a href="
mailto:administrator@mycompany.com">administrator@mycompany.com</a>",
  "filters": {
    "_links": {
      "self": {
        "href": "/api/resourcelink"
      }
    },
    "name": "important-events"
  },
  "name": "Admin_Email",
  "type": "email"
}
```

## Response

```
Status: 200, Ok
```

| Name | Type | Description |
|---|---|---|
| _links | _links | |
| certificate | certificate | Certificate information is valid for the "rest_api" type. |
| destination | string | Event destination |
| filters | array[filters] | |
| name | string | Destination name. Valid in POST. |
| type | string | Type of destination. Valid in POST. |

**Example response**

```
{
  "_links": {
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "certificate": {
    "ca": "VeriSign",
    "serial_number": 1234567890
  },
  "destination": "<a href="
mailto:administrator@mycompany.com">administrator@mycompany.com</a>",
  "filters": {
    "_links": {
      "self": {
        "href": "/api/resourcelink"
      }
    },
    "name": "important-events"
  },
  "name": "Admin_Email",
  "type": "email"
}
```

## Error

```
Status: Default
```

ONTAP Error Response Codes

| Error Code | Description |
|---|---|
| 983088 | The destination name provided cannot be empty |
| 983089 | The destination name provided cannot contain spaces |
| 983094 | The destination name provided is invalid. The destination name must contain between 2 and 64 characters and start and end with an alphanumeric symbol or _(underscore). The allowed special characters are _(underscore) and -(hyphen) |
| 983104 | The syslog destination provided is invalid |

| Error Code | Description |
| --- | --- |
| 983116 | The number of notifications has reached maximum capacity |
| 983117 | The number of destinations has reached maximum capacity |
| 983129 | The rest-api destination must contain a valid scheme, such as http// or https// |
| 983130 | The rest-api destination provided contains an invalid URL |
| 983131 | The rest-api destination provided contains an invalid IPv6 URL |
| 983142 | The security certificate provided does not exist |
| 983143 | The private security key provided does not exist |
| 983144 | The security certificate information provided is incomplete. Provide the certificate and serial number |
| 983145 | The rest-api destination provided has an 'http://' scheme. It is invalid to provide certificate information |
| 983150 | The type of an existing destination cannot be changed |
| 983151 | A property provided cannot be configured on the requested destination type |
| 983152 | Default destinations cannot be modified or removed |

| Name | Type | Description |
| --- | --- | --- |
| error | error | |

**Example error**

```
{
  "error": {
    "arguments": {
      "code": "string",
      "message": "string"
    },
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

## Definitions

**See Definitions**

href

| Name | Type | Description |
|---|---|---|
| href | string | |

_links

| Name | Type | Description |
|---|---|---|
| self | href | |

certificate

Certificate information is valid for the "rest_api" type.

| Name | Type | Description |
|---|---|---|
| ca | string | Client certificate issuing CA |
| serial_number | string | Client certificate serial number |

filters

| Name | Type | Description |
|---|---|---|
| _links | _links | |
| name | string | |

ems_destination

| Name | Type | Description |
|---|---|---|
| _links | _links | |
| certificate | certificate | Certificate information is valid for the "rest_api" type. |
| destination | string | Event destination |
| filters | array[filters] | |
| name | string | Destination name. Valid in POST. |
| type | string | Type of destination. Valid in POST. |

error_arguments

| Name | Type | Description |
| --- | --- | --- |
| code | string | Argument code |
| message | string | Message argument |

error

| Name | Type | Description |
| --- | --- | --- |
| arguments | array[error_arguments] | Message arguments |
| code | string | Error code |
| message | string | Error message |
| target | string | The target parameter that caused the error. |

**Copyright information**

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

**Trademark information**

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.