SnapLock ボリュームを移動

ONTAP 9

NetApp
February 28, 2022

This PDF was generated from https://docs.netapp.com/ja-jp/ontap/snaplock/create-snaplock-security-administrator-account-task.html on February 28, 2022. Always check docs.netapp.com for the latest.

目次

SnapLock ボリュームを移動 1
SnapLock セキュリティ管理者アカウントを作成します 1
SnapLock ボリュームを移動 1

SnapLock ボリュームを移動

SnapLock セキュリティ管理者アカウントを作成します

SnapLock の移動を実行するには、 SnapLock セキュリティ管理者の権限が必要です。この権限は、 ONTAP 9.8 で導入された _ SnapLock _ ロールで付与されます。このロールが割り当てられていない場合は、クラスタ管理者に、この SnapLock セキュリティロールを持つ SnapLock セキュリティユーザの作成を依頼してください。

必要なもの

- このタスクを実行するには、クラスタ管理者である必要があります。
- セキュアな接続（ SSH 、コンソール、または ZAPI ）でログインする必要があります。

SnapLock ロールは、データ SVM に関連付けられる vsadmin-snaplock ロールとは異なり、クラスタ SVM に関連付けられています。

ステップ

1. SnapLock 管理者ロールを持つ SVM 管理者アカウントを作成します。

   「 * security login create -vserver *svm_name* _ user-or -group-name_user_or_group_name *application* -authmethod *authentication_method*-role *role*-comment_*`

   次のコマンドは、事前定義された「 SnapLock 」ロールを持つ SVM 管理者アカウント「 S napLockAdmin 」がパスワードを使用して「 S VM2 」にアクセスできるようにします。

   ```
   cluster1::> security login create -vserver SVM2 -user-or-group-name
   SnapLockAdmin -application ssh -authmethod password -role snaplock
   ```

SnapLock ボリュームを移動

「 volume move 」コマンドを使用して、 SnapLock ボリュームをデスティネーションアグリゲートに移動できます。

必要なもの

- SnapLock ボリュームの移動を実行する前に、 SnapLock で保護された監査ログを作成しておく必要があります。

  "監査ログを作成します"。

- ONTAP 9.10.1 より前のバージョンの ONTAP を使用している場合は、デスティネーションアグリゲートの SnapLock タイプが、 Compliance から Compliance へ、または Enterprise から Enterprise への移動対象の SnapLock ボリュームと同じである必要があります。ONTAP 9.10.1 以降ではこの制限が解除され、Compliance SnapLock と Enterprise の両方のボリューム、および SnapLock 以外のボリュームをアグリゲートに含めることができます。
- SnapLock セキュリティロールを持つユーザである必要があります。

手順

1. セキュアな接続を使用して、 ONTAP クラスタ管理 LIF にログインします。

   'ssh snaplock_user@node_mgmt_ip'

2. SnapLock ボリュームを移動します。

   ` * volume move start -vserver_svm_name_-volume_snaplock_volume_name — destination -aggregate_destination_aggregate-name_*`

3. ボリューム移動処理のステータスを確認します。

   `* volume move show -volume` *`snaplock_volume_name`* `−` *`vserver_svm_name`* `-fields volume 、 phase 、 vserver *`

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.