使用 SMB 共享 ACL 确保文件访问安全

ONTAP 9

NetApp
July 13, 2022

This PDF was generated from https://docs.netapp.com/zh-cn/ontap/smb-admin/manage-smb-level-acls-concept.html on July 13, 2022. Always check docs.netapp.com for the latest.

目录

使用 SMB 共享 ACL 确保文件访问安全 1
管理 SMB 共享级 ACL 的准则 1
创建 SMB 共享访问控制列表 1
用于管理 SMB 共享访问控制列表的命令 3

使用 SMB 共享 ACL 确保文件访问安全

管理 SMB 共享级 ACL 的准则

您可以更改共享级 ACL ，为用户授予对共享的或多或少的访问权限。您可以使用 Windows 用户和组或 UNIX 用户和组配置共享级 ACL 。

默认情况下，创建共享后，共享级 ACL 会为名为 Everyone 的标准组授予读取访问权限。ACL 中的读取访问权限意味着域和所有受信任域中的所有用户都对共享具有只读访问权限。

您可以使用 Windows 客户端上的 Microsoft 管理控制台（ MMC ）或 ONTAP 命令行更改共享级别 ACL 。

使用 MMC 时，请遵循以下准则：

- 指定的用户名和组名必须为 Windows 名称。
- 您只能指定 Windows 权限。

使用 ONTAP 命令行时，请遵循以下准则：

- 指定的用户和组名称可以是 Windows 名称或 UNIX 名称。

  如果在创建或修改 ACL 时未指定用户和组类型，则默认类型为 Windows 用户和组。

- 您只能指定 Windows 权限。

创建 SMB 共享访问控制列表

通过为 SMB 共享创建访问控制列表（ ACL ）来配置共享权限，可以控制用户和组对共享的访问级别。

您可以使用本地或域 Windows 用户或组名称或 UNIX 用户或组名称来配置共享级 ACL 。

在创建新 ACL 之前，应删除默认共享 ACL `Everyone / Full Control` ，这会带来安全风险。

在工作组模式下，本地域名为 SMB 服务器名称。

步骤

1. 删除默认共享 ACL ：`vserver cifs share access-control delete -vserver` *`vserver_name`* `-share` *`share_name`* `-user-or-group everyone`
2. 配置新 ACL ：

如果要使用配置 **ACL**，请使用 ...	输入命令 ...
Windows 用户	`vserver cifs share access-control create -vserver` *`vserver_name`* `-share` *`share_name`* `-user-group-type windows -user-or-group` *`windows_domain_name`*`\\`*`user_name`* `-permission _access_right_s`
Windows 组	`vserver cifs share access-control create -vserver` *`vserver_name`* `-share` *`share_name`* `-user-group-type windows -user-or-group` *`windows_group_name`* `-permission _access_right_s`
UNIX 用户	`vserver cifs share access-control create -vserver` *`vserver_name`* `-share` *`share_name`* `-user-group-type` *`unix-uster`* `-user-or-group` *`unix_user_name`* `-permission access_right`
UNIX 组	`vserver cifs share access-control create -vserver` *`vserver_name`* `-share` *`share_name`* `-user-group-type` *`unix-group`* `-user-or-group` *`unix_group_name`* `-permission access_right`

3. 使用 `vserver cifs share access-control show` 命令验证应用于共享的 ACL 是否正确。

以下命令为 "`vs1.example.com`"SVM: 上的 `sSales` 共享向 `SSales` Windows 组提供 `Change` 权限

```
cluster1::> vserver cifs share access-control create -vserver
vs1.example.com -share sales -user-or-group "Sales Team" -permission
Change

cluster1::> vserver cifs share access-control show
                 Share       User/Group              User/Group  Access
Vserver          Name        Name                    Type
Permission
---------------- ----------- --------------------    ---------
-----------
vs1.example.com  c$          BUILTIN\Administrators  windows
Full_Control
vs1.example.com  sales       DOMAIN\"Sales Team"     windows     Change
```

以下命令为 "`vs2.example.com`"SVM: 上 "`eng` " 共享的 "`engineering` "UNIX 组提供 `Read` 权限

```
cluster1::> vserver cifs share access-control create -vserver
vs2.example.com -share eng -user-group-type unix-group -user-or-group  eng
-permission Read

cluster1::> vserver cifs share access-control show
                 Share       User/Group                User/Group  Access
Vserver          Name        Name                      Type
Permission
---------------- ----------- -------------------       -----------
-----------
vs2.example.com  c$          BUILTIN\Administrators    windows
Full_Control
vs2.example.com  eng         engineering               unix-group  Read
```

以下命令为 `vs1 SVM 上的 datavol5 共享向名为 "`Tiger Team` " 的本地 Windows 组提供 Change 权限，并为名为 Sual_Control 的本地 Windows 用户提供权限`：

```
cluster1::> vserver cifs share access-control create -vserver vs1 -share
datavol5 -user-group-type windows -user-or-group "Tiger Team" -permission
Change

cluster1::> vserver cifs share access-control create -vserver vs1 -share
datavol5 -user-group-type windows -user-or-group "Sue Chang" -permission
Full_Control

cluster1::> vserver cifs share access-control show -vserver vs1
               Share       User/Group                   User/Group  Access
Vserver        Name        Name                         Type
Permission
-------------- ----------- ---------------------------- -----------
-----------
vs1            c$          BUILTIN\Administrators       windows
Full_Control
vs1            datavol5    DOMAIN\"Tiger Team"          windows     Change
vs1            datavol5    DOMAIN\"Sue Chang"           windows
Full_Control
```

用于管理 SMB 共享访问控制列表的命令

您需要了解用于管理 SMB 访问控制列表（ACL）的命令，其中包括创建，显示，修改和删除这些列表。

如果您要 ...	使用此命令 ...
创建新的 ACL	`vserver cifs share access-control create`
显示 ACL	`vserver cifs share access-control show`
修改 ACL	`vserver cifs share access-control modify`
删除 ACL	`vserver cifs share access-control delete`

版权信息

版权所有©2022 NetApp、Inc.。保留所有权利。Printed in the U.S.版权所涵盖的本文档的任何部分不得以任何形式或任何手段复制、包括影印、录制、 磁带或存储在电子检索系统中—未经版权所有者事先书面许可。

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

本软件由NetApp按"原样"提供、不含任何明示或默示担保、包括但不限于适销性和特定用途适用性的默示担保、特此声明不承担任何责任。IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice.NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp.The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S.patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

商标信息

NetApp、NetApp标识和中列出的标记 http://www.netapp.com/TM 是NetApp、Inc.的商标。其他公司和产品名称可能是其各自所有者的商标。